

EDB Postgres Distributed (PGD)

Version 5.10.0

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Built at 2026-11-20T11:50:52

1 EDB Postgres Distributed (PGD) 8
2 EDB Postgres Distributed 5 release notes 9
2.1 EDB Postgres Distributed 5.10.0 release notes 10
2.2 EDB Postgres Distributed 5.9.5 release notes 16
2.3 EDB Postgres Distributed 5.9.4 release notes 21
2.4 EDB Postgres Distributed 5.9.3 release notes 23
2.5 EDB Postgres Distributed 5.9.2 release notes 24
2.6 EDB Postgres Distributed 5.9.1 release notes 27
2.7 EDB Postgres Distributed 5.9.0 release notes 30
2.8 EDB Postgres Distributed 5.8.1 release notes 32
2.9 EDB Postgres Distributed 5.8.0 release notes 34
2.10 EDB Postgres Distributed 5.7.0 release notes 37
2.11 EDB Postgres Distributed 5.6.1 release notes 41
2.12 EDB Postgres Distributed 5.6.0 release notes 43
2.13 EDB Postgres Distributed 5.5.1 release notes 48
2.14 EDB Postgres Distributed 5.5.0 release notes 49
2.15 EDB Postgres Distributed 5.4.1 release notes 51
2.16 EDB Postgres Distributed 5.4.0 release notes 52
2.17 EDB Postgres Distributed 5.3.0 release notes 54
2.18 EDB Postgres Distributed 5.2.0 release notes 56
2.19 EDB Postgres Distributed 5.1.0 release notes 58
2.20 EDB Postgres Distributed 5.0.1 release notes 60
2.21 EDB Postgres Distributed 5.0.0 release notes 61
3 Known issues 63
4 PGD compatibility 65
5 Terminology 66
6 PGD overview 70
6.1 Architecture overview 71
6.2 PGD overview - architecture and performance 74
6.3 PGD compared 76
7 Introducing PGD quick starts 78
7.1 Deploying an EDB Postgres Distributed example cluster on Docker 80
7.2 Deploying an EDB Postgres Distributed example cluster on Linux hosts 85
7.3 Deploying an EDB Postgres Distributed example cluster on AWS 92
7.4 Deploying an EDB Postgres Distributed example cluster on Azure and Google cloud platforms
7.5 Connecting to your database 9998
7.6 Exploring replication with PGD 103
7.7 Exploring failover handling with PGD 107
7.8 Exploring conflict handling with PGD 115
7.9 Next steps with PGD 120
8 Planning your PGD deployment 121
8.1 Choosing your architecture 122
8.2 Choosing a Postgres distribution 126
8.3 Choosing your deployment method 127
8.4 Other considerations 128
8.5 Limitations 129
9 Deploying and configuring EDB Postgres Distributed 131
9.1 Manual deployment and configuration of PGD 132

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1 Deploying PGD manually 133
9.1.1.1 Step 1 - Provisioning hosts 134
9.1.1.2 Step 2 - Installing Postgres 136
9.1.1.3 Step 3 - Configuring PGD repositories 137
9.1.1.4 Step 4 - Installing the PGD software 139
9.1.1.5 Step 5 - Creating the PGD cluster 145
9.1.1.6 Step 6 - Checking the cluster 148
9.1.1.7 Step 7 - Configure proxies 152
9.1.1.8 Step 8 - Using PGD CLI 157
9.2 Deployment and management with TPA 161
9.2.1 Deploying PGD using TPA 162
9.2.1.1 Configuring a PGD cluster with TPA 163
9.2.1.2 Provisioning, deploying, and testing 166
9.3 Deploying and configuring PGD on Kubernetes 167
9.4 Deploying and configuring PGD on EDB Postgres AI Cloud Service 168
10 Application use 169
10.1 Application behavior 170
10.2 DML and DDL replication and nonreplication 173
10.3 Nodes with differences 174
10.4 General rules for applications 176
10.5 Timing considerations and synchronous replication 177
10.6 Using extensions with PGD 178
10.7 Use of table access methods (TAMs) in PGD 180
10.8 Feature compatibility 181
11 DDL replication 182
11.1 DDL overview 183
11.2 DDL replication options 185
11.3 DDL locking details 186
11.4 Managing DDL with PGD replication 188
11.5 DDL command handling matrix 190
11.6 DDL and role manipulation statements 199
11.7 Workarounds for DDL restrictions 200
11.8 PGD functions that behave like DDL 202
12 Sequences 203
13 Node management 210
13.1 Creating PGD nodes 211
13.2 Groups and subgroups 213
13.3 Creating and joining PGD groups 214
13.4 Viewing PGD topology 215
13.5 Removing nodes and groups 217
13.6 Joining a heterogeneous cluster 218
13.7 Connection DSNs and SSL (TLS) 219
13.8 Replication slots created by PGD 220
13.9 Node restart and down node recovery 222
13.10 Maintenance commands through proxies 223
14 Connection Manager 226
14.1 Connection Manager overview 227
14.2 Connection Manager Authentication 230

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

14.3 Configuring Connection Manager 232
14.4 Load Balancing with Connection Manager 233
14.5 Monitoring the Connection Manager 235
15 Postgres configuration 237
16 PGD Proxy 239
16.1 EDB Postgres Distributed Proxy overview 240
16.2 Installing PGD Proxy 243
16.3 PGD Proxy configuration 246
16.4 Administering PGD Proxy 248
16.5 Monitoring PGD Proxy 249
16.6 Read-only routing with PGD Proxy 251
16.7 Proxies, Raft, and Raft subgroups 254
16.7.1 Creating Raft subgroups using TPA 255
16.7.2 Working with Raft subgroups and PGD CLI 258
16.7.3 Migrating to Raft subgroups 259
16.7.4 Raft elections in depth 260
17 Backup and recovery 262
18 Security and roles 268
18.1 Roles 269
18.2 Role management 270
18.3 PGD predefined roles 272
18.4 Roles and replication 275
18.5 Access control 276
19 Monitoring 278
19.1 OpenTelemetry integration 279
19.2 Monitoring through SQL 282
20 Testing and tuning PGD clusters 293
21 Upgrading 295
21.1 Upgrading PGD clusters with TPA 296
21.2 Upgrading PGD clusters manually 298
21.3 Supported PGD upgrade paths 303
21.4 Compatibility changes 304
21.5 Application schema upgrades 305
21.6 In-place Postgres or Postgres and PGD major version upgrades 306
21.7 Performing a Postgres major version rolling upgrade on a PGD cluster 310
22 Data migration to EDB Postgres Distributed 322
22.1 EDB*Loader and PGD 323
23 EDB Postgres Distributed Command Line Interface (PGD CLI) 324
23.1 Installing PGD CLI 325
23.1.1 Installing PGD CLI on Linux 326
23.1.2 Installing PGD CLI on macOS 328
23.1.3 Installing PGD CLI with TPA 329
23.2 Using PGD CLI 330
23.3 Configuring PGD CLI 333
23.4 Discovering connection strings 335
23.5 Command reference 338
23.5.1 pgd assess 340
23.5.2 pgd cluster 341

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.2.1 pgd cluster show 342
23.5.2.2 pgd cluster verify 344
23.5.3 pgd commit-scope 347
23.5.3.1 pgd commit-scope create 348
23.5.3.2 pgd commit-scope drop 350
23.5.3.3 pgd commit-scope show 351
23.5.3.4 pgd commit-scope update 352
23.5.4 pgd completion 353
23.5.5 pgd events 354
23.5.5.1 pgd events show 355
23.5.6 pgd group 357
23.5.6.1 pgd group show 358
23.5.6.2 pgd group set-option 361
23.5.6.3 pgd group get-option 363
23.5.6.4 pgd group set-leader 365
23.5.7 pgd groups 366
23.5.7.1 pgd groups list 367
23.5.8 pgd node 368
23.5.8.1 pgd node get-option 369
23.5.8.2 pgd node set-option 371
23.5.8.3 pgd node show 372
23.5.8.4 pgd node upgrade 374
23.5.9 pgd nodes 376
23.5.9.1 pgd nodes list 377
23.5.10 pgd raft 379
23.5.10.1 pgd raft show 380
23.5.11 pgd replication 381
23.5.11.1 pgd replication show 382
24 Node types and capabilities 384
24.1 An overview of PGD Node types 385
24.2 Witness nodes 386
24.3 Logical standby nodes 387
24.4 Subscriber-only nodes and groups 388
24.4.1 An overview of Subscriber-only nodes 389
24.4.2 Creating Subscriber-only groups and nodes 390
24.4.3 Joining nodes to a Subscriber-only group 391
24.4.4 Optimizing subscriber-only groups 392
25 Commit Scopes 394
25.1 Overview of durability options 395
25.2 Durability terminology 396
25.3 Commit scopes 397
25.4 Origin groups 400
25.5 Commit scope rules 402
25.6 Comparing durability options 404
25.7 Degrading commit scope rules 406
25.8 Synchronous Commit 408
25.9 Group Commit 409
25.10 Commit At Most Once 413

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.11 Lag Control 419
25.12 Administering 422
25.13 Legacy synchronous replication using PGD 423
25.14 Limitations 425
25.15 Internal timing of operations 427
26 Conflict Management 428
26.1 Conflicts 429
26.1.1 Overview 430
26.1.2 Types of Conflict 432
26.1.3 Conflict detection 441
26.1.4 Conflict resolution 443
26.1.5 Conflict logging 444
26.1.6 Data verification with LiveCompare 445
26.2 Column-level conflict detection 446
26.2.1 Overview 447
26.2.2 Enabling and disabling column-level conflict resolution 449
26.2.3 Timestamps in column-level conflict resolution 451
26.3 Conflict-free replicated data types 453
26.3.1 CRDTs Overview 454
26.3.2 Using CRDTs 455
26.3.3 Operation-based and state-based CRDTs 458
26.3.4 CRDT Disk-space requirements 459
26.3.5 CRDTs vs conflict handling/reporting 460
26.3.6 Resetting CRDT values 461
26.3.7 Implemented CRDTs 462
27 Parallel Apply 469
28 Replication sets 471
29 Stream triggers 480
30 PGD AutoPartition 486
31 Explicit two-phase commit (2PC) 489
32 Decoding worker 490
33 Transaction streaming 492
34 Timestamp-based snapshots 495
35 CDC Failover support 496
36 PGD reference 500
36.1 User visible catalogs and views 511
36.2 System functions 542
36.3 PGD settings 564
36.4 Node management 575
36.5 Node management interfaces 578
36.6 Routing functions 590
36.7 Commit scopes 593
36.8 Conflicts 599
36.9 Conflict functions 602
36.10 Replication set management 605
36.11 Replication set membership 608
36.12 DDL replication filtering 610
36.13 Testing and tuning commands 612

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.14 Global sequence management interfaces 615
36.15 Autopartition 622
36.16 Stream triggers reference 626
36.16.1 Stream triggers manipulation interfaces 627
36.16.2 Stream triggers row functions 629
36.16.3 Stream triggers row variables 631
36.17 Internal catalogs and views 632
36.18 Internal system functions 639
36.19 Column-level conflict functions 649

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

1 EDB Postgres Distributed (PGD)

EDB Postgres Distributed (PGD) provides multi-master replication and data distribution with advanced conflict management, data-loss protection, and throughput up to 5X faster than native logical replication. It enables distributed Postgres clusters with high availability up to five 9s.

Read about why PostgreSQL is better when it's distributed with EDB Postgres Distributed in Distributed PostgreSQL:The Key to Always On Database Availability
PGD Free Trial
Contact Sales

By default, EDB Postgres Distributed uses asynchronous replication, applying changes on the peer nodes only after the local commit. You can configure additional levels of synchronicity between different nodes, groups of nodes, or all nodes by configuring Synchronous Commit, Group Commit (optionally with Eager Conflict Resolution), or CAMO.

Compatibility

EDB Postgres Distributed 5 is compatible with PostgreSQL, EDB Postgres Extended, and EDB Postgres Advanced versions 13-17. See Compatibility for more details, including information about compatibility with different operating systems and architectures. For feature compatibility with compatible servers, see Choosing a Postgres distribution.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2 EDB Postgres Distributed 5 release notes

The EDB Postgres Distributed documentation describes the latest version of EDB Postgres Distributed 5, including minor releases and patches. The release notes provide information on what was new in each release. For new functionality introduced in a minor or patch release, the content also indicates the release that introduced the feature.

Release Date	EDB Postgres Distributed	BDR extension	PGD CLI	PGD Proxy
19 Nov 2026	5.10.0	5.10.0	5.10.0	5.10.0
20 Aug 2026	5.9.5	5.9.5	5.9.5	5.9.5
26 May 2026	5.9.4	5.9.4	5.9.4	5.9.4
15 Apr 2026	5.9.3	5.9.3	5.9.3	5.9.3
26 Mar 2026	5.9.2	5.9.2	5.9.2	5.9.2
05 Dec 2025	5.9.1	5.9.1	5.9.1	5.9.1
19 Aug 2025	5.9.0	5.9.0	5.9.0	5.9.0
25 Jun 2025	5.8.1	5.8.1	5.8.1	5.8.1
22 May 2025	5.8.0	5.8.0	5.8.0	5.8.0
25 Feb 2025	5.7.0	5.7.0	5.7.0	5.7.0
25 Nov 2024	5.6.1	5.6.1	5.6.1	5.6.1
15 Oct 2024	5.6.0	5.6.0	5.6.0	5.6.0
31 May 2024	5.5.1	5.5.1	5.5.0	5.5.0
16 May 2024	5.5.0	5.5.0	5.5.0	5.5.0
03 April 2024	5.4.1	5.4.1	5.4.0	5.4.0
05 March 2024	5.4.0	5.4.0	5.4.0	5.4.0
14 November 2023	5.3.0	5.3.0	5.3.0	5.3.0
04 August 2023	5.2.0	5.2.0	5.2.0	5.2.0
16 May 2023	5.1.0	5.1.0	5.1.0	5.1.0
21 Mar 2023	5.0.1	5.0.0	5.0.1	5.0.1
21 Feb 2023	5.0.0	5.0.0	5.0.0	5.0.0

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.1 EDB Postgres Distributed 5.10.0 release notes

Released: 19 November 2026

EDB Postgres Distributed 5.10.0 includes an enhancement and bug fixes focused on improving stability and reliability. For a list of known issues, seeKnown issues and limitations.

Highlights

- Raft PreVote: PreVote, introduced in PGD 6, is now backported to PGD 5. A node isolated by an unstable network link no longer forces a Raft leader election when it reconnects, so a healthy leader isn't displaced and clusters recover from network flapping without disruption. No configuration is required. PreVote takes effect once all nodes run PGD 5.10 and applies to the top-level group.

Enhancements

Component	Version	Description	Addresses
BDR	5.10.0	Backported Raft PreVote from PGD 6 to prevent unnecessary Raft leader elections. A node that was isolated by a flapping network link no longer forces a Raft leader election when it reconnects. PreVote needs no configuration and takes effect once all nodes run PGD 5.10. In PGD 5.10.0, it applies only to the Raft instance of the top-level group.	
BDR	5.10.0	Connection Manager now says which server closed a connection during the handshake. When a Postgres server closed the connection before the startup handshake or the SCRAM exchange had completed, Connection Manager logged `connection failed: ProtocolError("")`. The `WARNING` now names the server address and the handshake phase, and shows the error as text (`protocol error: ...`) rather than in its internal form.	60716

Security Fixes

Component	Version	Description
BDR	5.10.0	Updated the FIPS cryptographic module of Connection Manager to AWS-LC FIPS 3.6.0.

Changes

Component	Version	Description
BDR	5.10.0	Connection Manager now follows the `ssl` setting for client connections. Connection Manager now offers TLS to clients only when `ssl` is on, as Postgres does. Before, it offered TLS whenever `ssl_cert_file` and `ssl_key_file` pointed to existing files, whatever `ssl` was set to. With `ssl` on, both files must be set. If clients connect to Connection Manager over TLS, set `ssl = on` before upgrading. The HTTPS status port (`use_https`) isn't affected and keeps using `ssl_cert_file` and `ssl_key_file` whatever `ssl` is set to.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Bug Fixes

Component	Version	Description	Addresses
BDR	5.10.0	Fixed a hard hang between a writer and the receiver in CAMO. A receiver restart, for example after the origin node was partitioned and then recovered, could hang when the downstream node had CAMO transactions in its commit decisions. The receiver waited on a flush while the writers waited for the full commit decision feedback queues that the receiver never emptied. The deadlock detector didn't detect this hang, and only a server restart resolved it. This issue has been present since 5.9.1.	65610
BDR	5.10.0	Fixed a misdirected signal from the writer that could restart an instance in a container. After a flush, the writer woke the receiver with a `kill()` call whose two arguments were swapped. On a normal host the call failed, since receiver PIDs are larger than the highest signal number, and the receiver waited up to 1 s for the flush confirmation unless something else woke it. In a container or another fresh PID namespace, the call could hit a Postgres process: with a receiver at PID 24, the writer sent signal 24 (`SIGXCPU`) to the checkpointer at PID 10, and the postmaster restarted the instance. The writer now wakes the receiver with the arguments in order, and only after it has confirmed the flush.	66414
BDR	5.10.0	Fixed the Raft term of exported consensus snapshots. `bdr.consensus_snapshot_export()` labeled a snapshot with the node's current Raft term instead of the term of the last entry the snapshot includes. After an election the two differ. Nodes that imported such a snapshot then disagreed with the exporting node about that entry, and when the exporting node was elected leader again, the Raft group committed no entries until the next snapshot sync. Snapshots now carry the term of their last entry.	
BDR	5.10.0	Fixed the loss of a committed Raft entry when the first node joins a Raft group. A Raft leader treated a node added while it was leader as silent until the node's first response. When the first node to join a Raft group became a voter before the leader's first heartbeat, the leader stepped down without having sent a heartbeat. The joining nodes then elected a leader with an empty log while the old leader held a committed entry, and that entry was truncated. The leader now counts a node it adds as heard from, as it does for the nodes present at its election.	
PGD CLI	5.10.0	Fixed `pgd node upgrade` restoring replication origins at the wrong position. `pgd node upgrade` restores each replication origin at the highest progress of its writer origins, but its patterns for the writer origins didn't match their names: - An origin whose ID contains a hex letter lost its writer origins and was restored behind them. - An origin could take the progress of another origin's writers (origin `0x2` matched the writers of `0x21`). Its subscription then started ahead in the wrong peer's WAL and skipped transactions. - A writer origin without recorded progress was taken as the furthest ahead. - The origins of a database whose name starts with `writer` weren't restored at all. The writer origins are now matched by their exact names.	
BDR	5.10.0	Fixed missing replication slots for witness nodes after concurrent joins. Witnesses skipped join serialization, though they need slots in both directions. A witness joining concurrently with other nodes could end up without some slots, breaking later operations such as node parting. Witnesses are now serialized like data nodes.	
BDR	5.10.0	Fixed a hang when a writer restarts while a global lock is held. If a writer or a node restarted after a global lock was acquired (after `ACQUIRE` or `ACQUIRE FINISH` , or after DDL had committed or prepared but before the lock was released), the manager or the writer doing DDL could hang forever. Locks recovered after a restart are now rebuilt without re-acquiring them, writers for the lock's origin are let through, and `FINISH` and `RELEASE` are routed to the same writer.	
BDR	5.10.0	Fixed `update_recently_deleted` conflicts detected as `update_missing` . An update to a recently deleted row could be classified as `update_missing` , so the default `insert_or_skip` resolver inserted the deleted row again. The conflict is now detected correctly.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.10.0	Fixed a memory leak in CAMO transactions. Fixed a memory leak where every commit under a CAMO commit scope leaked a small buffer in the backend's top memory context. On long-lived connections, such as pooled connections to the write leader, the leak caused unbounded memory growth and could lead to out-of-memory conditions. The same leak on the commit error path for other commit scopes that use group commit is also fixed.	65147
BDR	5.10.0	Fixed conflict detection for EXCLUDE constraints over an index expression. Conflicts on an EXCLUDE constraint that indexes an expression, for example a `tstzrange(time_from, time_to)` column, weren't detected. The writer failed with a plain `23P01` error and retried until it exited, no conflict was logged to `bdr.conflict_history`, the configured conflict resolver wasn't used, and replication from that peer was blocked. Conflict detection now supports EXCLUDE constraints over an index expression, and these conflicts are resolved like other EXCLUDE conflicts.	
BDR	5.10.0	Fixed the receiver skipping cleanup when it exits with a broken upstream connection. When a receiver exited gracefully while its upstream connection was already broken, sending standby status or CAMO feedback raised an `ERROR` inside the exit callback. That unwound out of the finish function and skipped writer cleanup, closing the connection, and the remaining exit callbacks. During process exit, these failures are now logged as warnings and the cleanup runs to completion.	
BDR	5.10.0	Lag values in `bdr.node_slots` are no longer reset when a peer reconnects. During the catch-up phase, the `write_lag`, `flush_lag`, and `replay_lag` fields in `bdr.node_slots` now report the calculated `offline_lag` until the slot goes back to the streaming state and lag can be measured again, instead of being reset to 0.	57149
BDR	5.10.0	Prevented DDL from creating galloc sequences with the `CYCLE` option. The `CYCLE` option on galloc sequences could cause duplicate `nextval()` values across nodes. PGD now prevents DDL that results in a galloc sequence with the `CYCLE` option, unless it's replicated DDL from another node.	
PGD CLI	5.10.0	PGD CLI now honors `ssl_password_command` from its configuration file. The `cluster.ssl.ssl_password_command` setting in `pgd-cli-config.yml` was accepted but ignored, so an obfuscated `sslpassword` failed with "bad decrypt" for users without a libpq deobfuscation preload, such as `root`. The CLI again runs the command with `sslpassword` on standard input and uses its output as the passphrase. Passwords are no longer shown in `--debug` output.	
BDR	5.10.0	Fixed a corrupted slot name in `bdr.node_local_info` after concurrent joins. In the promote step of a node join, PGD kept a pointer to a short-lived copy of the replication slot name, and a later update of `bdr.node_local_info` wrote whatever that memory held by then. After concurrent joins, a row could hold a truncated slot name followed by garbage bytes, and the replication slot checks then failed. PGD now keeps its own copy of the name.	
BDR	5.10.0	Fixed switching between `bdr.raft_election_timeout` and `bdr.raft_global_election_timeout`. `bdr.raft_election_timeout` is a deprecated alias of `bdr.raft_global_election_timeout`, and only one of the two can be set. Replacing one name by the other in the configuration file failed on every reload until a restart: the postmaster shut down, and in other processes the statement that processed the reload failed. Meanwhile the node ran with the default timeout. With both names in the configuration file, the server didn't start. Now: • A conflicting line in the configuration file is logged and skipped, at startup and on reload. On a reload the name already in effect wins; at startup, `bdr.raft_global_election_timeout`. • One reload applies an edit of the file that replaces one name by the other. • `ALTER SYSTEM` still refuses to set the second name. `RESET` the first one and reload before you set it. • Raft applies a new timeout at the next consensus restart, as before.	66284

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.10.0	Fixed walsender failures during an upgrade from PGD 4.4 with subscriber-only nodes. While the extension was being upgraded from 4.4.x, a walsender started for a subscriber-only node's slot looked up `bdr.failover_replication_slots` before the upgrade script had created it, and `START_REPLICATION` failed. PGD now treats the missing catalog as no failover slot.	
BDR	5.10.0	Fixed PGD worker processes missing a change to PGD's internal catalogs. When a transaction changed PGD's internal catalogs, PGD notified the Connection Manager, router and manager worker processes at commit, before it had published the change to the catalog caches of those workers. A worker that checked its cache in that window kept the old contents. A worker that reads the catalogs once per notification stayed stale until an unrelated catalog change. PGD now publishes the change before it notifies any worker.	
PGD CLI	5.10.0	Fixed the PGD CLI's Raft leader lookup when some nodes don't answer. The CLI took the Raft leader from the first row of `bdr.group_raft_details`, which is ordered by node name and has an empty row for each node that doesn't answer. When the first nodes by name were unreachable, for example with a whole region down, `pgd groups list --verbose` and the compatibility command `pgd show-groups` showed an empty Raft leader for the top-level group although it had one. The CLI now takes the leader known in the newest Raft term that any node reports.	66386
BDR	5.10.0	Fixed streamed transactions failing to apply with the WAL decoder enabled. With the WAL decoder enabled and transaction streaming in use, two problems could break replication of large or catalog-only transactions: • A streamed transaction whose changes were all filtered out, such as an autoanalyze that touches only catalogs, could make the receiving node fail an assertion or crash. • If a node reconnected while a large transaction was still open, the WAL sender could stop with "encountered incomplete transaction", and the transaction reached the node only after another reconnect.	
BDR	5.10.0	Fixed client certificate checks in Connection Manager. Connection Manager now checks client certificates the way Postgres does. Before, it accepted a client certificate without checking who issued it. The problem affected only `cert` rules in the Connection Manager HBA configuration, on nodes where the Postgres server uses `trust` authentication for connections from Connection Manager. Other related changes: • Client certificates are checked against `ssl_ca_file`, `ssl_crl_file`, and `ssl_crl_dir`, and the `clientcert` HBA option is applied. Without `ssl_ca_file`, `cert` authentication fails, as in Postgres. • If a CRL can't be parsed, for example a version 1 CRL, client certificates are refused and a `WARNING` is logged. Other authentication methods keep working. • The HTTPS status port (`use_https`) no longer asks for a client certificate. If the certificate or key file is missing, it serves plain HTTP and logs a `WARNING`.	
BDR	5.10.0	Removed password hashes and cached credentials from Connection Manager log messages. When a connection to Connection Manager matched no HBA rule, the "no matching HBA rule found" error written to the server log included the role's stored password hash. It also included credentials cached from the role's earlier logins, such as the password itself after a login with the cleartext `password` method. The log messages now show only the role name, password type, and role memberships.	
BDR	5.10.0	Fixed `leader_id` being reported as 0 on the Raft leader. A node that granted a prevote request cleared its record of the current leader, even though a prevote doesn't change who leads the term. On the sitting leader, the node recorded its own `leader_id` as 0 and kept that value until the next leadership change. As a result, `bdr.get_raft_status()` reported a `leader_id` of 0 on the leader, and the PGD CLI clock-drift check failed. Granting a prevote no longer changes the known leader.	65124

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.10.0	Fixed Raft catalog vacuum running at most once per hour regardless of `bdr.raft_vacuum_interval`. Since PGD 5.9.1, an hourly throttle added to prevent `VACUUM FULL` from causing consensus request timeouts during node group creation made any `bdr.raft_vacuum_interval` shorter than one hour, including the 5-minute default, behave as one hour. `bdr.raft_vacuum_interval` now takes effect as configured. `bdr.raft_vacuum_full_interval` must be at least one hour, or `-1` to disable it, and the first `VACUUM FULL` runs no earlier than one hour after the consensus worker starts. `bdr.raft_vacuum_interval` must be less than `bdr.raft_vacuum_full_interval`. Setting a value that breaks these rules fails. If such a value is in the configuration file at server start, PGD logs a warning and uses the default.	
BDR	5.10.0	Fixed PGD ignoring the `failover` option of logical replication slots on Postgres 17 and later. On EDB Postgres Extended and EDB Postgres Advanced Server 17 and later, with `failover_slot_scope` set to `global`, PGD registered every new non-temporary logical replication slot as a failover slot, even if it was created with `failover` set to `false`, the Postgres default. These slots were created on every node, holding back WAL on each one, and creating them required Raft consensus. PGD now honors the `failover` option, as documented: create slots with `failover => true` to make them failover slots. Slots already listed in `bdr.failover_replication_slots` remain failover slots. To make one local, drop it and re-create it without the option.	
BDR	5.10.0	Fixed `bdr.monitor_group_raft()` reporting OK while a node follows a stale Raft leader. `bdr.monitor_group_raft()` now checks the leader of every follower node. Before, it checked only every other follower. If a follower with a stale or missing leader was one of the skipped nodes, the function returned OK. It should have returned CRITICAL with "There are node(s) following a leader different than the node set as RAFT_LEADER". The problem affected PGD 5.0.0 and later. Other related changes: • When more voting nodes are unreachable than the group contains, the function now returns CRITICAL with "The BDR group raft does not reach the quorum". Before, it returned OK.	
BDR	5.10.0	Fixed high CPU usage by the task manager on idle clusters. Fixed an issue where the task manager background worker consumed significant CPU (typically 5–50% of a core) on an otherwise idle cluster that had at least one enabled autopartition rule. The worker failed to back off when no partition work was needed, so it repeatedly re-ran its partition check many times per second. The worker now backs off when no work is queued. The regression was introduced in PGD 5.9.5.	65610, 66822, 67317
BDR	5.10.0	Fixed a memory leak when applying changes to partitioned tables. Fixed a memory leak in the native writer when applying changes to partitioned tables. Rows landing on different partitions repeatedly triggered per-relation setup that left memory allocated until the end of the transaction. Large bulk loads into partitioned tables could therefore grow memory without bound and cause out-of-memory failures.	
BDR	5.10.0	A global DML lock on a partitioned table now locks the whole partition hierarchy. Previously, the global DML lock taken by DDL such as `ALTER TABLE ... SET NOT NULL` was registered on the partitioned table only. Another node could keep writing directly into a partition while the DDL was in flight, so the replicated DDL could meet rows it didn't expect and break replication. The lock now applies to the partitioned table and all of its partitions, including after a node restart.	
BDR	5.10.0	Fixed an assertion failure on subtransaction order in file-streamed transactions. The receiver asserted that the subtransactions of a transaction streamed to a file are in XID order. They are added in the order of their first change, which can differ, so the receiver crashed on assert-enabled builds. The receiver no longer checks the XID order and only checks that positions in the changes file increase.	
PGD CLI	5.10.0	Fixed `pgd group set-option` for the proxy fallback options. `pgd group set-option` with `proxy_fallback_node_groups` or `proxy_fallback_node_group_timeout` always failed with "unknown proxy configuration key", because the CLI passed names that `bdr.alter_proxy_option()` doesn't know. The CLI now passes the server's names, `fallback_groups` and `fallback_group_timeout`.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.10.0	Connection Manager uses the libpq defaults for options a node DSN doesn't set. Options that a node's DSN doesn't set take the libpq default where one exists and otherwise stay unset. For example, a DSN without `dbname` connects to the `postgres` database, and a DSN without `port` or `sslcert` uses libpq's defaults for them.	
BDR	5.10.0	Fixed a potential crash in the local node lookup. An internal lookup of the local node could crash the backend instead of returning cleanly when the database had the BDR extension installed but no local node, for example before `bdr.create_node()` or after the node was parted. No known user operation reached this code path. The lookup is now safe for such callers.	
BDR	5.10.0	Fixed a hang when a node parts itself while a writer is logging a conflict. When a node parted itself, cleanup waited for the receiver and writer processes to exit while still holding a lock on `bdr.event_history`. A writer logging an apply conflict at that moment needed the same lock, so the part could hang and leave replication origins behind. Parting now releases the lock before waiting.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.2 EDB Postgres Distributed 5.9.5 release notes

Released: 20 August 2026

EDB Postgres Distributed (PGD) 5.9.5 includes only bug fixes focused on improving stability and reliability. For a list of known issues, seeKnown issues.

Enhancements

Component	Version	Description	Addresses
BDR	5.9.5	Reduced `bdr.run_on_nodes` latency by performing connection setup asynchronously. `bdr.run_on_nodes()` set up connections to each node sequentially in a loop, so latency scaled linearly with node count. Connection setup is now nonblocking, reducing latency to roughly a constant factor of the worst-case round-trip time. This benefits every caller of `bdr.run_on_nodes()`, including `bdr.monitor_group_raft()`, especially on large clusters.	35480, 51823, 61486
BDR	5.9.5	Improved Autopartition task manager responsiveness after creating work items. The task manager's exponential backoff, up to 290 seconds, wasn't reset after creating or processing work items, so a newly created partition work item could sit waiting through a long sleep before Autopartition acted on it. This could cause `bdr.autopartition_wait_for_partitions_on_all_nodes()` to time out waiting on partitions that hadn't been created yet. PGD now resets the backoff to its minimum interval whenever work is processed, so new work items are picked up promptly.	

Security Fixes

Component	Version	Description
PGD Proxy	5.9.5	Updated PGD Proxy Go dependencies to address known vulnerabilities. Updated `golang.org/x/crypto`, `github.com/jackc/pgx/v5`, and related transitive dependencies to their latest patch versions to resolve known CVEs.

Bug Fixes

Component	Version	Description	Addresses
BDR	5.9.5	Fixed node-join failure caused by an under-sized replication origin estimate during catch-up. The function `bdr.get_min_required_replication_slots()` previously ignored the temporary catch-up subscription active during a node join, so joining a cluster sized to the reported minimum exhausted `max_replication_slots` and failed. The estimate now accounts for the catch-up subscription, and a new `bdr.get_min_required_active_replication_origins()` function returns the matching estimate for Postgres 18's separate `max_active_replication_origins` limit.	
BDR	5.9.5	Fixed a crash caused by a race between a joining and a parting node. A joining node sometimes reached the `PART_CATCHUP` phase of a concurrent node part before it had created a replication origin for the parting node, crashing the manager or writer process when it tried to access the missing origin. PGD now creates the origin in this case, and removes it automatically once the parting node reaches the `PARTED` state.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.9.5	Fixed a crash on dynamic partition creation for `HASH` and `LIST` subpartitions. Creating a dynamic interval partition with `HASH` or `LIST` subpartitions crashed the originating node, and once fixed, produced duplicate partition names that looped until the server ran out of memory. The partition-naming hook is now strategy-aware, producing a unique, deterministic name for each partition across all nodes.	61769
PGD Proxy	5.9.5	Fixed PGD Proxy packages not upgrading to 5.9.5. The 5.9.5 PGD Proxy package had a lower epoch than 5.9.4, so package managers treated it as older and skipped the upgrade. The epoch is now set correctly.	
BDR	5.9.5	Fixed routing getting stuck in an infinite loop after a major network outage. A major network outage that disconnected and reconnected multiple nodes could leave routing stuck in an infinite loop, repeatedly logging `Routing stuck in infinite loop` warnings about a node group's routing record version, with no write leader elected.	63103
BDR	5.9.5	Adopt recovered global locks lazily instead of reacquiring them at writer startup. A writer that restarted while holding a global lock previously reacquired every lock left in recovery state and bound it to itself, sometimes leaving parallel apply disabled after the lock was released. Writers now adopt an existing recovered lock for the same origin node instead, which also supports locks that apply on any streaming writer.	58160
BDR	5.9.5	Fixed a duplicate-key error that could prevent the consensus worker from starting in containerized environments. The consensus worker seeded its own random number generator from the process PID and node ID, which could repeat across restarts in PID-namespaced or containerized environments, causing consensus journal request ID collisions and worker startup failures. The worker now relies on Postgres's own PRNG seeding, which has used a stronger entropy source since Postgres 12, resolving the collisions.	
BDR	5.9.5	Fixed a crash and an out-of-memory crash naming dynamic default RANGE and LIST subpartitions. `bdr_choose_part_name()`, the hook EDB Postgres Advanced Server calls to name unnamed dynamic (sub)partitions, had two related defects when naming a default RANGE subpartition synthesized from an emptied subpartition template. Naming the default subpartition crashed the backend in `get_range_partbound_string()`. Separately, when sibling subpartitions across different parents shared the same synthesized bound, the naming hook returned the same colliding name on every retry, looping indefinitely and leaking memory until the node was killed by the out-of-memory killer. Both defects are now fixed.	
BDR	5.9.5	Fixed critical global lock handling that could cause indefinite blocking. Heavy-weight session locks used for cluster-wide coordination could become misrouted to multiple writers or leak entirely, causing subsequent operations to block indefinitely and requiring a manual Postgres restart to resolve. PGD now routes all global lock messages for a transaction to the same writer, prevents unrelated transactions from being streamed to the global-lock writer, and maintains binding invariants to prevent lock leaks.	
BDR	5.9.5	Fixed cross-subscription deadlock detection and recovery. The deadlock detector previously only reasoned about writers within the same subscription's writer group, so a deadlock spanning multiple subscriptions could pick a victim that wasn't actually holding the contended lock. The abort then freed nothing, the deadlock cycle reformed, and replication slowed severely or wedged permanently under concurrent apply. PGD now detects when deadlock participants span multiple subscriptions and restarts the affected subscription instead of retrying in place.	
BDR	5.9.5	Fixed `bdr.replication_set_remove_table()` crashing when the node isn't part of a node group. The function dereferenced the node's node group without checking for `NULL`, crashing the backend when called before the node had joined a node group, such as during Autopartition's early setup. It now reports a clear error instead of crashing.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.9.5	Fixed a snapshot restore crash with proxy routing enabled. Restoring a consensus snapshot that carried group routing entries crashed the backend with a null pointer dereference in the connection manager backoff reset logic. The crash occurred only with proxy routing enabled and affected `bdr.consensus_snapshot_import()`. PGD now guards against null worker contexts and handles group routing snapshots correctly.	62189
BDR	5.9.5	Fixed consensus worker crashes when a dropped leader appears in change events. The consensus worker crashed and looped when processing a committed `set_leader` entry that referenced a node already dropped from the cluster. PGD now tolerates dropped leader nodes, omitting the leader name when the node is missing, instead of crashing repeatedly.	62189
BDR	5.9.5	Fixed `bdr.alter_subscription_disable(immediate := true)` hanging indefinitely. The pglogical writer being stopped could get stuck in an unbounded retry loop scanning for a row to update, unable to honor a cancel or shutdown signal, whenever a concurrent modification kept invalidating each attempt. Disabling the subscription, or even terminating the backend, couldn't interrupt it, leaving a full restart as the only recovery option. The retry loop now checks for interrupts, so it can be canceled normally.	62159
BDR	5.9.5	Fixed target-table-missing conflict logging on assert-enabled builds. When the apply process encountered a target-table-missing conflict, logging it to `bdr.conflict_history` could trigger an assertion failure on debug builds, because the logging code path didn't register a transaction snapshot before inserting into a TOAST table. PGD now registers an active snapshot around the conflict insert.	62064
BDR	5.9.5	Fixed crashes in `bdr.node_group_config_summary` caused by a default commit scope in an inconsistent state. Querying `bdr.node_group_config_summary` crashed with a segmentation fault if a node group's default commit scope referred to a commit scope that no longer existed, or if resolving the `analytics_autoadd_tables` group option ran on a node with no analytics replication set catalog row, such as a parted node. `bdr.drop_commit_scope()` now also rejects dropping a commit scope that's still configured as the default for a node group, which is what left the catalog in this inconsistent state in the first place.	64521
BDR	5.9.5	Fixed Autopartition rules not being preserved on node rebuild. During `bdr_init_physical` and logical node joins, Autopartition rules copied from the source node were missing three columns (`ap_drop_after_retention_period`, `ap_partition_min_upperbound`, and `ap_analytics_offload_period`). The `ap_drop_after` flag reverted to false, so partitions were detached but never dropped, causing unbounded storage growth on the rebuilt node. PGD now selects these columns from the source and applies the correct defaults.	62064
BDR	5.9.5	Fixed `ALTER PROFILE` replication failure on witness nodes when a password verify function is set. On EDB Postgres Advanced Server (EPAS), witness nodes don't replicate non-role database objects, so replicating `ALTER PROFILE` with a `PASSWORD_VERIFY_FUNCTION` failed on witness nodes with a `function does not exist` error. PGD now skips executing the function on witness nodes, since it already ran on the originating node.	61289
BDR	5.9.5	Protect against creating a Default partition on an autopartitioned table. Autopartition doesn't support a Default partition. DDL that attempted to create one on an autopartitioned table is now rejected instead of leaving the table in an inconsistent state.	61462
BDR	5.9.5	Fixed `bdr.switch_node_group` incorrectly succeeding in a mixed-version cluster during a rolling upgrade. `bdr.switch_node_group` was previously allowed even when the cluster hadn't yet reached the required Raft protocol version during a rolling upgrade. It's now permitted only after the cluster reaches the required protocol version, with a clear error otherwise.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
PGD CLI	5.9.5	Fixed `pgd replication show` erroring out on a subscription with a NULL LSN. `pgd replication show` failed instead of reporting a subscription that hasn't made progress and has a NULL LSN. The command now reports these no-progress subscriptions without erroring out.	
BDR	5.9.5	Fixed commit decisions never being cleaned up for certain workloads after repeated timeouts. Under certain workloads, the commit-decision store's maintenance pass could time out repeatedly without ever fully cataloging its backlog, leaving some commit decisions uncleaned. Maintenance now performs a final no-timeout cleanup pass after multiple timeouts, ensuring all commit decisions are eventually cleaned up.	
BDR	5.9.5	Fixed a duplicate-key error crashing the consensus worker after a node's own generation number diverged. A node whose own `bdr.node` row had a generation diverged from the cluster's view of that node ID crashed its consensus worker in a loop when restoring a Raft snapshot describing its own identity, with `duplicate key value violates unique constraint` node_pkey`. PGD now reconciles this case by updating the existing row instead of trying to insert a new one.	63835
BDR	5.9.5	Fixed `pg_dump` unintentionally emitting references to certain `bdr` extension objects when dumping database schemas. A small number of objects in the `bdr` extension SQL file were created in a way that caused `pg_dump` to emit `GRANT` / `REVOKE` statements for those objects, even though SQL for the objects themselves was correctly not emitted. While this doesn't affect PGD operations, it could inconvenience users making a manual backup of the database schema.	
BDR	5.9.5	Added separate control of published and subscribed replication sets for a node. `bdr.alter_node_replication_sets()` previously applied the same list of replication sets to both what a node publishes and what it subscribes to. New `pub_repsets` and `sub_repsets` arguments let a node publish and subscribe to different replication sets, which is needed to apply a row filter correctly on a Subscriber-Only node.	62864
BDR	5.9.5	Fixed peer nodes deriving a different Autopartition initial lower bound than the originator. `bdr.autopartition()` derives the initial partition lower bound from the local clock when the caller omits it, but replicated the original omitted value to peers instead of the derived one. Each peer then re-derived its own lower bound independently, so a peer with a skewed clock, or one applying the call after a date boundary crossed, could install a different lower bound and never create partitions for the affected period. The derived lower bound is now forwarded to peers so all nodes install the same value.	61462
BDR	5.9.5	Fixed `bdr_maintain_group_slot` getting stuck when the group slot's target LSN exceeded `min_commit_decision_lsn`. `bdr_maintain_group_slot` assumed the group slot always advanced to its computed target LSN, but `bdr_advance_group_slot` skips the advance when the target LSN is past `min_commit_decision_lsn`. `bdr_maintain_group_slot` then waited for a target LSN one WAL segment higher before trying again, indefinitely delaying group slot maintenance.	
BDR	5.9.5	Fixed the CAMO partner unnecessarily receiving a finish message for a transaction it already resolved. A cleanup step ran too early and discarded the per-transaction CAMO configuration before the commit-prepared or rollback-prepared callback could check it, so PGD always fell back to sending an explicit two-phase finish message to the CAMO partner. The partner then applied it unnecessarily, since it had already resolved the transaction through the pre-commit path. The configuration now survives until the finish callback has used it, removing this needless overhead from the CAMO hot path.	
BDR	5.9.5	Fixed the writer blocking the manager and consensus worker while resending commit decisions. `bdr_resend_commit_decisions()` ran the writer's eager confirmation resend as a single blocking pass, holding a lock for the whole duration. This could block the manager's decision cleanup, the consensus worker's periodic snapshot, and even read-only queries like `bdr.commit_decisions`, for as long as the resend took. The resend is now split into a step that copies out only what's needed while holding the lock, and a separate step that sends the backlog incrementally without blocking. The writer also no longer waits for the entire backlog to drain before entering its main loop, so it can service a receiver's flush request right away instead of only after the backlog is fully processed.	63068

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.9.5	Fixed a memory leak in the legacy `bdr.raft_election_timeout` configuration parameter alias. The legacy `bdr.raft_election_timeout` alias had a memory leak in its assign hook that orphaned the preferred parameter name string when the real variable was registered, leaking memory on every configuration reload (SIGHUP) while the legacy alias was in use. PGD now reorders parameter registration to prevent the leak and removes an unnecessary `SetConfigOption` call from the hook.	
BDR	5.9.5	Fixed a memory leak when reloading the `bdr.temp_directory` configuration parameter. The `bdr.temp_directory` assign hook didn't free the previous value when reassigning the parameter, leaking memory on every SIGHUP-driven reload while the parameter was changed. PGD now frees the prior allocation before storing the new value.	
BDR	5.9.5	Fixed an uninitialized data read in Autopartition work item error handling. `bdr_taskmgr_workitem_fromtuple()` left the runtime-only `ap_is_local` field uninitialized at several call sites, since the field isn't part of the catalog tuple. A customer Valgrind run caught a read of this uninitialized value when the task manager's error-context callback formatted an error. PGD now populates `ap_is_local` at every call site that builds a work item.	
BDR	5.9.5	Fixed resource leaks in `bdr.ri_fkey_on_del_trigger`. The `bdr.ri_fkey_on_del_trigger` trigger function left a relation, a tuple descriptor, and a snapshot open every time it ran, logging `resource was not closed` warnings on every node. The function now closes these resources correctly.	
BDR	5.9.5	Fixed incorrect values reported by `bdr.stat_subscription` for pre-commit counters. The `npre_commit` and `npre_commit_confirmations` columns of `bdr.stat_subscription`, and the underlying `bdr.get_subscription_stats()` function, had their values swapped. `npre_commit` always reported 0, or whatever value `npre_commit_confirmations` actually held, while `npre_commit_confirmations` reported the real pre-commit count. This was a reporting-only issue. Commit At Most Once (CAMO) and group commit replication behavior weren't affected, and only the statistics view was wrong.	
BDR	5.9.5	Fixed a relcache reference leak in `bdr.autopartition_disable()` and `bdr.autopartition_enable()`. Calling either function on a table that isn't an autopartitioned relation returned without closing the table, logging a `relcache reference leak` warning.	
BDR	5.9.5	Re-enabled writes to `bdr.camo_decision_journal`. A faulty condition, introduced years earlier, silently skipped every write to `bdr.camo_decision_journal`, breaking this CAMO diagnostics feature. Writes are now re-enabled.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.3 EDB Postgres Distributed 5.9.4 release notes

Released: 26 May 2026

EDB Postgres Distributed (PGD) 5.9.4 includes only bug fixes focused on improving stability and reliability. For a list of known issues, seeKnown issues.

Enhancements

Component	Version	Description	Addresses
BDR	5.9.4	DDL on objects in the `bdr` schema is no longer permitted. Database users can no longer create or modify database objects in the `bdr` schema, or set the namespace of an object to the `bdr` schema. This restriction prevents catalog corruption and extension upgrade issues that such operations could cause.	53224
BDR	5.9.4	Added sanity checks for joining and parting nodes in CAMO-configured groups. Attempting to join a data node to a group where existing nodes are configured as CAMO partners, or to part a data node when the group's `default_commit_scope` or the local node's `bdr.commit_scope` is set to a CAMO commit scope, now raises an error. To perform these operations, drop the CAMO commit scope first.	55212
BDR	5.9.4	The configuration parameter `bdr.enable_auto_sync_reconcile` is now visible in `pg_settings`. The `bdr.enable_auto_sync_reconcile` configuration parameter is now exposed in the `pg_settings` view, making it visible to monitoring tools.	
BDR	5.9.4	Improved log output when the transaction change tracker buffer is exceeded. The emitted log message now makes it clear that the issue is transient and that processing resumes following an automatic restart of the writer.	

Bug Fixes

Component	Version	Description	Addresses
BDR	5.9.4	Fixed zero OID assigned to tablespaces during logical join sync. `bdr_tablespace_upsert()` was not setting the OID when inserting a new tablespace, causing a duplicate key violation when multiple user tablespaces were synced during logical join.	59715
BDR	5.9.4	Fixed a memory leak in the walsender for the temporary replication slot used by joining nodes. Fixed a memory leak in `bdr_copy_to_repl_dest_receiver_receive`, where per-row allocations in the walsender for the temporary replication slot used by joining nodes were not freed correctly.	59663
BDR	5.9.4	Fixed a writer segfault when a replication origin was already in use. Enabling a `NORMAL` subscription while a `sync_node` request was in progress for the same origin caused a second writer to crash with a `SIGSEGV`. PGD now blocks enabling a `NORMAL` subscription in this case, and the origin-acquisition path returns a recoverable error instead of crashing.	
BDR	5.9.4	Fixed a parallel apply livelock caused by reading stale transaction IDs from the commit queue. With Parallel Apply enabled, the leader and parallel `pglogical` writer could deadlock while applying a large streamed transaction, requiring the writer processes to be forcibly terminated. The root cause was `bdr_writer_check_commit_queue()` reading a stale transaction ID from `APPLY_QUEUED` commit queue entries.	61055

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
PGD CLI	5.9.4	Fixed `pgd node upgrade` failing with invalid logical replication slots error. Upgrading from EDB Postgres Extended (PGE) 17 with PGD 5 to PGE 18 with PGD 6 using `pgd node upgrade` was failing because `pg_upgrade` detected BDR replication slots as invalid. The fix backports the logic to hide BDR-managed slots from `pg_upgrade` during the upgrade process, allowing the upgrade to proceed successfully.	
PGD CLI	5.9.4	Fixed `pgd node upgrade` hanging due to configured commit scopes. During `pgd node upgrade`, configured commit scopes are now reset to `local` to prevent the upgrade from hanging. The reset is applied via DSN parameter before the upgrade proceeds.	60466
BDR	5.9.4	Fixed Connection Manager process not stopping after postmaster is killed.	59631
BDR	5.9.4	Fixed memory leak in Postgres worker caused by `bdr_connection.client_addr` updates. Handling updates to the `bdr_connection.client_addr` configuration parameter, used by Connection Manager in session pooling mode, was leaking memory in the Postgres worker.	
BDR	5.9.4	Fixed segfaults in `bdr.stat` shared-memory entry handling. Concurrent statistics readers observed partially-initialized or freed Dynamic Shared Area (DSA) pointers when a stat entry was being created or dropped, causing `bdr_stat_write_file` to dereference NULL or freed memory. The initialization path now marks entries invalid until allocation succeeds, the drop path holds an exclusive lock, and all dshash scan paths guard against invalid DSA pointers.	
BDR	5.9.4	Fixed pglogical manager process spinning at 100% CPU when a PGD worker becomes unresponsive to `SIGTERM`. When the pglogical manager process died with an error and tried to terminate other PGD workers, it hung if those workers had died uncleanly or were stuck and unable to receive signals. The process now exits correctly in all such cases.	60272
BDR	5.9.4	Fixed Connection Manager log level filtering to match Postgres behavior. Connection Manager was incorrectly interpreting `log_min_messages`, causing inconsistent log filtering compared to Postgres.	
BDR	5.9.4	Fixed task manager incorrectly reporting AutoPartition table local status. The `local` state of an AutoPartition table is now logged correctly by the task manager.	
BDR	5.9.4	Fixed physical join failing when Postgres restarts on the joining node mid-join. In some cases, a Postgres restart on the joining node during a physical join caused the join to attempt a logical sync, resulting in errors. The fix prevents the physical join from falling back to logical join logic when a restart occurs mid-join.	59904
BDR	5.9.4	Fixed memory leaks identified through Valgrind analysis. Several memory leaks detected during Valgrind analysis of a two-node PGD cluster have been resolved.	
BDR	5.9.4	Fixed `bdr.bdr_version_num()` returning an incorrect version number. The `BDR_VERSION_NUM` constant was not updated to match the version string, causing `bdr.bdr_version_num()` to return the previous version's numeric value.	60659

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.4 EDB Postgres Distributed 5.9.3 release notes

Released: 15 April 2026

This is a patch release of PGD 5, which includes several enhancements and bug fixes. For a list of known issues, see Known issues.

Changes

Component	Version	Description
PGD Proxy	5.9.3	Updated third-party dependencies to address security vulnerabilities. Updated internal library dependencies to address security vulnerabilities CVE-2026-33815 and CVE-2026-33816.

Bug Fixes

Component	Version	Description
BDR	5.9.3	Fixed user login attributes not replicated to peer nodes. After a `CREATE USER` statement, the user's login attribute was not propagated to peer nodes, preventing login on any node other than the originating one. This fix ensures role login attributes are correctly included in replication.
Connection Manager	undefined	Fixed Connection Manager using outdated routing configuration when routing was enabled or disabled on a node group.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.5 EDB Postgres Distributed 5.9.2 release notes

Released: 26 March 2026

This is a patch release of PGD 5, which includes several enhancements and bug fixes.

Enhancements

Component	Version	Description	Addresses
BDR	5.9.2	Improved the group deletion process to automatically drop associated replication sets. Enhanced the node group removal logic to automatically drop replication sets of the same name.	57531
BDR	5.9.2	Improved the consistency of Connection Manager against `pg_hba.conf`. Enhanced how the Connection Manager matches database names and usernames against `pg_hba.conf` fields. Key improvements include support for `sameuser` matching, refined `samerole` logic, and expanded `+rolename` matching to include the role itself and indirect members. Additionally, quotes are now stripped from usernames before matching to ensure consistent authentication behavior.	
BDR	5.9.2	Added support for user name mapping (`pg_ident.conf`) to the Connection Manager. This enhancement allows the Connection Manager to use `pg_ident.conf` for user name mapping. Currently, this functionality applies to the `cert` authentication method, aligning Connection Manager behavior with PostgreSQL's native authentication identity mapping.	
BDR	5.9.2	Made `bdr.max_writers_per_subscription` runtime-reloadable. `bdr.max_writers_per_subscription` is now `PGC_SIGHUP` : change the value with `ALTER SYSTEM` followed by `pg_reload_conf()` — no node restart is required. The value is captured by each writer group at initialization, so an in-flight subscription continues with the value it was started with; the new limit takes effect on the next writer-group start (subscription disable/enable, or the next reconnect cycle).	

Changes

Component	Version	Description
PGD Proxy	5.9.2	Updated third-party dependencies to resolve CVE-2026-4427 and address GitHub Dependabot alerts. Patched internal libraries to address a security vulnerability (CVE-2026-4427). Although the vulnerability does not directly expose the PGD Proxy, a malicious or compromised PostgreSQL server could send a crafted DataRow message to crash the PGD Proxy, resulting in a denial-of-service (DoS) attack.

Bug Fixes

Component	Version	Description	Addresses
BDR	5.9.2	Fixed a replication crash loop caused by interrupted partition detaching. Resolved an issue where logical replication would enter an infinite crash loop if a `DETACH PARTITION CONCURRENTLY` command was interrupted. Previously, the walsender would fail with the error `relation has no parent because it's being detached` when decoding WAL for a partition in a `detach-pending` state.	53628, 59291

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.9.2	Fixed a `walsender` crash loop during partition detachment. Fixed an issue where the `walsender` process could enter a crash loop when encountering partitions with `inhdetachpending = true`, which reported `ERROR: relation %u has no parent failures`.	53628, 59291
BDR	5.9.2	Fixed `ALTER ROLE` replication failures. Fixed an issue where replication would break because attributes like `NOSUPERUSER` or `NOREPLICATION` were automatically added to the replicated command. Since these options can only be altered by a superuser, the apply process failed on downstream nodes. This change ensures the replicated command only includes options that were explicitly specified and for which the user has sufficient privileges.	54906
BDR	5.9.2	Improved lock handling during change application to prevent data corruption from concurrent backends. Table and index locks are now held until transaction commit when applying changes. This ensures correct serialization and prevents data consistency issues during concurrent operations, specifically addressing risks introduced by parallel apply.	
BDR	5.9.2	Parallel Apply can now be enabled when PGD is deployed with community Postgres. Resolved an issue where enabling Parallel Apply on community PostgreSQL caused writer hangs and stuck subscriptions due to frequent lock timeouts. This fix allows Parallel Apply to be used reliably without requiring it to be disabled as a workaround.	54565, 57005, 57327
PGD CLI	5.9.2	Fixed the in-line help for `pgd group set-option` command. Corrected the help text for `pgd group set-option` to accurately reflect group-level options.	
PGD CLI	5.9.2	Fixed the matrix view output for the `pgd replication show` command. Inactive/disconnected slots now display `!` instead of `*` when lag is below 10 MB, restoring consistency.	56295
PGD CLI	5.9.2	Backported TDE options for the `pgd node upgrade` command to PGD 5. The pgd node upgrade command now supports the `in-place` conversion of a non-TDE PGD node to a TDE-enabled node via the `--key-unwrap-command` and `--copy-by-block` options.	
BDR	5.9.2	Fixed a memory leak in the consensus process when subscriber-only nodes are down. Resolved a malloc-based memory leak related to the improper freeing of connection strings.	57094
BDR	5.9.2	Fixed a segmentation fault occurring during `COPY` commands when `pgaudit.role` is set to a non-default value. Resolved an issue where Postgres would crash with a segmentation fault when executing a `COPY` command if the `pgaudit.role` configuration was set to a non-default value.	58060
BDR	5.9.2	Fixed an issue where the `use_https` node group configuration option was ignored. Resolved a bug where Connection Manager incorrectly ignored the `use_https` setting. When upgrading to PGD 6.3.0 or 5.9.2, you must explicitly enable HTTPS by setting the `use_https` group option to `true` (in addition to having `ssl_cert_file` and `ssl_key_file` configured in `postgresql.conf` or via the command line) before the upgrade to maintain previous behavior.	
BDR	5.9.2	Fixed a Connection Manager memory leak occurring during configuration reloads. Resolved a memory leak in the Connection Manager caused by incorrect handling of Postgres memory contexts during configuration reloads.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.9.2	Fixed proxy configuration loss after `bdr_init_physical`. Fixed an issue where proxy configurations were not preserved after running `bdr_init_physical` due to Raft snapshot restores failing to persist proxy settings.	58319
BDR	5.9.2	Fixed stale `galloc` sequence allocation entries after `DROP` and `CREATE`. Fixed a bug where `sequence_alloc` entries persisted after a `galloc` sequence was dropped and recreated. The fix ensures proper cleanup propagation across the cluster, including witness nodes.	
BDR	5.9.2	Fixed `bdr.alter_sequence_set_kind` ignoring start values for `galloc` sequences. Fixed an issue where changing a sequence kind to `galloc` would silently discard the provided `start_value`. Additionally, resolved a bug where a `startval` of `0` was lost during WAL replication.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.6 EDB Postgres Distributed 5.9.1 release notes

Released: 5 December 2025

This is a patch release of PGD 5, which includes several enhancements and bug fixes.

Features

Component	Version	Description
BDR	5.9.1	Added support for LDAP authentication to Connection Manager. Connection Manager now supports the same LDAP authentication features as PostgreSQL, with the exception that OpenLDAP configuration files and environment variables are not supported.

Enhancements

Component	Version	Description	Addresses
PGD CLI	5.9.1	Added `Details` column to `cluster verify --verbose --arch` output. The cluster verify command now includes a `Details` column in the architecture verification section when using the `--verbose` option. This column provides specific, detailed information about any issues encountered during the architecture check.	
PGD Proxy	5.9.1	Added the `-V, --version` flag to PGD Proxy. Added the `-V, --version` flag to the `pgd-proxy` binary to verify the installed PGD Proxy version.	51980
BDR	5.9.1	Support for encrypted server side certificates. Connection Manager now supports the PostgreSQL `ssl_passhrase_command` option to decrypt the server private key.	53695
BDR	5.9.1	Only synchronize relevant PGD role settings. The role synchronization logic has been refined to only apply role settings from the source node if they are global, or are specifically configured for the PGD database on the source node.	
BDR	5.9.1	Emit warning message for `synchronous_standby_names` clash with commit scope. Added a new sanity check that emits a warning during startup if the PostgreSQL configuration parameter `synchronous_standby_names` is configured in a way that might clash with a PGD commit scope. This helps administrators quickly identify and correct potential misconfigurations.	

Changes

Component	Version	Description
BDR	5.9.1	Upgraded internal library version. Upgraded the project's Golang runtime to version 1.24.0.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Bug Fixes

Component	Version	Description	Addresses
BDR	5.9.1	Fixed an issue whereby a connection is silently dropped in the Connection Manager. The fix improves the handling of authentication failures in the Connection Manager.	
BDR	5.9.1	Fixed an issue whereby Connection Manager crashed when full hostname is used in the `pg_hba.conf` `address` field. The fix also corrects the handling of hostname suffixes. Since hostname matching is not supported by the Connection Manager, HBA rules using hostnames or hostname suffixes are now correctly ignored by the Connection Manager, preventing instability.	
BDR	5.9.1	Improved Connection Manager routing change logic. Resolved an issue where the Connection Manager dropped existing client connections whenever a write-leader or read-only node routing change occurred. With this fix, client connections are no longer affected by a routing refresh, as long as the PGD node they are currently connected to remains operational.	
BDR	5.9.1	Fixed unexpected subscription and slot creation involving subscriber-only and witness nodes. Resolved an issue where subscriptions or replication slots were incorrectly created between subscriber-only nodes and witness nodes. This fix prevents the incorrect creation of both subscriptions and replication slots between subscriber-only nodes and witness nodes.	
PGD CLI	5.9.1	Ensure child origins are cleaned up when a PGD node parts. Resolved a bug whereby child origins remained on a PGD node after the parting operation was complete.	
BDR	5.9.1	Fixed writer error `could not open temporary file` after restart. This issue occurred when streaming a large transaction, and the writer restarted only to find the temporary file name had been incorrectly freed. The bug was introduced with parallel apply and is resolved now.	53341
BDR	5.9.1	Fixed consensus schema version compatibility issue affecting PGD upgrades. Resolved a compatibility problem encountered during upgrades from PGD versions previous to 5.6.0 to newer releases. The issue was caused by added fields in the `bdr.node_group_routing_info` catalog, which caused interoperability failures with `pgd-proxy` when using the `bdr.raft_catalog_read_consistency` feature in mixed version clusters.	51027
PGD CLI	5.9.1	Backported Connection Manager group options to `pgd group` commands. Resolved an issue where Connection Manager options were not included when the it was backported to PGD 5. These options are now backported and available for use with the `group get-option`, `group set-option`, and `group show` commands.	
BDR	5.9.1	Fixed the `bdr.msgb_connect` hang by introducing a connection timeout. Resolved an issue where the `bdr.msgb_connect` function could hang indefinitely due to a missing network timeout setting. The fix adds the a timeout to the function.	53442
BDR	5.9.1	Connection Manager now starts and responds on its configured ports on all nodes, even those that are not currently part of a node group with routing enabled. In these cases, the configuration inherited from the top-level node group is automatically applied.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.9.1	Fixed a unique constraint violation error that could occur during an `UPDATE` operation on tables configured with both primary and unique keys. Previously, an `UPDATE` conflict with an `update_missing` resolution (which attempts to insert a new record) did not check for conflicts against existing primary or unique keys, leading to an error. This issue is now fixed by treating the scenario as an `insert_exists` conflict and applying the appropriate resolution logic.	50539, 51417, 54323
BDR	5.9.1	Fixed join inconsistency during physical node setup. Resolved an issue during physical node joins where the last transaction was redundantly included in the physical snapshot. The system now ensures this final transaction is excluded from the snapshot, as it will be correctly received later via logical replication, preventing duplication.	
BDR	5.9.1	Fixed various issues with EPAS role and profile synchronization. Resolved various synchronization issues affecting the correct replication and management of EDB Postgres Advanced Server (EPAS) roles and profiles across the cluster.	52572
BDR	5.9.1	Fixed cleanup of stale LSN records in `bdr.node_peer_progress_mapping`. Resolved an issue where stale records from parted or dropped nodes were retained in the `bdr.node_peer_progress_mapping` table. Proper cleanup is now enforced to prevent these stale records from unnecessarily holding back the group replication slot.	50616, 50778, 50856
BDR	5.9.1	Fixed spurious walsender timeouts during lengthy transactions. Resolved an issue where spurious walsender timeouts could occur while the receiver process was flushing a lengthy transaction.	52018
BDR	5.9.1	Fixed error during join due to altered non-database role settings. Resolved an issue where the error `database with remote_datid 0 not found in remote_databases` occurred during the node join process. This failure happened when a role on the upstream source node had been altered to include a setting that was not specific to the database, causing a lookup failure during synchronization.	52859
BDR	5.9.1	Ensure hard-coded `CRDT` merge functions are always available. Resolved an issue where the system incorrectly required built-in, hard-coded `CRDT` merge functions to be explicitly registered in the `bdr.crdt_handlers` catalog.	52759
BDR	5.9.1	Fixed incorrect error during `bdr.commit_scope` check. Resolved an issue where the check for the configuration parameter `bdr.commit_scope` incorrectly raised an error if the PostgreSQL configuration was reloaded while a transaction was in progress, even when the parameter's value had not actually been modified.	51457
BDR	5.9.1	Fixed EPAS role and profile replication issues. Resolved two replication issues related to EPAS roles and profiles: - Fixed an issue where profile names were incorrectly quoted as string literals instead of identifiers, causing syntax errors when replicating `CREATE ROLE` or `ALTER ROLE` commands with the `PROFILE` clause. - Corrected a bug where `ALTER ROLE` commands that did not change passwords incorrectly included the `PASSWORD` clause, which triggered password reuse policy violations when profiles had `PASSWORD_REUSE_TIME` or `PASSWORD_REUSE_MAX` constraints.	54909
BDR	5.9.1	Fixed consensus timeout errors during initial cluster setup. Resolved `consensus request timed out` errors that could occur during BDR cluster initialization. This issue happened when vacuum operations on internal consensus tables interfered with critical group creation processes. The fix now defers vacuum operations until the cluster is properly established.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.7 EDB Postgres Distributed 5.9.0 release notes

Released: 19 August 2025

This is a minor release of PGD 5, which includes several enhancements and bug fixes. This version is also a prerequisite for seamless upgrades to PGD 6.1.0, and it has been updated to include key infrastructure, such as a back-ported Connection Manager, to ensure a smooth transition to the latest major version.

Highlights

- This is the first PGD 5 version to support a direct, in-place upgrade to PGD 6, beginning with PGD 6.1.0
- New Detach Partition function for PGD AutoPartition
- Support EDB Postgres Advanced Server (EPAS) Interval Partitioning

Features

Component	Version	Description
BDR	5.9.0	New drop_after_retention_period argument added to the bdr.autopartition function bdr.autopartition() now takes an additional boolean argument drop_after_retention_period which can be set to false if the user does not want the partition to be dropped, but only detached.

Enhancements

Component	Version	Description
BDR	5.9.0	Improve Raft snapshot export/import to reset Raft completely We've made improvements to how our Raft consensus mechanism handles snapshots. This ensures that in the rare event of a data consistency issue, restoring a snapshot will now fully reset the system's state, allowing operations to resume smoothly from a consistent starting point.
BDR	5.9.0	EPAS Interval Partition Support for PGD A new enhancement allows partitions created by EDB Postgres Advanced Server (EPAS) AutoPartition to work correctly within a multi-node PGD environment. This fix ensures partitions are created consistently on each node and are visible across all nodes.
BDR	5.9.0	Connection Manager Back-Port for PGD 5.9 To streamline the upgrade process, the Connection Manager has been back-ported to PGD 5.9 as an optional feature that's disabled by default. This change allows for seamless upgrades to PGD 6 by having the necessary infrastructure in place. It also gives you the opportunity to test the Connection Manager in non-production environments before a full production upgrade.
BDR	5.9.0	Enable proxy routing by default for subgroups Subgroups have proxy routing enabled by default from 5.9.0 however it doesn't impact the existing behavior of subgroups and how to connect to the nodes without proxy.
BDR	5.9.0	Synchronize roles and tablespaces during logical join Roles and tablespaces are now synchronized before the schema is restored from the join source node. If there are already existing roles or tablespaces (or EPAS profiles), they will be updated to have the same settings, passwords etc. as the ones from the join source node. System roles (i.e. the ones created by initdb) are not synchronized.
BDR	5.9.0	Replication of roles to witness nodes Roles are now replicated to witness nodes at node join. Roles also get replicated to witness nodes during normal operation of the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Bug Fixes

Component	Version	Description	Addresses
BDR	5.9.0	Fix for PGD node upgrade fails with 'function max(pg_lsn) does not exist' We've resolved a bug that could cause a PGD node upgrade to fail with the error 'function max(pg_lsn) does not exist'.	
BDR	5.9.0	Fix for Subscription Key Errors During Node Sync A fix has been implemented to resolve an issue that caused duplicate key value violates unique constraint "subscription_pkey" errors during node resynchronization. To ensure unique names and prevent manager crashes, subscription names now include the source node name, which provides a more robust and reliable resynchronization process.	
PGD CLI	5.9.0	PGD CLI cluster verify Command Fix for Witness-Only Groups The pgd cluster verify command no longer displays a warning for witness-only groups that do not contain data nodes. This resolves an issue where the command incorrectly flagged these groups, ensuring that the verification output is now accurate for all cluster types.	
BDR	5.9.0	Raft Fix for Parting Lagging Nodes Raft no longer fails to recover after a heavily-lagging node that was previously a leader is parted from the cluster. This fixes a bug where the Raft leader could crash with a "BDR node XXX not found" error, which previously required a manual, forceful reset of the Raft state. Now, Raft correctly handles this scenario and recovers automatically, ensuring cluster stability.	50099
BDR	5.9.0	Fix for "Clock Has Moved Backwards" Error with Snowflake Sequences A race condition has been fixed that could cause a "clock has moved backwards" error when using Snowflake sequences, even when the system clock was functioning correctly. This fix ensures the sequence correctly handles concurrent access, preventing this error and improving the reliability of Snowflake sequence generation.	
BDR	5.9.0	Fix for `bdr_init_physical` Hangs with Synchronous Commit A bug has been fixed that could cause `bdr_init_physical` to hang when the upstream node had a synchronous commit scope. This issue, which prevented a new node from completing physical initialization, was caused by a specific interaction with synchronous commit settings. The fix ensures that `bdr_init_physical` now works reliably in all configurations, even before the new node joins the group and is considered for synchronous commits.	50599
BDR	5.9.0	Fix a crash with pg_failover_slots Ensure that CDC hooks are no-op when recovery is in progress or the backend is not connected to a database. This can definitely happen if `pg_failover_slots` is active.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.8 EDB Postgres Distributed 5.8.1 release notes

Released: 25 June 2025

EDB Postgres Distributed 5.8.1 includes a number of bug fixes.

Bug Fixes

Component	Version	Description	Addresses
PGD CLI	5.8.1	Removed the `--new-socketdir` CLI option and corresponding `PGSOCKETDIRNEW` env variable for `pgd node upgrade` command. The `--new-socketdir` CLI option and corresponding `PGSOCKETDIRNEW` env variable was introduced to address a scenario where the old and new socket dirs are different. This fix addresses the issue by fetching the value of new socket dirs from the initialized new server.	49024
PGD CLI	5.8.1	Added a more useful error message if CLI cannot find the executable binaries. This fixes the command crash if the CLI cannot find the binaries like `postgres`, `pg_ctl` on the expected path. By default it searches the binaries at the path of the `pgd` binary itself.	
PGD CLI	5.8.1	Fix the broken replication slot issue after rolling Postgres upgrade using `pgd node upgrade` command. Merge writer origin positions to the parent origin during node upgrade. In PGD 5 and older writer origin names map to parent origin id which may change during inplace upgrade.	46412,48747
BDR	5.8.1	Ensure that GRANT check for BDR objects works for EPAS object types The mechanism for determining whether user can be granted permissions on BDR extension objects was failing for EPAS-specific objects. This is a regression from PGD release 5.7.0 and is now fixed.	49649
BDR	5.8.1	Ensured physical join does not leave behind a slot that holds WAL. Physical join using bdr_init_physical resulted in creation of an extra slot after the physical join is over, and can result in holding up WAL. This is a regression from BDR release 5.7.0. This is now fixed.	48710, 50099
BDR	5.8.1	Fixed node sync bugs This release has fixed several issues related to node synchronization in BDR. The node sync process now properly cleans up slots and subscriptions when any of the source, target, or origin parts are involved. Additionally, the node part operation has been fixed to prevent hanging during node sync operations. Subscriber-only nodes will also now be correctly synced.	
PGD CLI	5.8.1	Renamed the check `Clock Skew` to `Clock Drift` for `pgd cluster show` command. The check is renamed to be consistent with the terminology used at other places in PGD.	
PGD CLI	5.8.1	Added a warning message if CLI fails to fetch value of a GUC for `pgd cluster verify` command. This fixed the command crash issue if CLI cannot fetch value of a GUC for some reason.	
BDR	5.8.1	Fixed rejoin of parted node with same name gets stuck in JOIN_START state. Rejoin of parted node with same name gets stuck in JOIN_START state. This problem was fixed.	45084, 44467
BDR	5.8.1	Fixed hang in database system shutdown. Fixed non-transactional WAL message acknowledgment by downstream that could cause a WAL sender to never exit during fast database system shutdown.	49022

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.8.1	Fixed DROP_REPLICATION_SLOT handling for physical / non-existing slots. DROP_REPLICATION_SLOT command for physical / non-existing slots was failing with an ERROR.	47308

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.9 EDB Postgres Distributed 5.8.0 release notes

Released: 22 May 2025

EDB Postgres Distributed 5.8.0 includes a number of enhancements and bug fixes.

Highlights

- PGD CLI improvements enhance usability and functionality.
- Additional functions simplify sequence management.
- Includes a fix for CVE-2025-2506.

Enhancements

Component	Version	Description
PGD CLI	5.8.0	The `--summary` and `--options` flags for `pgd node show` CLI command. Add the `--summary` and `--options` flags to `pgd node show` command to filter the output of the `pgd node show` command. This also maintains symmetry with other `show` commands.
PGD CLI	5.8.0	More GUCs verfied in `pgd cluster verify` CLI command. Add the `bdr.lock_table_locking` and `bdr.truncate_locking` GUCs to list of GUCs verfied in `pgd cluster verify` command.
BDR	5.8.0	We now ensure that commit scope logic only runs on data nodes. While commit scope processing does not have any direct affect on non-data nodes, by skipping it altogether we can avoid potentially confusing error messages.
BDR	5.8.0	Added `bdr.galloc_chunk_info()` function to simplify sequences. The `bdr.galloc_chunk_info()` function provides information about the chunk allocation for a given sequence. This function returns the chunk ID, the sequence ID, and the chunk size. This function is useful for debugging and understanding how sequences are allocated in BDR.
PGD CLI	5.8.0	Improve the CLI debug messages. Improve the formating of the log messages to be more readable and symmetrical with Postgres log messages.
PGD CLI	5.8.0	Added a new column for `pgd cluster verify --settings` CLI command output. Add the `recommended_value` column to the result of the `pgd cluster verify --settings` command. The column will not be displayed in tabular output but will be displayed in JSON output.
PGD CLI	5.8.0	Display sorted output for CLI. The output for the commands with tabular output will be sorted by the resource name. For the commands that display more than one resource, the output will be sorted by each resource column in order.
BDR	5.8.0	Improved pgd_bench error message related to CAMO. If executed with `--mode=camo`, but the provided test script is not wrapped in an explicit transaction, pgd_bench will not be able to retrieve the expected `transaction_id` value. Now the emitted error message contains a hint about a possible missing transaction.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Security Fixes

Component	Version	Description	Addresses
BDR	5.8.0	Addressed CVE-2025-2506, which could enable a user with CONNECT access to obtain read access to replicated tables. An issue, CVE-2025-2506, was discovered in pglogical which is present in later versions of BDR and PGD. The issue could enable a user with CONNECT access to obtain read access to replicated tables.	CVE-2025-2506

Bug Fixes

Component	Version	Description	Addresses
BDR	5.8.0	Added "safety nets" for CDC failover. CDC failover now has additional safety nets to ensure that the consumer does not start replication from a node that is not the creator of the replication slot. This is to prevent data loss or duplicate transactions. The changes also add additional checks to ensure that the consumer does not start replication from a node that does not have the required WAL files to decode the transactions that are missing on the consumer but were included in the initial snapshot that the newly joined node had obtained (physical or logical).	
BDR	5.8.0	Fixed replication failure with concurrent updates on a non-unique index. Updated to compare tuples on lookup to ensure it is the same when handling non-unique indexes.	43523, 43802, 45244, 47815, 48007
BDR	5.8.0	Improved handling of connection information and password obfuscation. The shared memory information for connection information may get obfuscated when a password is present and become useless. Instead of reading from there, we are now using the `primary_conninfo` GUC which is now available on all supported PG versions.	41776
PGD CLI	5.8.0	Fixed the CLI `pgd cluster show` command's behavior with clock drift errors and a degraded cluster. The `pgd cluster show` command would exit with an error regarding clock drift if only one node was up and running in a N node cluster, and not show the associated `health` and `summary` information. The command now returns output for, `health` and `summary`, while reporting an appropriate error for `clock-drift`.	
PGD CLI	5.8.0	Fixed the CLI `pgd node show` command crashing if a non-existent node is given. The `pgd node show` command crashed if a non-existent node was given to the command. The command now fails gracefully with an appropriate error message.	
PGD CLI	5.8.0	Fixed the timestamp parsing issue for `pgd replication show` CLI command. The `pgd replication show` command previously crashed when formatting EPAS timestamps.	47280
BDR	5.8.0	Prevent segfault in bdr.taskmgr_set_leader. The node_name argument to bdr.taskmgr_set_leader is required. The function now throws an appropriate error in case node_name := NULL is passed in.	
BDR	5.8.0	Improved deadlock avoidance where bdr_init_physical and monitoring queries are running concurrently. We have replaced TRUNCATEs with DELETEs from all BDR catalogs on a local node drop. This is to avoid deadlock in bdr_init_physical if the user happens to run monitoring queries during node joining / cleaning unwanted source node data.	46952
BDR	5.8.0	Ensure a new joiner processes the watermark message in the CATCHUP phase. Setting nci->min_lsn to XactLastCommitEnd of watermark message Tx to ensure CATCHUP phase finishes on new joiner only after watermark is processed.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.8.0	Fix Raft leader election timeout/failure after upgrade Ensure that any custom value set in the deprecated GUC `bdr.raft_election_timeout` is applied to its replacement `bdr.raft_global_election_timeout`.	
BDR	5.8.0	Ensure that disabled subscriptions on subscriber-only nodes are not re-enabled During subscription reconfiguration, if there is no change required to a subscription, do not enable it since it could have been disabled explicitly by the user. Skip reconfiguring subscriptions if there are no leadership changes.	46519
BDR	5.8.0	Subscriber-only nodes will not take a lock when running DDL Subscriber-only nodes will no longer attempt to take a lock on the cluster when running DDL. The DDL will be executed locally and not replicated to other nodes.	47233
BDR	5.8.0	Fixed deadlock issue in bdr_init_physical. Fixed deadlock between bdr_init_physical cleaning unwanted node data and concurrent monitoring queries.	46952
BDR	5.8.0	Fixed a consistency issue in node join where a joining node could possibly miss some data sent to it from the source node. Fixed an issue when a new node joining the cluster finishes CATCHUP phase before getting its replication progress against all data nodes. This could have caused a new node to be out of sync with the cluster.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.10 EDB Postgres Distributed 5.7.0 release notes

Released: 25 February 2025

Updated: 26 March 2025

EDB Postgres Distributed 5.7.0 includes a number of enhancements and bug fixes.

Highlights

- **Improved 3rd Party CDC Tool Integration**: PGD 5.7.0 now supports failover of logical slots used by CDC tools with standard plugins (such as test_decoding, pgoutput, and wal2json) within a PGD cluster. This enhancement eliminates the need for 3rd party subscribers to reseed their tables during a lead Primary change.
- **PGD Compatibility Assessment**: Ensure a seamless migration to PGD with the new Assess command in the PGD CLI. This tool proactively reports any PostgreSQL incompatibilities—especially those affecting logical replication—so you can address them before upgrading to PGD.
- **Upgrade PGD and Postgres with a Single Command**: Leverage the new `pgd node upgrade` command in the PGD CLI to upgrade a node to the latest versions of PGD and Postgres.
- **Ubuntu 24.04 supported**: PGD 5.7.0 now supports Ubuntu 24.04. (23 March 2025)

Features

Component	Version	Description	Addresses
BDR	5.7.0	Added support for failover slots for logical replication. When a PGD node fails or becomes unavailable, consumers can now continue to consume changes from some other node in the cluster. The feature can be turned on by setting the top group option `failover_slot_scope` to `global`. The consumer needs to handle duplicate transactions, but PGD guarantees that every transaction is decoded and sent at least once.	
BDR	5.7.0	Ensured that the `remote_commit_time` and `remote_commit_lsn` are properly reported in the conflict reports.	42273
PGD CLI	5.7.0	Added new CLI command structure for easier access. The new CLI command structure is more intuitive and easier to use. The new structure is a "noun-verb" format, where the noun is the object you want to work with and the verb is the action you want to perform. Full details are available in the CLI command reference.	
PGD CLI	5.7.0	Added a new local assesment feature for local non-PGD nodes to the CLI The new feature allows you to assess the local node for compatibility with PGD. The feature is available as `pgd assess`. Full details are available in the CLI command reference.	
PGD CLI	5.7.0	Added `pgd node upgrade` functionality to the PGD CLI. The new command allows you to upgrade a node to the latest version of PGD and Postgres. It integrates the operation of `bdr_pg_upgrade` into the CLI and is run locally. See pgd node upgrade and inplace upgrades for more information.	
BDR	5.7.0	Fixed an issue whereby concurrent joins of subscriber-only nodes occasionally stopped responding. A node could end up waiting for the local state of another concurrently joined node to advance, which caused the system to stop responding.	42964
BDR	5.7.0	Ubuntu 24.04 is now supported. Packages are now available for Ubuntu 24.04 for all PGD components.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Enhancements

Component	Version	Description
BDR	5.7.0	Narrowed down `bdr.node_slots` output to list only relevant slots. The slots are displayed based on the node type, its role, and the cluster topology.
BDR	5.7.0	Added `target_type` column to `bdr.node_slots` view to indicate slot purpose/status.
BDR	5.7.0	Improved performance of DML and other operations on partitioned tables. Many code paths touching partitioned tables were performing costly checks to support additional table access methods. This code was adjusted to make the most common case (heap) the fastest.
BDR	5.7.0	Improved `bdr_init_physical` to be able to run without superuser. Now only the `bdr_superuser` is required.
PGD CLI	5.7.0	Added new CLI commands for adding removing and updating commit scopes. The new commands are `pgd commit-scope show`, `pgd commit-scope create`, `pgd commit-scope update` and `pgd commit-scope drop`. Full details are available in the CLI command reference.
PGD CLI	5.7.0	Added support for legacy CLI command structure in the updated PGD CLI. The legacy CLI command structure is still supported in the updated PGD CLI. The legacy command support is available for a limited time and will be removed in a future release. It is implemented as a wrapper around the new commands.
PGD CLI	5.7.0	Added new subcommands to PGD CLI `node` and `group` for getting options. The new subcommands are `pgd node get-options` and `pgd group get-options`. Full details are available in the CLI command reference.
PGD CLI	5.7.0	Added new output formatting options `psql` and `markdown` to the PGD CLI. The new options allow you to format the output of the CLI commands in a psql-like or markdown format. Format options are now `json`, `psql`, `modern`, `markdown`, `simple` and defaults to `simple`.
BDR	5.7.0	Removed redundant `WARNING` when executing `ALTER SEQUENCE`. The message now only appears when creating the sequence.

Bug Fixes

Component	Version	Description	Addresses
BDR	5.7.0	Fixed a server panic by ensuring that catalog lookups aren't performed in a callback that gets called very late in the commit cycle.	
BDR	5.7.0	Fixed an unintentional timed wait for a synchronous logical replication that resulted in unusually high latency for some transactions.	42273
BDR	5.7.0	The `bdr.group_camo_details` view now only lists data nodes belonging to the CAMO group. The `bdr.group_camo_details` view now only lists data nodes belonging to the CAMO commit scope group. Previously, the view could include data nodes were not part of the CAMO group, logical standby nodes, Subscriber-Only nodes and witness nodes.	45354

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.7.0	Improved PostgreSQL 17 compatibility. Internal tables managed by autopartition that were created before the upgrade to PG17 were missing a `rowtype` entry into `pg_depend`. This issue caused errors after upgrading to PG17.	44401
BDR	5.7.0	Fixed a bug where parting stopped responding with consensus timeout or consensus errors. This fix also ensures parting doesn't stop responding when any of the nodes restart when part is in progress. Origin LSNs don't show up as 0/0 in log messages.	42056
BDR	5.7.0	Fixed a memory leak in a global hook. This bug could cause memory to leak even if `bdr.so` is just loaded and the extension isn't installed.	43678
BDR	5.7.0	Fixed a bug where subgroup member part prevented new nodes from joining. This fix ensures that if a subgroup member is parted while Raft subgroup routing is active, then another node can subsequently join that subgroup.	
BDR	5.7.0	Fixed a case where galloc sequence overflow wasn't being caught correctly. This bug resulted in `nextval` call being stuck.	44755
BDR	5.7.0	Fixed group slot movement for witness and data nodes in presence of subscriber-only nodes and witness nodes. For PGD 5.6.0 and later, there are no subscriptions from a subscriber-only node to a witness node. This caused a problem with movement of group slot on data nodes and witness nodes in the presence of subscriber-only nodes in the cluster. This bug could cause WAL to be held on both witness nodes and data nodes when there's a subscriber-only node in the cluster.	
BDR	5.7.0	Fixed a bug where conflict resolution functions were executed also on the witness nodes.	
BDR	5.7.0	Fixed a bug where `bdr_init_physical` stopped responding when `synchronous_commit` is set to `remote_write/remote_apply`. `bdr_init_physical` disables synchronous replication on a new node by resetting `synchronous_standby_names` to an empty string. A warning message reminds you to set `synchronous_standby_names` as needed.	44760
PGD Proxy	5.7.0	Fixed proxy regression by improving dsn name support for read nodes A regression in the way read nodes were identified in the proxy in 6.5.1 was fixed by enabling support for different values in the `dsn` field's host and the node_name.	
BDR	5.7.0	Fixed a bug to handle additional replication sets on witness nodes. The witness node now only cares about the top replication set and thus allows it to miss replications sets and not error out.	41776, 44527
BDR	5.7.0	Changed origin deletion to be done asynchronously when optimized topology is enabled. In an optimized topology, origin names now use the generation ID of the node. This fixes an inconsistency in which some transactions can be lost or sent twice when a node is parted.	
BDR	5.7.0	Fixed a crash during upgrades in a mixed-version cluster. Upgrading from versions earlier than 5.6.0 to 5.6.0 and later in a mixed-version cluster with a standby or a node joining/parting could cause a crash.	
BDR	5.7.0	Unsupported `ALTER TABLE` command on materialized views is no longer replicated. Replication no longer becomes stuck when the command is issued.	
BDR	5.7.0	Disallowed `GRANT` on BDR objects to non-BDR users.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.7.0	Improved maintenance of the `bdr.leader` table.	

Deprecations

Component	Version	Description
PGD CLI	5.7.0	Deprecated proxy commands in new PGD CLI command structure. The proxy commands are deprecated in the new CLI command structure. The proxy commands are still available in the legacy CLI command structure. Proxy options can be set using the `pgd group set-option` command.
PGD CLI	5.7.0	Removed `yaml` output as an option in PGD CLI The `yaml` output option is removed from the PGD CLI. The `json` output option is still available.

Other

Component	Version	Description
BDR	5.7.0	Added a GUC to support upgrade to 5.7.0 for clusters with optimized topology (a preview feature). An upgrade to 5.7.0 from clusters that have `bdr.force_full_mesh` set to `off` to enable optimized topology (a preview feature) must first set this GUC to `on` and then upgrade. After the entire cluster upgrades, this GUC can be set to `off` again to enable optimized topology. Having this GUC set to `off` during upgrade isn't supported.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.11 EDB Postgres Distributed 5.6.1 release notes

Released: 25 November 2024

EDB Postgres Distributed 5.6.1 includes a number of enhancements and bug fixes.

Highlights

- Postgres 17 support
- ARM64 processor support

Features

Component	Version	Description
BDR	5.6.1	Added Postgres 17 support Support for Postgres 17 has been added for all flavors (PostgreSQL, EDB Postgres Extended, and EDB Postgres Advanced Server) starting with version 17.2.
BDR	5.6.1	Added ARM64 processor Support Support ARM architecture for EDB Postgres Distributed on Debian 12 and RHEL 9.

Enhancements

Component	Version	Description
BDR	5.6.1	Added `bdr.wait_node_confirm_lsn()`. The function `bdr.wait_node_confirm_lsn()` has been introduced to wait until a specific node reaches a designated Log Sequence Number (LSN). It first checks the `confirmed_flush_lsn` of the replication slot for the specified node. If that information is not available, the function connects to the node and queries `pg_replication_origin_progress()`, using the invoking node as the origin. If the `nodename` parameter is NULL, the function will wait for all nodes to reach the specified LSN. If the `target` LSN is NULL, it will wait for the current `wal_flush_lsn`.
BDR	5.6.1	Improvements made in SO Node Management and Progress Tracking. An update addresses the movement of group slots in SO nodes, ensuring they don't appear as peers in progress updates. Improvements include enhanced watermark management for SO leaders in the Optimized Topology configuration, where write leaders now include watermarks in their updates. Watermarks are broadcasted to simplify progress tracking on idle clusters. The peer progress mapping for SO nodes has been corrected, and the tap test for group slot movement has been revised. Additionally, the `bdr_get_all_origins` function now considers SO node origins.
BDR	5.6.1	LSN Progress in Optimized Topology Configurations is now communicated. While there are no connections from non-leader data nodes to subscriber-only nodes in an optimized topology configuration, the LSN progress of all data nodes is periodically communicated to these subscriber-only nodes through logical replication.
BDR	5.6.1	Some DDL commands are now allowed by `bdr.permit_unsafe_commands` when set. The `bdr.permit_unsafe_commands` parameter now allows some DDL commands that were previously disallowed. Specifically `ALTER COLUMN...TYPE...USING` can now be permitted if the user knows the operation is safe.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Bug Fixes

Component	Version	Description	Addresses
BDR	5.6.1	Addressed walsender crash that happend during configuration reload. Ensure that pglogical GUCs are overridden only when operating within the pglogical worker. If this is not the case, MyPGLogicalWorker will be NULL, resulting in a segmentation fault when the walsender attempts a configuration reload from the pgl_wait_for_standby_confirmation() function.	42100
BDR	5.6.1	Fixed unintended eager connection related to consensus connections among Subscriber Only group members The msgbroker module used to establish consensus connections lazily, meaning that connections were created only when the first message was sent to a specific destination. This method negatively affected the latency of Raft leader elections. The behavior was modified to create connections to consensus peers eagerly. However, this change resulted in an unintended consequence: a fully meshed consensus network among subscriber-only nodes, which may conflict with customer network designs. This patch keeps the eager connection setup but limits it to voting nodes only, reverting to a lazy connection setup for non-voting nodes.	42041
BDR	5.6.1	Fixed autopatition task scheduling. To improve reliability, shuffle the scheduling of autopartition tasks. This way, tasks that are prone to failure won't consistently impact the success of other tasks.	41998
BDR	5.6.1	Fixed parting subscription with standbys. The parting subscription used to hang, failing to wait for standbys when the bdr.standby_slot_names parameter was defined.	41821
BDR	5.6.1	Fixed parting SO node with multiple origins. All relevant origins must be removed when parting SO node. With Optimized Topology, parting an SO node should result in removing all origins it has, not just the one related to its SO group leader. When parting a data node, even though there is no subscription to it from SO node, the origin should be removed. DO not make SO node target of a part catchup subscription when Optimized Topology is enabled.	
BDR	5.6.1	Stopped creation of slots for subscriber only nodes on witness nodes. Subscriber only nodes should not have slots on witness nodes.	
BDR	5.6.1	Ensure no waiting for DEGRADE timeout when in an already degraded state. When using commit scope with DEGRADE clause, if system detects that it's in degraded state, transactions should start in the DEGRADE mode. This ensures that the timeout is not applied on every commit.	
PGD Proxy	5.6.1	Fixed routing strategy for read nodes. Corrected routing strategy for read nodes after a network partition.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.12 EDB Postgres Distributed 5.6.0 release notes

Released: 15 October 2024

EDB Postgres Distributed 5.6.0 includes a number of enhancements and bug fixes.

Highlights

- Improved observability with new monitoring functions and SQL views.
- Improvements to commit scopes including:
  - GROUP COMMIT and SYNCHRONOUS COMMIT support graceful degrading using DEGRADE ON.
  - ORIGIN_GROUP support and commit scope inheritance simplify commit scope creation.
  - Improved synchronous commit behavior around deadlocks.
  - Metrics for commit scope performance and state.

- Optimized Topology support for Subscriber-only groups and nodes. (preview)
- Improved Postgres compliance with support for:
  - Exclusion Constraints
  - REINDEX replications
  - createrole_self_grant
  - column reference in DEFAULT expressions
  - CREATE SCHEMA AUTHORIZATION

- Streaming Transaction support with Decoding Worker.

Enhancements

Component	Version	Description	Addresses
BDR	5.6.0	Decoding Worker supports Streaming Transactions One of the main advantages of streaming is that the WAL sender sends the partial transaction before it commits, which reduces replication lag. Now, with streaming support, the WAL decoder does the same thing, but it streams to the LCRs segments. Eventually, the WAL sender will read the LCRs and mimic the same behavior of streaming large transactions before they commit. This provides the benefits of decoding worker, such as reduced CPU and disk space, as well as the benefits of streaming, such as reduced lag and disk space, since ".spill" files are not generated. The WAL decoder always streams the transaction to LCRs, but based on downstream requests, the WAL sender either streams the transaction or just mimics the normal BEGIN..COMMIT scenario. In addition to the normal LCRs segment files, we create streaming files with the starting names `TR_TXN_<file-name-format>` and `CAS_TXN_<file-name-format>` for each streamed transaction.	
BDR	5.6.0	Introduce several new monitoring views There are several view providing new information as well as making some existing information easier to discover: - `bdr.stat_commit_scope` : Cumulative statistics for commit scopes. - `bdr.stat_commit_scope_state` : Information about current use of commit scopes by backends. - `bdr.stat_receiver` : Per subscription receiver statistics. - `bdr.stat_writer` : Per writer statistics. There can be multiple writers for each subscription. This also includes additional information about the currently applied transaction. - `bdr.stat_raft_state` : The state of the Raft consensus on the local node. - `bdr.stat_raft_followers_state` : The state of the followers on the Raft leader node (empty on other nodes), also includes approximate clock drift between nodes. - `bdr.stat_worker` : Detailed information about PGD workers, including what the operation manager worker is currently doing. - `bdr.stat_routing_state` : The state of the connection routing which PGD Proxy uses to route the connections. - `bdr.stat_routing_candidate_state` : Information about routing candidate nodes on the Raft leader node (empty on other nodes).	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.6.0	Support conflict detection for exclusion constraints This allows defining `EXCLUDE` constraint on table replicated by PGD either with `CREATE TABLE` or with `ALTER TABLE` and uses similar conflict detection to resolve conflicts as for `UNIQUE` constraints.	
BDR	5.6.0	Detect and resolve deadlocks between synchronous replication wait-for-disconnected sessions and replication writer. This will cancel synchronous replication wait on disconnected sessions if it deadlocks against replication, preventing deadlocks on failovers when using synchronous replication. This only affects commit scopes, not synchronous replication configured via `synchronous_standby_names`.	
BDR	5.6.0	Add bdr.bdr_show_all_file_settings() and bdr.bdr_file_settings view Fix: Correct privileges for bdr_superuser. Creating wrapper SECURITY DEFINER functions in the bdr schema and granting access to bdr_superuser to use those: - bdr.bdr_show_all_file_settings - bdr.bdr_file_settings	
BDR	5.6.0	Add create/drop_commit_scope functions Add functions for creating and dropping commit scopes that will eventually deprecate the non-standard functions for adding and removing commit scopes. Notify the user that these will be deprecated in a future version, suggesting the use of the new versions.	
BDR	5.6.0	Grant additional object permissions to role "bdr_monitor". Permissions for the following objects have been updated to include SELECT permissions for role "bdr_monitor": bdr.node_config	
BDR	5.6.0	Add `bdr.raft_vacuum_interval` and `bdr.raft_vacuum_full_interval` GUCs to control frequency of automatic Raft catalog vacuuming. This update introduces GUCs to regulate the frequency of automatic vacuuming on the specified catalogs. The GUC `bdr.raft_vacuum_interval` determines the frequency at which tables are examined for VACUUM and ANALYZE. Autovacuum GUCs and table reloptions are utilized to ascertain the necessity of VACUUM/ANALYZE. The `bdr.raft_vacuum_full_interval` initiates VACUUM FULL on the tables. Users have the ability to deactivate VACUUM FULL if regular VACUUM suffices to manage bloat.	40412
BDR	5.6.0	Add "node_name" to "bdr.node_config_summary" Add "node_name" to the view "bdr.node_config_summary". This makes it consistent with other summary views, which report the name of the object (node, group, etc.) for which the summary is being generated.	
BDR	5.6.0	bdr_init_physical: improve local node connection failure logging Ensure that bdr_init_physical emits details about connection failure if the "--local-dsn" parameter is syntactically correct but invalid, e.g., due to an incorrect host or port setting.	
BDR	5.6.0	`bdr_config`: add PG_FLAVOR output `bdr_config` now shows the PostgreSQL "flavor" which BDR was built against, one of: - COMMUNITY - EPAS - EXTENDED - BDRPG	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.6.0	Enhance warning messages Enhance messages issued during DML and DDL lock acquisition.	
BDR	5.6.0	Do not send Raft snapshot very aggressively Avoid sending Raft snapshots too frequently as it can slow down follower nodes. Limit the snapshot rate to once in every election timeout, unless there is no other communication between the nodes, in which case send a snapshot every 1/3rd of the election timeout. This will help all nodes keep pace with the leader and improve CPU utilization.	37725
BDR	5.6.0	Group-Specific Configuration Options It is now possible to set akk top-level and subgroup level options. The following options are available for top-both groups: • check_constraints • enable_wal_decoder • num_writers • streaming_mode • enable_raft Subgroups inherit settings from their parent group, but can override them if set in the subgroup.	37725
BDR	5.6.0	Subscriber-only node groups have a leader Subscriber-only node groups have a leader elected by top-level Raft. There is now a bdr.leader catalog that tracks leadership of subgroups and subscriber-only nodes. If the node that is the leader of a subscriber-only node group goes down or becomes unreachable, a new leader is elected from that group.	
BDR	5.6.0	Optimized topology for subscriber-only nodes via the leader of the subscriber-only node group Subscriber-only nodes earlier used to have subscriptions to each data node. Now if optimized topology is enabled, only the leaders of subscriber-only node groups have subscriptions to routing leaders of data node subsgroups. The subscriber only nodegroup leaders route data to other nodes of that subscriber-only nodegroup. This reduces the load on all data nodes so they do not have to send data to all subscriber-only nodes. The GUC `bdr.force_full_mesh=off` enables this optimized topology. This GUC variable is on by default, retaining pre-5.6.0 behavior.	
BDR	5.6.0	Introduce new subscription types to support optimized topology New subscription types that forward data from all nodes of the subgroup via a routing leader (mode: l), and those that forward data from the entire cluster via a subscriber-only group leader (mode: w) are introduced.	
BDR	5.6.0	Introduce version number and timestamp for write leader A write leader has a version. Every time a new leader is elected, the version is incremented and timestamp noted via Raft. This is to build a foundation for better conflict resolution.	
BDR	5.6.0	Allow use of column reference in DEFAULT expressions Using column references in default expressions is now supported, this is particularly useful with generated columns, for example: `ALTER TABLE gtest_tableoid ADD COLUMN c regclass GENERATED ALWAYS AS (tableoid) STORED;`	
BDR	5.6.0	Support replication of REINDEX Both REINDEX and REINDEX CONCURRENTLY are now replicated commands.	
BDR	5.6.0	Fix receiver worker being stuck when exiting Receiver worker could get stuck when exiting, waiting for a writer that never actually started. This could on rare occasions break replication after configuration changes until Postgres was restarted.	
BDR	5.6.0	Reduce performance impact of PGD specific configuration parameters that are sent to client Changes to values of variables `bdr.last_committed_lsn`, `transaction_id` and `bdr.local_node_id` are automatically reported to clients when using CAMO or GROUP COMMIT. This has now been optimized to use less resources.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.6.0	Allow use of commit scopes defined in parent groups When there is a commit scope defined for top-level group, it can be used by any node in a subgroup and does not need to be redefined for every subgroup anymore. This is particularly useful when combined with `ORIGIN\_GROUP` keyword to reduce the complexity of commit scope setup.	
PGD CLI	5.6.0	Use bdr.bdr_file_settings view in verify-settings Use bdr.bdr_file_settings view to get the current settings for the proxy.	

Bug Fixes

Component	Version	Description	Addresses
BDR	5.6.0	Fixed buffer overrun in the writer Include an extra zero byte at the end of a column value allocation in shared memory queue insert/update/delete messages.	98966
BDR	5.6.0	Fixes for some race conditions to prevent node sync from entering a hung state with the main subscription disabled.	
BDR	5.6.0	Do not accidentally drop the autopartition rule when a column of the autopartitioned table is dropped. When ALTER TABLE .. DROP COLUMN is used, the object_access_hook is fired with `classId` set to RelationRelationId, but the `subId` is set to the attribute number to differentiate it from the DROP TABLE command. Therefore, we need to check the subId field to make sure that we are not performing actions that should only be triggered when a table is dropped.	40258
BDR	5.6.0	Adjust `bdr.alter_table_conflict_detection()` to propagate correctly to all nodes Ensure that the propagation of `bdr.alter_table_conflict_detection()` (as well as the related, deprecated `bdr.column_timestamps_(en|dis)able()` functions) is carried out correctly to all logical standbys. Previously, this propagation did not occur if the logical standby was not directly attached to the node on which the functions were executed.	40258
BDR	5.6.0	Prevent a node group from being created with a duplicate name Ensure that a nodegroup is not inadvertently created with the same name as an existing nodegroup. Failure to do so may result in a complete shutdown of the top-level Raft on all nodes, with no possibility of recovery.	
BDR	5.6.0	Prevent spurious "local info ... not found" errors when parting nodes Handle the absence of the expected node record gracefully when a node is being removed, the local node record might have already been deleted, but an attempt could be made to update it anyway. This resulted in harmless "BDR node local info for node ... not found" errors.	
BDR	5.6.0	Prevent a corner-case situation from being misdiagnosed as a PGD version problem Improve Raft error messages to handle cases where nodes may not be correctly participating in Raft.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.6.0	Handling duplicate requests in RAFT preventing protocol breakage When processing RAFT entries, it's crucial to handle duplicate requests properly to prevent Raft protocol issues. Duplicate requests can occur when a client retries a request that has already been accepted and applied by the Raft leader. The problem arose when the leader failed to detect the duplicate request due to historical evidence being pruned.	37725
BDR	5.6.0	Handling Raft Snapshots: Consensus Log When installing or importing a Raft snapshot, discard the consensus log unless it contains an entry matching the snapshot's last included entry and term.	37725
BDR	5.6.0	Be more restrictive about which index to use during replication for REPLICA IDENTITY FULL tables This fixes various index related errors during replication like: 'could not lookup equality operator for type, optype in opfamily' or 'function "amgettuple" is not defined for index "brinidx"'	
BDR	5.6.0	Support `createrole_self_grant` The `createrole_self_grant` configuration option affects inherited grants by newly created roles. In previous versions `CREATE ROLE` / `CREATE USER` replication would not take this into consideration, resulting in different role privileges on different nodes.	
BDR	5.6.0	Allow `CREATE SCHEMA AUTHORIZATION ...` combined with other create operations Previously, this would throw "cannot change current role within security-restricted operation" error	
BDR	5.6.0	Use base type instead of domain type while casting values This prevents errors when replicating UPDATEs for domains defined as NOT VALID where tables contain data which would not be allowed by current definition of such domain.	
Utilities	5.6.0	bdr_pg_upgrade - Create logical slot with twophase set to true for PG 14+	
BDR	5.6.0	Fix inconsistency caused by writer error followed by receiver restart in PG 16	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.13 EDB Postgres Distributed 5.5.1 release notes

Released: 31 May 2024

EDB Postgres Distributed version 5.5.1 is a patch release containing bug fixes for EDB Postgres Distributed.

> **Recommended upgrade**
>
> We recommend that all users of PGD 5 upgrade to PGD 5.5.1. See PGD/TPA upgrades for details.

Bug fixes

Component	Version	Description	Ticket
BDR	5.5.1	Fixed potential data inconsistency issue with mixed-version usage during a rolling upgrade. Backward-incompatible change in PGD 5.5.0 may lead to inconsistencies when replicating from a newer PGD 5.5.0 node to an older version of the PGD node, specifically during the mixed-mode rolling upgrade. This release addresses a backward-compatibility issue in mixed-version operation, enabling seamless rolling upgrades.	
BDR	5.5.1	Disabled auto-triggering of node sync by default. Automatically triggered synchronization of data from a down node caused issues by failing to resume once it came back up. As a precautionary measure, the feature is now disabled by default (PGD setting `bdr.enable_auto_sync_reconcile`).	115110

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.14 EDB Postgres Distributed 5.5.0 release notes

Released: 16 May 2024

EDB Postgres Distributed version 5.5.0 is a minor version of EDB Postgres Distributed.

> **Recommended upgrade**
>
> We recommend that all users of PGD 5 upgrade to PGD 5.5. See PGD/TPA upgrades for details.

Highlights of EDB Postgres Distributed 5.5.0

Highlights of this 5.5.0 release include:

- Read scalability enhancements in PGD Proxy which allow read-only queries to be routed to nodes that are members of a read-only pool. This feature can improve the overall performance of the PGD cluster.

Compatibility

> **EDB server version compatibility**
>
> This version requires the recently released Postgres versions 14.10, 15.4, or 16.1 (or later) of EDB Postgres Advanced Server or EDB Postgres Extended Server. No such restrictions exist for Community Postgres Server.
>
> Package managers on Debian, RHEL, and SLES pull in the required EDB Postgres Advanced Server or EDB Postgres Extended upgrades with an upgrade of EDB Postgres Distributed.

Features

Component	Version	Description	Ticket
BDR	5.5.0	Added support for read-only proxy routing.	
BDR	5.5.0	Improved stability of routing leader selection by using Raft heartbeat for connectivity check.	
CLI	5.5.0	Added PGD CLI binaries for macOS.	
Proxy	5.5.0	Added support for read-only proxy routing.	

Enhancements

Component	Version	Description	Ticket
BDR	5.5.0	Improved bulk INSERT/UPDATE/DELETE performance by sending multiple messages together in a group rather than individually.	
BDR	5.5.0	Changes received by the writer now aren't saved to a temporary file.	
BDR	5.5.0	BDR now logs completion of an extension upgrade.	
BDR	5.5.0	Added restrictions for group commit options.	
BDR	5.5.0	Each autopartition task is now executed in its own transaction.	RT101407/35476
BDR	5.5.0	DETACH CONCURRENTLY is now used to drop partitions.	RT101407/35476
BDR	5.5.0	Node group creation on a node bad state is now disallowed.	
BDR	5.5.0	Granted additional object permissions to role `bdr_read_all_stats`.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Ticket
BDR	5.5.0	Improved stability of manager worker and Raft consensus by not throwing error on non-fatal dynamic shared memory read failures.	
BDR	5.5.0	Improved stability of Raft consensus and workers by handling dynamic shared memory errors in the right place.	
BDR	5.5.0	The number of changes processed by writer in a large transaction is now exposed in `bdr.writers`.	
BDR	5.5.0	`bdr_init_physical` now stops the initial replication connection and starts it only when needed.	RT102828/35305
BDR	5.5.0	`bdr_superuser` is now granted use of `pg_file_settings` and `pg_show_all_file_settings()`.	
CLI	5.5.0	Added new read scalability related options to JSON output of `show-proxies` and `show-groups` commands.	
CLI	5.5.0	Added new option called `proxy-mode` to `create-proxy` command for read scalability support.	
CLI	5.5.0	Added Raft leader in tabular output of `show-groups` command.	

Bug fixes

Component	Version	Description	Ticket
BDR	5.5.0	Improved handling of node group configuration parameter "check_constraints".	RT99956/31896
BDR	5.5.0	Fixed incorrect parsing of pre-commit message that caused nodes to diverge on commit decision for group commit transactions.	
BDR	5.5.0	Fixed an issue to prevent potential segfault in `bdr.monitor_group_versions()`	RT102290/34051
BDR	5.5.0	BDR now correctly elects a new leader when the current leader gets route_writes turned off.	
BDR	5.5.0	`bdr.remove_commit_scope()` now handles non-existent commit scope.	
BDR	5.5.0	An improved queue flush process now prevents unexpected writer terminations.	RT98966/35447
BDR	5.5.0	Fixed multi-row conflict accidentally deleting the wrong tuple multiple times .	
BDR	5.5.0	Fixed receiver to send status update when writer is blocked, avoiding slot disconnect.	
BDR	5.5.0	Fixed minor memory leak during `bdr_join_node_group_sql`.	
BDR	5.5.0	Node joining with witness and standby nodes as source nodes is now disallowed.	
BDR	5.5.0	Now use `bdr.default_sequence_kind` when updating sequence kind of existing sequences upon node creation.	
BDR	5.5.0	Fixed a bug preventing some trusted extension management commands (CREATE/ALTER) from being replicated.	
BDR	5.5.0	Fixed a non-critical segfault which could occur in upgrades from BDR 3.7.	
BDR	5.5.0	Fixed an issue to manage rights elevation for trusted extensions.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.15 EDB Postgres Distributed 5.4.1 release notes

Released: 03 Apr 2024

EDB Postgres Distributed version 5.4.1 is a patch release containing bug fixes for EDB Postgres Distributed.

> **Recommended upgrade**
>
> We recommend that all users of PGD 5 upgrade to PGD 5.4.1. See PGD/TPA upgrades for details.

Bug fixes

Component	Version	Description	Tickets
BDR	5.4.1	Fixed WAL retention logic to prevent disk space issues on a PGD node with version 5.4.0 and Postgres 16, PGE 16, and EDB Postgres Advanced Server 16. A fix was implemented to ensure proper cleanup of write-ahead logs (WAL) even after reaching a size of 4 GB on a node. A change in version 5.4.0 resulted in WAL being retained indefinitely after reaching this threshold. This issue is specific to PGD 5.4.0 in conjunction with Postgres 16, PGE 16, and EDB Postgres Advanced Server 16.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.16 EDB Postgres Distributed 5.4.0 release notes

Released: 05 Mar 2024

EDB Postgres Distributed version 5.4.0 is a minor version of EDB Postgres Distributed.

> **Recommended upgrade**
>
> We recommend that all users of PGD 5 upgrade to PGD 5.4. See PGD/TPA upgrades for details.

Highlights of EDB Postgres Distributed 5.4.0

Highlights of this 5.4.0 release include improvements to:

- Group Commit, aiming to optimize performance by minimizing the effect of a node's downtime and simplifying overall operating of PGD clusters.
- `apply_delay`, enabling the creation of a delayed read-only replica for additional options for disaster recovery and to mitigate the impact of human error, such as accidental DROP table statements.

Compatibility

> **EDB Server version compatibility**
>
> This version requires the recently released Postgres versions 14.10, 15.4, or 16.1 (or later) of EDB Postgres Advanced Server or EDB Postgres Extended Server. No such restrictions exist for PostgreSQL Server.
>
> Package managers on Debian, RHEL, and SLES pull in the required EDB Postgres Advanced Server or EDB Postgres Extended upgrades with an upgrade of EDB Postgres Distributed.

Features

Component	Version	Description	Addresses
BDR	5.4.0	PGD now automatically detects and synchronizes all available nodes to the furthest ahead node for transactions originating from failed or disconnected node.	
BDR	5.4.0	PGD now automatically resolves pending Group Commit transactions when the originating node fails or disconnects, ensuring uninterrupted transaction processing within the cluster.	
BDR	5.4.0	Added ability to set the `apply_delay` group option on subgroups, enabling adding of delayed subscriber-only nodes.	
BDR	5.4.0	Loading data using EDB*Loader (except direct mode) is now supported.	

Bug fixes

Component	Version	Description	Addresses
BDR	5.4.0	Fixed memory leaks when running a query on some or all nodes.	
BDR	5.4.0	Resolved an issue of high CPU usage for consensus processes.	RT97649
BDR	5.4.0	Improved WAL retention logic when a part_node occurs.	
BDR	5.4.0	Witness nodes will now automatically not synchronize structure when joining a group.	
BDR	5.4.0	bdr.create_node() / bdr.alter_node() now give a hint when an invalid node kind is used.	
BDR	5.4.0	Fixed transactions PREPARE/COMMIT/ABORT order with Parallel Apply enabled.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.4.0	DDL replication now takes into account more of the Postgres configuration options that are set in the original session or transaction to provide more consistent results of the DDL execution. Added `standard_conforming_strings`, `edb_redwood_date`, `default_with_rowids`, and `check_function_bodies`.	
BDR	5.4.0	Improved `pgd_bench` cluster initialization and command line help output.	
BDR	5.4.0	Restoring a node group from a consensus snapshot now correctly applies option changes (number of writers, streaming, and apply_delay) to local subscriptions.	
BDR	5.4.0	Fixed debug logging of pg_ctl enabling output capture for debugging purposes in `bdr_init_physical`.	
BDR	5.4.0	Fixed assertion failure when TargetColumnMissing conflict occurs in a Group Commit transaction.	
BDR	5.4.0	Fixed detection of UpdateOriginChange conflict to be more accurate.	
BDR	5.4.0	Added support for timeout for normal Group Commit transaction.	
BDR	5.4.0	Fixed error handling in writer when there are lock timeouts, conflicts, or deadlocks with and without Group Commit transactions.	
BDR	5.4.0	Now allow the origin of Group Commit transactions to wait for responses from all the required nodes before taking an abort decision.	
BDR	5.4.0	Eager transactions abort correctly after Raft was disabled or not working and has recovered.	RT101055
BDR	5.4.0	Increased default `bdr.raft_keep_min_entries` to 1000 from 100.	
BDR	5.4.0	Now allow the origin of Group Commit transactions to wait for responses from all the required nodes before taking an abort decision.	
BDR	5.4.0	Now run ANALYZE on the internal Raft tables.	RT97735
BDR	5.4.0	Fixed segfault in I2PC concurrent abort case.	RT93962
BDR	5.4.0	Now avoid bypassing other extensions in BdrProcessUtility when processing COPY..TO.	RT99345
BDR	5.4.0	Ensured that consensus connection are handled correctly.	RT97649
BDR	5.4.0	Fixed memory leaks while running monitoring queries.	RT99231, RT95314
BDR	5.4.0	The `bdr.metrics_otel_http_url` and `bdr.trace_otel_http_url` options are now validated at assignment time.	
BDR	5.4.0	When `bdr.metrics_otel_http_url` and `bdr.trace_otel_http_url` don't include paths, `/v1/metrics` and `/v1/traces` are used, respectively.	
BDR	5.4.0	Setting `bdr.trace_enable` to `true` is no longer required to enable OTEL metrics collection.	
Proxy	5.4.0	Now use route_dsn and perform sslpassword processing while extracting write leader address.	RT99700
Proxy	5.4.0	Now log client and server addresses at debug level in proxy logs.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.17 EDB Postgres Distributed 5.3.0 release notes

Released: 14 Nov 2023

EDB Postgres Distributed version 5.3.0 is a minor version of EDB Postgres Distributed.

> **Recommended upgrade**
>
> We recommend that all users of PGD 5 upgrade to PGD 5.3. See PGD/TPA upgrades for details.

Highlights of EDB Postgres Distributed 5.3.0

- Support for PostgreSQL 16 server, EDB Postgres Extended Server 16, and EDB Postgres Advanced Server 16

Compatibility

> **EDB Server version compatibility**
>
> This version requires the recently released Postgres versions 14.10, 15.4, or 16.1 (or later) of EDB Postgres Advanced Server or EDB Postgres Extended Server. No such restrictions exist for PostgreSQL Server.
>
> Package managers on Debian, RHEL, and SLES pull in the required EDB Postgres Advanced Server or EDB Postgres Extended upgrades with an upgrade of EDB Postgres Distributed.

Features

Component	Version	Description	Addresses
PGD	5.3.0	Added support for PostgreSQL 16 server, EDB Postgres Extended Server 16, and EDB Postgres Advanced Server 16.	

Enhancements

Component	Version	Description	Addresses
Proxy	5.3.0	Added the default service unit file to package	
BDR	5.3.0	Dependencies on EDB Postgres Advanced Server or EDB Postgres Extended are now reflected in packages.	

Bug fixes

Component	Version	Description	Addresses
BDR	5.3.0	Ensure that the WalSender process doesn't request locks on the partitions, thus avoiding a deadlock with user process waiting on sync commit.	RT97952
BDR	5.3.0	Consider only CAMO transactions to be asynchronous when the CAMO setup was degraded to local mode. This solves the split-brain problem when deciding fate of transactions that happened during failover.	RT78928
BDR	5.3.0	Handle partitions with different attribute numbers when batch inserting.	RT99115
BDR	5.3.0	Fixed unsafe CAMO decisions in remote_write mode.	
BDR	5.3.0	Taskmgr process now respects SIGINT.	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Description	Addresses
BDR	5.3.0	Speeded up manager process startup by limiting the amount of WAL read for loading commit decisions.	
BDR	5.3.0	Physical joins now clean up stale records in `bdr.taskmgr_local_work_queue`.	
BDR	5.3.0	Fixed a bug in copying `bdr.autopartition_rules` during logical join.	
BDR	5.3.0	Override `bdr.ddl_replication=off` in taskmgr worker.	
BDR	5.3.0	Avoid a potential deadlock between `bdr.autopartition_wait_for_partitions()` and taskmgr.	
BDR	5.3.0	Fixed writer missing updates in streaming mode with TDE enabled.	
BDR	5.3.0	Block new EDB Postgres Advanced Server automatic partitioning on PGD cluster.	
BDR	5.3.0	Allow existing automatically partitioned tables when cluster is created or upgraded.	
BDR	5.3.0	Block PGD autopartition on EDB Postgras Advanced Server INTERVAL partitioned table.	
BDR	5.3.0	Ensure that replication doesn't break when `bdr.autopartition()` is invoked on a mixed version cluster running with 3.7.23 and 4.3.3/5.3	
BDR	5.3.0	Fixed default selective replication behavior for data groups. The data groups are supposed to publish only replication sets of the group or any parent groups by default, which mirrors what they subscribe to.	
BDR	5.3.0	Fixed memory leak in LCR file TDE encryption.	
BDR	5.3.0	Fixed memory leak in streaming transaction processing.	
BDR	5.3.0	Allow force parting of nodes that are already being parted normally.	
BDR	5.3.0	PART_CATCHUP is now more resilient to replication slot and node_catchup_info conflict.	
BDR	5.3.0	Fixed row filter failure for partitions created after a table column was dropped.	RT95149
BDR	5.3.0	Avoid aborting a group commit transaction on receiving the first abort response. The other nodes are given a chance to respond, and transaction can succeed if the required responses are received.	
BDR	5.3.0	Ensure that replication receiver worker reloads configuration correctly when `pg_reload_conf()` is called.	
BDR	5.3.0	Prevent duplicate Raft request ID generation which could break replication.	
BDR	5.3.0	Fixed several rare memory access issues that could potentially cause crashes of workers.	
BDR	5.3.0	Fixed issue where explicit 2PC transactions aborted earlier when encountering conflicts.	RT92897
CLI	5.3.0	Fixed `verify-settings` command if the `shared_preload_libraries` GUC contains file path.	
CLI	5.3.0	Show replslots status as `Critical` in `check-health` command when PGD cluster is reduced to just a witness node.	
Proxy	5.3.0	Always set the server connection close behavior (setLinger(0)). Earlier it was set only on client error.	
Proxy	5.3.0	Fixed the logs fill up issue when all nodes are down in a PGD cluster	
Utilities	1.2.0	Removed the preupgrade step in `bdr_pg_upgrade` that sets the CONNECTION LIMIT to 0 at database level	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.18 EDB Postgres Distributed 5.2.0 release notes

Released: 04 Aug 2023

EDB Postgres Distributed version 5.2.0 is a minor version of EDB Postgres Distributed.

Highlights of EDB Postgres Distributed 5.2.0

- Parallel Apply is now available for PGD's Commit at Most Once (CAMO) synchronous commit scope and improving replication performance.
- Parallel Apply for native Postgres asynchronous and synchronous replication has been improved for workloads where the same key is being modified concurrently by multiple transactions to maintain commit sequence and avoid deadlocks.
- PGD Proxy has added HTTP(S) APIs to allow the health of the proxy to be monitored directly for readiness and liveness. See Proxy health check.

> **Recommended upgrade**
>
> We recommend that users of PGD 5.1 upgrade to PGD 5.2.

> **PostgreSQL version compatibility**
>
> This version is required for EDB Postgres Advanced Server versions 12.15, 13.11, 14.8, and later.

Component	Version	Type	Description
BDR	5.2.0	Feature	Added Parallel Apply for synchronous commit scopes with CAMO.
BDR	5.2.0	Feature	Allow multiple SYNCHRONOUS_COMMIT clauses in a commit scope rule.
BDR	5.2.0	Enhancement	BDR extension now allows transaction streaming with SYNCHRONOUS_COMMIT and LAG CONTROL commit scopes.
BDR	5.2.0	Enhancement	Improved handling of concurrent workloads with Parallel Apply.
BDR	5.2.0	Enhancement	Modified `bdr.stat_subscription` for new columns.
BDR	5.2.0	Bug fix	Fixed an issue by allowing a logical join of node if there are foreign key constraints violations. (RT91745)
BDR	5.2.0	Bug fix	Changed `group_raft_details` view to avoid deadlock possibility.
BDR	5.2.0	Bug fix	Fixed an issue by adding ability to log the extension upgrade.
BDR	5.2.0	Bug fix	Added check for conflicting node names.
BDR	5.2.0	Bug fix	Fixed a crash during Raft manual snapshot restore.
BDR	5.2.0	Bug fix	Fixed an issue whereby BDR extension was attempting to establish consensus connections to parting or parted nodes.
BDR	5.2.0	Bug fix	Fixed `tcp_user_timeout` GUC to use the correct unit.
BDR	5.2.0	Bug fix	Fixed the consensus snapshot compatibility with PGD 3.7. (RT93022)
BDR	5.2.0	Bug fix	Fixed an issue whereby a crash occurred when BDR extension is used with pgaudit.
BDR	5.2.0	Bug fix	Fixed an issue by skipping parting synchronization to witness node.
BDR	5.2.0	Bug fix	Fixed an issue by now generating correct keepalive parameters in connection strings.
BDR	5.2.0	Bug fix	Enabled various scenarios of switching nodes between groups and their subgroups, for example, transition node from a group to any of the nested subgroups.
BDR	5.2.0	Bug fix	Reduced the amount of WAL produced by consensus on idle server.
BDR	5.2.0	Bug fix	Fixed deadlock on autopartition catalogs when a concurrent `DROP EXTENSION` is executing.
BDR	5.2.0	Bug fix	Fixed sporadic failure when dropping extension after node restart
BDR	5.2.0	Bug fix	Added a workaround for crash due to pgaudit bug.
BDR	5.2.0	Bug fix	Fixed deadlock between consensus and global monitoring queries.
BDR	5.2.0	Bug fix	Fixed query cancellation propagation across `bdr.run_on_all_nodes`.
BDR	5.2.0	Bug fix	Fixed an issue by disallowing invoking `bdr.run_on_nodes()`, `bdr.run_on_group()` and `bdr.run_on_all_nodes()` on parted nodes.
CLI	5.2.0	Enhancement	Added new GUCs verification in `verify-settings` command.
CLI	5.2.0	Bug fix	Fixed an issue by truncating the long value of GUC in tabular output of `verify-settings`.
CLI	5.2.0	Bug fix	Fixed `connect_timeout` issue when `sslmode=allow` or `sslmode=prefer` by upgrading database driver library version.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Type	Description
Proxy	5.2.0	Feature	Added HTTP(S) APIs for Proxy health check.
Proxy	5.2.0	Enhancement	Improved route change events handling mechanism.
Proxy	5.2.0	Enhancement	Added retry mechanism on consensus query error.
Proxy	5.2.0	Bug fix	Fixed `connect_timeout` issue when `sslmode=allow` or `sslmode=prefer` by upgrading database driver library version.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.19 EDB Postgres Distributed 5.1.0 release notes

Released: 16 May 2023

EDB Postgres Distributed version 5.1.0 is a minor version of EDB Postgres Distributed. This version addresses security vulnerabilities in dependencies for PGD Proxy and PGD CLI.

Highlights of EDB Postgres Distributed 5.1

- **Synchronous Commit** is now available in PGD's unified COMMIT SCOPE syntax. Modeled on Postgres's legacy synchronous commit option, PGD Synchronous Commit allows DBAs to take advantage of the finer-grained commit and sync management. This addition complements the existing Group Commit, CAMO, and Lag Control commit scope options.
- Fixes to **priority-based proxy routing** now enable better handling of failover. You can now configure the grace period for proxies through PGD CLI, allowing you to tune proxy response to losing the Raft leader. To accompany that, Raft events are visible in the PGD CLI's `show-events` command, showing the event, source, and subtype.
- `bdr.drop_node_group()` adds support for removing empty node groups using the PGD SQL interface.

> **Recommended upgrade**
>
> We recommend that users of PGD 5.0 upgrade to PGD 5.1.

> **PostgreSQL version compatibility**
>
> This version is required for EDB Postgres Advanced Server versions 12.15, 13.11, 14.8, and later.

Component	Version	Type	Description
BDR	5.1.0	Feature	Added pid to the log message emitted upon writer process death.
BDR	5.1.0	Feature	Added group name in the bdr.event_summary view.
BDR	5.1.0	Feature	Added SLES support. SLES 15sp4 is now supported.
BDR	5.1.0	Feature	Added subscription status column to the group subscription summary view. This feature allows you to distinguish whether NULL values are due to a node being down or a subscription being disabled.
BDR	5.1.0	Feature	Added NOT group filter to Group Commit. This feature allows you to invert the meaning of a group filter to include all nodes except the ones in specified groups.
BDR	5.1.0	Feature	Added `bdr.drop_node_group`. You can now drop empty node groups.
BDR	5.1.0	Feature	Added SYNCHRONOUS_COMMIT to commit scopes. This feature allows dynamic synchronous_commit-like behavior for replication.
BDR	5.1.0	Feature	Added event_node_name column to `bdr.event_summary`.
BDR	5.1.0	Feature	Added write leader election to event history. Added information about the node that's elected as a write leader for each group in the event_history catalog. Also improved the reporting of raft instance ids in the event_detail of event_history.
BDR	5.1.0	Feature	Added ability to allow exporting and importing of other Raft instance snapshots. This feature allows exporting and importing snapshots for other instances and not only top Raft instances.
BDR	5.1.0	Bug fix	Fixed memory leak in consensus process. (RT91830)
BDR	5.1.0	Bug fix	Fixed issue where a node can be inconsistent with the group after rejoining. If a node was part of a subgroup, parted, and then rejoined to the group, it could be inconsistent with the group. The changes from some nodes of the group were replayed from a wrong starting point, resulting in potential data loss.
BDR	5.1.0	Bug fix	Fixed join and replication when SDW and standby_slot_names are set. (RT89702, RT89536)
BDR	5.1.0	Bug fix	Fixed spurious warnings when processing sequence options. (RT90668)
BDR	5.1.0	Bug fix	Fixed upgrades for nodes with CRDTs.
BDR	5.1.0	Bug fix	Adjusted lag tracking parameters for LCRs from pg_stat_replication.
BDR	5.1.0	Bug fix	Adjusted node routing options defaults based on node kind. This change is related only to the display of the information and not the behavior. For example, witness nodes aren't marked as candidates for receiving writes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Type	Description
BDR	5.1.0	Bug fix	All sequences are now converted to "distributed" during create node.
BDR	5.1.0	Bug fix	Fixed streaming transactions with `standby_slot_names`. This might have led to a subscriber-only node getting ahead of a data node.
BDR	5.1.0	Bug fix	Made priority work properly for routing selection. Previously, node priority was working only if there wasn't a previous leader, which is never the case on failover.
BDR	5.1.0	Bug fix	Fixed the recording of its join as complete for the first node.
BDR	5.1.0	Bug fix	Disabled tracing by default. Tracing was enabled only for initial debugging and was meant to be disabled before 5.0 release.
BDR	5.1.0	Bug fix	Added support for reload configuration for the pglogical receiver. When the server receives a reload signal, the pglogical receiver reloads and applies the configuration changes.
BDR	5.1.0	Bug fix	Improved missing instance error message in `bdr.monitor_group_raft()`.

BDR	5.1.0	Bug fix	Implemented consistent use of tcp keepalives across all BDR connections.
			This change added the following GUCs:
			`bdr.global_connection_timeout`
			`bdr.global_keepalives`
			`bdr.global_keepalives_idle`
			`bdr.global_keepalives_interval`
			`bdr.global_keepalives_count`
			`bdr.global_tcp_user_timeout`
			The defaults are set to fairly conservative values and are subject to adjustments in the future patches.

BDR	5.1.0	Bug fix	Closed Raft connections on no activity after a timeout. This uses wal_sender_timeout/wal_receiver_timeout underneath.
BDR	5.1.0	Bug fix	Made backends that receive Raft messages easily identifiable. Added information in the log message related to Raft backends.
BDR	5.1.0	Bug fix	Fixed issue whereby Parallel Apply might slow down under heavy load.
BDR	5.1.0	Enhancement	Restarting sync workers is now avoided. This fix is to prevent the node join from failing when config changes are made that signal the restart of subscription workers.
PGD Proxy	5.1.0	Enhancement	`application_name` is now set to proxy name if it wasn't set by the user in the connection string for internal db connections.
PGD Proxy	5.1.0	Enhancement	Implemented the new `consensus_grace_period` proxy option, which is the duration for which a proxy continues to route to the current write leader (if it's available) upon loss of a Raft leader. If the new Raft leader isn't elected during this period, the proxy stops routing. If set to `0s`, the proxy stops routing immediately.
PGD Proxy	5.1.0	Bug fix	Changed from blocking when write leader is unavailable to closing the new client connections.
CLI	5.1.0	Enhancement	Enhanced the `show-events` command to show Raft events, event source and subtype.
CLI	5.1.0	Enhancement	Improved clockskew estimation in `show-clockskew` and `check-health` commands.
CLI	5.1.0	Feature	Added support to view and set `consensus_grace_period` proxy option.
Utilities	1.1.0	Bug fix	Implemented handling of uninitialized physical replication slots issue.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.20 EDB Postgres Distributed 5.0.1 release notes

Released: 21 Mar 2023

EDB Postgres Distributed version 5.0.1 is a patch version of EDB Postgres Distributed. This version addresses security vulnerabilities in dependencies for PGD-Proxy and PGD-CLI.

Component	Version	Type	Description
CLI	5.0.1	Change	Upgrade 3rd party dependencies to fix Github dependabot alerts
Proxy	5.0.1	Change	Upgrade 3rd party dependencies to fix Github dependabot alerts

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

2.21 EDB Postgres Distributed 5.0.0 release notes

Released: 21 Feb 2023

EDB Postgres Distributed version 5.0.0 is a is a new major version of EDB Postgres Distributed. This version brings major new features and compatibility changes.

The highlights of this release include:

- Flexible deployment architectures
- Enhanced routing capabilities
- Unified replication durability configuration
- Support for EDB Advanced Storage Pack
- Support for TDE with EDB Postgres Advanced 15 and EDB Postgres Extended 15
- Integration with OpenTelemetry
- Improved transaction tracking performance (Group Commit, CAMO)
- Postgres 12 to 15 compatiblity

Component	Version	Type	Description
PGD	5.0.0	Feature	Flexible Deployment Architectures Redefined Always-ON to support wider variety of deployments.
BDR	5.0.0	Feature	Enhanced routing capabilities BDR cluster elects a write leader for every group (and associated location) using per group Raft when routing is enabled for the group. It takes care of write leader failover and provides SQL commands to change a write leader.
BDR	5.0.0	Feature	Support for EDB Advanced Storage Pack EDB Advanced Storage Pack provides advanced storage options for PostgreSQL databases in the form of table access method (TAM) extensions. These storage options can enhance the performance and reliability of databases without requiring application changes.
BDR	5.0.0	Feature	Unified replication durability configuration The durability options such as Group Commit, CAMO, Eager Replication or Lag Control are now all configured through commit scope configuration.
BDR	5.0.0	Feature	EDB Postgres Advanced and EDB Postgres Extended TDE support EDB Postgres Distributed 5 fully supports the Transparent Data Encryption feature in EDB Postgres Advanced and EDB Postgres Extended.
BDR	5.0.0	Feature	Integration with OpenTelemetry BDR extension can now send monitoring metrics as well as traces to the OpenTelemetry collector for better integration with existing monitoring solutions.
BDR	5.0.0	Feature	Postgres 15 compatibility EDB Postgres Distributed 5 is compatible with Postgres 12 to 15.
BDR	5.0.0	Feature	Improved Cluster Event Management The `bdr.worker_errors` and `bdr.state_journal_details` view were replaced by unified `bdr.event_summary` which also include changes in Raft role for the local node. In the future additional events may be added to it.
BDR	5.0.0	Change	Improved transaction tracking performance Transaction tracking now uses shared memory instead of `bdr.internal_node_pre_commit` catalog which considerably improves performance as it does not incur additional I/O.
BDR	5.0.0	Feature	Support non-default replication sets with Decoding Worker Allows Decoding Worker feature to be used in clusters using non-default replication sets like asymmetric replication setup.
BDR	5.0.0	Feature	Add support for HASH partitioning in Autopartition Extend autopartition/autoscale to support HASH partitioning. Many of things that are required for RANGE partitioning are not needed for HASH partitioning. For example, we expect to create all HASH partitions in one go (at least for the current work; later we may change this). We don't expect HASH partitions to be moved to a different tablespace or dropped. So data retention policies don't apply for HASH partitioning.
BDR	5.0.0	Feature	Add a new benchmarking utility `pgd_bench` The utility supports benchmarking CAMO transactions and in future releases will be used for benchmarking PGD specific workloads.
BDR	5.0.0	Change	Nodes now have a node kind This better differentiates different kinds of nodes such as data, witness, subscriber-only and standby.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Component	Version	Type	Description
BDR	5.0.0	Change	Separate Task Management from Autopartition In this release, the autopartition work queue mechanism has been moved to a separate module called Task Manager (taskmgr). The task manager is responsible for creating new tasks and executing the ones created by the local node or the task manager leader node. The autopartition worker is thus renamed as taskmgr worker process in this release. In the older PGD releases, the Raft leader was responsible for creating new work items. But that creates a problem because a witness node can become a Raft leader while it does not have the full view of the cluster objects. In this release, we have introduced a concept of Task Manager Leader node. The node is selected automatically by PGD, but for upgraded clusters, its important to set the `node_kind` property for all nodes in the cluster. The user is expected to do this manually after upgrading to the latest PGD version by calling bdr.alter_node_kind() SQL function for each node.
BDR	5.0.0	Deprecation	`bdr.assess_lock_statement` and `bdr.assess_update_replica_identity` are deprecated.
Proxy	5.0.0	Feature	PGD built-in proxy A TCP layer 4, pass through proxy for PGD cluster using routing capabilities of BDR.
CLI	5.0.0	Feature	PGD cluster verification CLI supports two new commands `verify-settings` and `verify-cluster`. `verify-settings` verifies the PostgreSQL configuration of each node in a PGD cluster against the recommendations. `verify-cluster` verifies the PGD cluster architectures against the flexible architecture deployment recommendations.
CLI	5.0.0	Feature	Proxy management and configuration `pgd` supports `create-proxy`, `delete proxy`, `set-group-options`, `set-node-options`, `set-proxy-options`, `show-proxies`, `show-groups` and `switchover` to configure and manage Proxy per group.
CLI	5.0.0	Change	Remove `show-camo` command and remove CAMO check from `check-health` command. Support for `commit scopes` in CLI will be added in a future release.
CLI	5.0.0	Change	Modify output of `show-nodes` and `show-raft` commands to accomodate routing capabilities.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

3 Known issues

These are currently known issues in EDB Postgres Distributed 5. These known issues are tracked in PGD's ticketing system and are expected to be resolved in a future release.

- If the resolver for the `update_origin_change` conflict is set to `skip`, `synchronous_commit=remote_apply` is used, and concurrent updates of the same row are repeatedly applied on two different nodes, then one of the update statements might hang due to a deadlock with the PGD writer. As mentioned in Conflicts, `skip` isn't the default resolver for the `update_origin_change` conflict, and this combination isn't intended to be used in production. It discards one of the two conflicting updates based on the order of arrival on that node, which is likely to cause a divergent cluster. In the rare situation that you do choose to use the `skip` conflict resolver, note the issue with the use of the `remote_apply` mode.

- The Decoding Worker feature doesn't work with CAMO/Eager/Group Commit. Installations using CAMO/Eager/Group Commit must keep `enable_wal_decoder` disabled.

- Lag Control doesn't adjust commit delay in any way on a fully isolated node, that's in case all other nodes are unreachable or not operational. As soon as at least one node connects, replication Lag Control picks up its work and adjusts the PGD commit delay again.

- For time-based Lag Control, PGD currently uses the lag time, measured by commit timestamps, rather than the estimated catch up time that's based on historic apply rates.

- Changing the CAMO partners in a CAMO pair isn't currently possible. It's possible only to add or remove a pair. Adding or removing a pair doesn't require a restart of Postgres or even a reload of the configuration.

- Group Commit can't be combined with CAMO.

- Transactions using Eager Replication can't yet execute DDL. The TRUNCATE command is allowed.

- Parallel Apply isn't currently supported in combination with Group Commit. Make sure to disable it when using Group Commit by either (a) Setting `num_writers` to 1 for the node group using `bdr.alter_node_group_option` or (b) using the GUC `bdr.writers_per_subscription`. See Configuration of generic replication.

- There currently is no protection against altering or removing a commit scope. Running transactions in a commit scope that's concurrently being altered or removed can lead to the transaction blocking or replication stalling completely due to an error on the downstream node attempting to apply the transaction. Make sure that any transactions using a specific commit scope have finished before altering or removing it.

- The PGD CLI can return stale data on the state of the cluster if it's still connecting to nodes that were previously parted from the cluster. Edit the `pgd-cli-config.yml` file, or change your `--dsn` settings to ensure only active nodes in the cluster are listed for connection.

To modify a commit scope safely, use `bdr.alter_commit_scope`.

- DDL run in serializable transactions can face the error: `ERROR: could not serialize access due to read/write dependencies among transactions`. A workaround is to run the DDL outside serializable transactions.

- The EDB Postgres Advanced Server 17 data type `BFILE` is not currently supported. This is due to `BFILE` being a file reference that is stored in the database, and the file itself is stored outside the database and not replicated.

- When running PGD on community PostgreSQL with Parallel Apply enabled, writer processes may terminate unexpectedly due to lock timeouts. This occurs because PGD sets a 30 second `lock_timeout` in the writer processes, which can be insufficient when one writer waits on a transaction lock held by another writer that is processing a large transaction. When the timeout is reached, the waiting writer exits, causing other writers and the receiver to terminate as well, which resets the replication process. As a workaround, disable parallel apply by setting `bdr.enable_parallel_apply = off` or migrate to an EDB Postgres variant. This issue is resolved in PGD 6.3.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- In PGD 5.9.2, user login attributes aren't replicated to peer nodes after a `CREATE USER` statement. Users created on one node can log in on the originating node but are blocked on all other nodes because the login attribute is missing from the replicated role definition. This issue is resolved in PGD 5.9.3.

  To identify affected roles, run the following command in psql:

  ```
  \du
  ```

  In the **Attributes** column, any role that should have login access but displays `Cannot login` is affected.

  Alternatively, query the system catalog directly:

  ```
  SELECT rolname AS role_name,
  rolcanlogin
  FROM
  pg_roles
  WHERE rolcanlogin =
  false;
  ```

  To resolve the issue without upgrading, manually grant login access on each affected node:

  ```
  ALTER USER <username> WITH
  LOGIN;
  ```

Details of other design or implementation limitations are also available.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

4 PGD compatibility

PGD compatibility with PostgreSQL versions

The following table shows the major versions of PostgreSQL that EDB Postgres Distributed (PGD) is compatible with.

PGD 5	Postgres Version
5.10+	17.12+
5.10+	16.16+
5.10+	15.20+
5.10+	14.25+
5.7+	17.3
5.6.1+	17
5.3+	16
5	15
5	14
5	13

> **Important**
>
> PGD 5.10.0 requires Postgres, EDB Postgres Extended, or EDB Postgres Advanced Server 14.25, 15.20, 16.16, or 17.12, or later, due to internal compatibility changes in PGD 5.10.0.

EDB recommends that you use the latest minor version of any Postgres major version with a supported PGD.

PGD compatibility with operating systems and architectures

The following tables show the versions of EDB Postgres Distributed and their compatibility with various operating systems and architectures.

Linux

Operating System	x86_64 (amd64)	ppc64le	arm64/ aarch64[2]
RHEL 8	Yes	Yes	
RHEL 9	Yes	Yes	Yes
Oracle Linux 8	Yes		
Oracle Linux 9	Yes		
Rocky Linux/AlmaLinux 8/9	Yes		
SUSE Linux Enterprise Server 15SP7	Yes		
Ubuntu 22.04	Yes		
Ubuntu 24.04	Yes[1]		
Debian 12	Yes		Yes

[1] From PGD 5.7 onwards and only with Postgres version 14 or later.

[2] From PGD 5.6.1 onwards.

> **Note**
>
> See PGD 6 Compatibility for the latest version of PGD.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

5 Terminology

This terminology list includes terms associated with EDB Postgres Distributed that you might be unfamiliar with.

Asynchronous replication

A type of replication that copies data to other PGD cluster members after the transaction completes on the origin node. Asynchronous replication can provide higher performance and lower latency than synchronous replication. However, asynchronous replication can see a lag in how long changes take to appear in the various cluster members. While the cluster will be eventually consistent, there's potential for nodes to be apparently out of sync with each other.

Commit scopes

Rules for managing how transactions are committed between the nodes and groups of a PGD cluster. Used to configure synchronous replication, Group Commit, CAMO, Eager, Lag Control, and other PGD features.

CAMO or commit-at-most-once

High-value transactions in some applications require that the application successfully commits exactly once, and in the event of failover and retrying, only once. To ensure this happens in PGD, CAMO can be enabled, allowing the application to actively participate in the transaction.

Conflicts

As data is replicated across the nodes of a PGD cluster, there might be occasions when changes from one source clash with changes from another source. This is a conflict and can be handled with conflict resolution. (Conflict resolution is a set of rules that decide which source is correct or preferred.) Conflicts can also be avoided with conflict-free data types.

Consensus

How Raft makes group-wide decisions. Given a number of nodes in a group, Raft looks for a consensus of the majority (number of nodes divided by 2 plus 1) voting for a decision. For example, when a write leader is being selected, a Raft consensus is sought over which node in the group will be the write leader. Consensus can be reached only if there's a quorum of voting members.

Cluster

Generically, a cluster is a group of multiple systems arranged to appear to end users as one system. See also PGD cluster and Postgres cluster.

DDL (data definition language)

The subset of SQL commands that deal with defining and managing the structure of a database. DDL statements can create, modify, and delete objects (that is, schemas, tables, and indexes) in the database. Common DDL commands are CREATE, ALTER, and DROP.

DML (data manipulation language)

The subset of SQL commands that deal with manipulating the data held in a database. DML statements can create, modify, and delete rows in tables in the database. Common DML commands are INSERT, UPDATE, and DELETE.

Eager

A synchronous commit mode that avoids conflicts by detecting incoming potentially conflicting transactions and “eagerly” aborts one of them to maintain consistency.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Eventual consistency

A distributed computing consistency model stating changes to the same item in different cluster members will eventually converge to the same value. Asynchronous logical replication with conflict resolution and conflict-free replicated data types exhibit eventual consistency in PGD.

Failover

The automated process that recognizes a failure in a highly available database cluster and takes action to maintain consistency and availability. The goal is to minimize downtime and data loss.

Group commit

A synchronous commit mode that requires more than one PGD node to successfully receive and confirm a transaction at commit time.

Immediate consistency

A distributed computing model where all replicas are updated synchronously and simultaneously. This model ensures that all reads after a write completes will see the same value on all nodes. The downside of this approach is its negative impact on performance.

Logical replication

A more efficient method of replicating changes in the database. While physical streaming replication duplicates the originating database's disk blocks, logical replication instead takes the changes made, independent of the underlying physical storage format, and publishes them to all systems that subscribed to see the changes. Each subscriber then applies the changes locally. Logical replication can't support most DDL commands.

Node

A general term for an element of a distributed system. A node can play host to any service. In PGD, PGD nodes run a Postgres database, the BDR extension, and optionally a PGD Proxy service.

Typically, for high availability, each node runs on separate physical hardware, but that's not always the case. For example, a proxy might share a hardware node with a database.

Node groups

PGD nodes in PGD clusters can be organized into groups to reflect the logical operation of the cluster. For example, the data nodes in a particular physical location can be part of a dedicated node group for the location.

PGD cluster

A group of multiple redundant database systems and proxies arranged to avoid single points of failure while appearing to end users as one system. PGD clusters can be run on Docker instances, cloud instances or "bare" Linux hosts, or a combination of those platforms. A PGD cluster can also include backup and proxy nodes. The data nodes in a cluster are grouped together in a top-level group and into various local node groups.

PGD node

In a PGD cluster are nodes that run databases and participate in the PGD cluster. A typical PGD node runs a Postgres database, the BDR extension, and optionally a PGD Proxy service. PGD modes are also referred to as *data nodes*, which suggests they store data. However, some PGD nodes, specifically witness nodes, don't do that.

Physical replication

By making an exact copy of database disk blocks as they're modified to one or more standby cluster members, physical replication provides an easily implemented method to replicate servers. But there are restrictions on how it can be used. For example, only one master node can run write transactions. Also, the method requires that all cluster members are on the same major version of the database software with the same operating system and CPU architecture.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Postgres cluster

Traditionally, in PostgreSQL, a number of databases running on a single server is referred to as a cluster (of databases). This kind of Postgres cluster isn't highly available. To get high availability and redundancy, you need a PGD cluster.

Quorum

A quorum is the minimum number of voting nodes needed to participate in a distributed vote. It ensures that the decision made has validity. For example, when aRaft consensus is needed by a PGD cluster, a minimum number of voting nodes participating in the vote are needed. With a 5-node cluster, the quorum is 3 nodes in the cluster voting. A consensus is 5/2+1 nodes, 3 nodes voting the same way. If there are only 2 voting nodes, then a consensus is never established. Quorums are required in PGD for global locks and Raft decisions.

Replicated available fault tolerance (Raft)

A consensus algorithm that uses votes from a quorum of machines in a distributed cluster to establish a consensus. PGD uses Raft within groups (top-level or local) to establish the node that's the write leader.

Read scalability

The ability of a system to handle increasing read workloads. For example, PGD can introduce one or more read replica nodes to a cluster and have the application direct writes to the primary node and reads to the replica nodes. As the read workload grows, you can increase the number of read replica nodes to maintain performance.

Subscription

PGD nodes will publish changes being made to data to nodes that are interested. Other PGD nodes will ask to subscribe to those changes. This behavior creates a subscription and is the mechanism by which each node is updated. PGD nodes bidirectionally subscribe to other PGD nodes' changes.

Switchover

A planned change in connection between the application or proxies and the active database node in a cluster, typically done for maintenance.

Synchronous replication

When changes are updated at all participating nodes at the same time, typically leveraging a two-phase commit. While this approach replicates changes and resolves conflicts before committing, a performance cost in latency occurs due to the coordination required across nodes.

Subscriber-only nodes

A PGD cluster is based around bidirectional replication. But in some use cases, such as needing a read-only server, bidirectional replication isn't needed. A subscriber-only node is used in this case. It subscribes only to changes in the database to keep itself up to date and provide correct results to any run directly on the node. This feature can be used to enable horizontal read scalability in a PGD cluster.

Two-phase commit (2PC)

A multi-step process for achieving consistency across multiple database nodes. The first phase sees a transaction prepared on an originating node and sent to all participating nodes. Each participating node validates that it can apply the transaction and signals its readiness to the originating node. This is the prepare phase. In the second phase, if all the participating nodes signal they're ready, the originating node proceeds to commit the transaction and signals the participating nodes to commit, too. This is the commit phase. If, in the prepare phase, any node signals it isn't ready, the entire transaction is aborted. This process ensures all nodes get the same changes.

Vertical scaling or scale up

A traditional computing approach of increasing a resource (CPU, memory, storage, network) to support a given workload until the physical limits of that architecture are reached, for example, Oracle Exadata.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Witness nodes

Witness nodes primarily serve to help the cluster establish a consensus. An odd number of data nodes is needed to establish a consensus. Where resources are limited, a witness node can be used to participate in cluster decisions but not replicate the data. Not holding the data means it can't operate as a standby server or provide majorities in synchronous commits.

Write leader

In an Always-on architecture, a node is selected as the correct connection endpoint for applications. This node is called the write leader. Once selected, proxy nodes route queries and updates to it. With only one node receiving writes, unintended multi-node writes can be avoided. The write leader is selected by consensus of a quorum of data nodes. If the write leader becomes unavailable, the data nodes select another node to become write leader. Nodes that aren't the write leader are referred to as *shadow nodes*.

Writer

When a subscription delivers data changes to a PGD node, the database server tasks a worker process, called a writer, with getting those changes applied.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

6 PGD overview

EDB Postgres Distributed (PGD) provides multi-master replication and data distribution with advanced conflict management, data-loss protection, and throughput up to 5X faster than native logical replication. It also enables distributed Postgres clusters with high availability up to five 9s.

- Architecture overview
- Architectural options and performance
- Comparison with other replication solutions

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.


6.1 Architecture overview

EDB Postgres Distributed (PGD) is a distributed database solution that extends PostgreSQL's capabilities, enabling highly available and fault-tolerant database deployments across multiple nodes. PGD provides data distribution with advanced conflict management, data-loss protection, high availability up to five 9s, and throughput up to 5X faster than native logical replication.

PGD is built on a multi-master foundation (Bi-Directional Replication, or BDR) which is then optimized for performance and availability through PGD Proxy. You can run PGD without PGD Proxy if you need a custom deployment that better utilizes the multi-master functionality. When running without PGD Proxy, writes are distributed among the nodes and replicated to one another, and conflict resolution is relied on for maintaining consistency. This approach can be more efficient depending on your architectural needs. However, PGD Proxy ensures lower contention and conflict through the use of a write leader. For each proxy instance, a single endpoint addresses all the data nodes in a group, removing the need for clients to round robin multi-host connection strings. Raft is implemented to help the system make important decisions, like deciding which node is the Raft election leader and which node is the write leader.

High-level architecture

At the highest level, PGD comprises two main components: BDR and PGD Proxy. BDR is a Postgres extension that enables a multi-master replication mesh between different BDR-enabled Postgres instances/nodes. PGD Proxy sends requests to the write leader, ensuring a lower risk of conflicts (stronger consistency) between nodes.



Changes are replicated directly, row-by-row between all nodes. Logical replication in PGD is asynchronous by default, so only eventual consistency is guaranteed (within seconds usually). However, commit scope options offer immediate consistency and durability guarantees viaCAMO, group and synchronous commits.

The Raft algorithm provides a mechanism for electing leaders (both Raft leader and write leader), deciding which nodes to add or subtract from the cluster. It generally ensures that the distributed system remains consistent and fault tolerant, even in the face of node failures.

Architectural elements

PGD comprises several key architectural elements that work together to provide its distributed database solution:

- **PGD nodes**: These are individual Postgres instances that store and manage data. They are the basic building blocks of a PGD cluster.
- **Groups**: By default, all nodes are also members of a top-level group with its own Raft leader but without a write leader. PGD nodes can be further organized into subgroups, which enhance manageability and high availability. Each group can contain multiple nodes, allowing for redundancy and failover within the group. Groups facilitate organized replication and data consistency among nodes within the same group and across different groups. Each group has its own write leader.
- **Replication mechanisms**: PGD's replication mechanisms include BDR for efficient replication across nodes, enabling multi-master replication. BDR supports asynchronous replication by default but can be configured for varying levels of synchronicity, such as Group Commit or Synchronous Commit, to enhance data durability.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- **Monitoring tools**: To monitor performance, health, and usage with PGD, you can use its built-in command-line interface (CLI), which offers several useful commands. For example:

    - The `pgd nodes list` command provides a summary of all nodes in the cluster, including their state and status.
    - The `pgd cluster show --health` command checks the health of the cluster, reporting on node accessibility, replication slot health, and other critical metrics.
    - The `pgd events show` command lists significant events like background worker errors and node membership changes, which helps in tracking the operational status and issues within the cluster.

  Furthermore, the BDR extension allows for monitoring your cluster using SQL using the `bdr.monitor` role.

Node types

All nodes in PGD are effectively data nodes. They vary only in their purpose in the cluster.

- Data nodes: Store and manage data, handle read and write operations, and participate in replication.

There are then three types of nodes which, although built like a data node, have a specific purpose. These are:

- Subscriber-only nodes: Subscribe to changes from data nodes for read-only purposes. Used in reporting or analytics.
- Witness nodes: Participate in the consensus process without storing data, aiding in achieving quorum and maintaining high availability.
- Logical standby nodes: Act as standby nodes that can be promoted to data nodes if needed, ensuring high availability and disaster recovery.

Node roles

Data nodes in a group can also take on particular roles to enable particular features. These roles are transient and can be transferred to any other capable node in the group if needed. These roles can include:

- **Raft leader**: Arbitrates and manages consensus between a group's nodes.
- Write leader: Receives all write operations from PGD Proxy.

Architectural flexibility

PGD offers flexible options with how its architecture can be deployed, maintained, and scaled to meet various performance, availability, and compliance needs.

PGD supports rolling maintenance, including blue/green deployments for both Postgres upgrades and other system or application-level changes. This approach ensures that the database remains available during routine tasks, such as minor or major version upgrades, schema changes, and vacuuming operations. The system seamlessly switches between active database versions, achieving zero downtime.

PGD provides automatic failover to ensure high availability. If a node in the cluster becomes unavailable, another node takes over its responsibilities, minimizing downtime. Also, PGD includes self-healing capabilities, where nodes that have failed or disconnected reconnect to the cluster and resume normal operations once the issue is resolved.

PGD allows for selective replication, enabling users to replicate only a subset of data to specific nodes. This feature can be used to optimize performance by reducing unnecessary data traffic between nodes or to meet regulatory requirements, such as geographical data restrictions. For instance, a healthcare application might only replicate patient data within a specific region to comply with local data privacy laws.

With commit scopes, PGD also provides configurable durability. Accordingly, durability can be increased from the default asynchronous behavior and tuned using various configurable commit scopes:

- Synchronous Commit: Works a lot like PostgreSQL's synchronous_commit option in its underlying operation. Requires writing to at least one other node at COMMIT time but can be tuned to require all nodes.
- CAMO (Commit At Most Once): Works by tracking each transaction with a unique ID and using a pair of nodes to confirm the transaction's outcome, ensuring the application knows whether to retry the transaction or not.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- Group Commit: An experimental commit scope, the goal of which is to protect against data loss in case of single-node failures of temporary outages by requiring more than one PGD node to successfully confirm a transaction at COMMIT time.

- Lag Control: If replication is running outside of set limits (taking too long for another node to be replicated to), a delay is injected into the node that originally received the transaction, slowing things down until other nodes have caught up.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

6.2 PGD overview - architecture and performance

Architectural options and performance

Always-on architectures

A number of different architectures can be configured, each of which has different performance and scalability characteristics.

The group is the basic building block consisting of 2+ nodes (servers). In a group, each node is in a different availability zone, with a dedicated router and backup, giving immediate switchover and high availability. Each group has a dedicated replication set defined on it. If the group loses a node, you can easily repair or replace it by copying an existing node from the group.

The Always-on architectures are built from either one group in a single location or two groups in two separate locations. Each group provides high availability. When two groups are leveraged in remote locations, they together also provide disaster recovery (DR).

Tables are created across both groups, so any change goes to all nodes, not just to nodes in the local group.

One node in each group is selected as the group's write leader. Proxies then direct application writes and queries to the write leader. The other nodes are replicas of the write leader. If, at any point, the write leader is seen to be unavailable, the remaining nodes in the group select a new write leader from the group and the proxies direct traffic to that node. Scalability isn't the goal of this architecture.

Since writes are mainly to only one node, the possibility of contention between nodes is reduced to almost zero. As a result, performance impact is much reduced.

Secondary applications might execute against the shadow nodes, although these are reduced or interrupted if the main application begins using that node.

In the future, one node will be elected as the main replicator to other groups, limiting CPU overhead of replication as the cluster grows and minimizing the bandwidth to other groups.

Supported Postgres database servers

PGD is compatible with PostgreSQL, EDB Postgres Extended Server, and EDB Postgres Advanced Server and is deployed as a standard Postgres extension named BDR. See Compatibility for details about supported version combinations.

Some key PGD features depend on certain core capabilities being available in the target Postgres database server. Therefore, PGD users must also adopt the Postgres database server distribution that's best suited to their business needs. For example, if having the PGD feature Commit At Most Once (CAMO) is mission critical to your use case, don't adopt the community PostgreSQL distribution. It doesn't have the core capability required to handle CAMO. See the full feature matrix compatibility in Choosing a Postgres distribution.

PGD offers close-to-native Postgres compatibility. However, some access patterns don't necessarily work as well in multi-node setup as they do on a single instance. There are also some limitations in what you can safely replicate in a multi-node setting. Application usage goes into detail about how PGD behaves from an application development perspective.

Characteristics affecting performance

By default, PGD keeps one copy of each table on each node in the group, and any changes propagate to all nodes in the group.

Since copies of data are everywhere, SELECTs need only ever access the local node. On a read-only cluster, performance on any one node isn't affected by the number of nodes and is immune to replication conflicts on other nodes caused by long-running SELECT queries. Thus, adding nodes increases linearly the total possible SELECT throughput.

If an INSERT, UPDATE, and DELETE (DML) is performed locally, then the changes propagate to all nodes in the group. The overhead of DML apply is less than the original execution. So if you run a pure write workload on multiple nodes concurrently, a multi-node cluster can handle more TPS than a single node.

Conflict handling has a cost that acts to reduce the throughput. The throughput then depends on how much contention the application displays in practice. Applications with very low contention perform better than a single node. Applications with high contention can perform worse than a single node. These results are consistent with any multimaster technology and aren't particular to PGD.

Synchronous replication options can send changes concurrently to multiple nodes so that the replication lag is minimized. Adding more nodes means using more CPU for replication, so peak TPS reduces slightly as each node is added.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

If the workload tries to use all CPU resources, then this resource constrains replication, which can then affect the replication lag.

In summary, adding more master nodes to a PGD group doesn't result in significant write throughput increase when most tables are replicated because all the writes are replayed on all nodes. Because PGD writes are in general more effective than writes coming from Postgres clients by way of SQL, you can increase performance. Read throughput generally scales linearly with the number of nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

6.3 PGD compared

The following table compares EDB Postgres Distributed with other replication solutions.

	PGD Standalone	PGD Managed	PSR + EFM	pglogical 2	PG Builtin Logical Replication
Version at last update (2025-06-19)	5.8.0	5.8.0	4.10	2.4.5	17
Deployment					
On Premise	Yes	Yes	Yes	Yes	Yes
Multi-cloud	Yes	Yes	Yes	Yes	Yes
Hybrid (on-prem + cloud)	Yes	Coming Soon	Yes	Yes	Yes
SLA	99.999	99.995	99.99	N/A	N/A
Performance					
Read Scalability	Yes	No	Yes - Physical standbys	Yes - More nodes	Yes - More nodes
Horizontal Scalability	No	No	No	No	No
Transaction Streaming	Yes	Yes	Yes	No	Yes
Parallel Apply (Vertical Scalability)	Yes	Yes	No	No	Partial - for large transactions only
Durability					
Asynchronous Replication	Yes	Yes	Yes	Yes	Yes
Optional RPO limit for asynchronous replication	Yes	Yes	No	No	No
Synchronous Replication	Yes	Yes	Yes	Yes	Yes
Consensus based replication	Yes	Yes	No	No	No
Per transaction durability setting	Yes	Yes	Yes	Yes	Yes
Consistency					
Automatic conflict management	Yes	Yes	N/A	Yes	No
Conflict avoidance types	Yes	Yes	N/A	No	No
Conflict avoidance at commit (pessimistic conflict handling)	Yes	Yes	N/A	No	No
Builtin distributed sequence	Yes - snowflake (bigint) - galloc (int/bigint)	Yes - snowflake (bigint) - galloc (int/bigint)	N/A	No	No
Data Distibution					
Data residency/selective replication	Yes	Yes	No	Yes	Yes
Cluster level Active-Active (writers in different regions)	Yes	Yes	No	Manual setup	No
Regional Active-Active (multiple writers within region)	Yes - not recommended unless specific setup	No	No	Manual setup	No
Automatic partitioning	Yes	Yes	Yes with EPAS	No	No
Offload cold data to cheaper storage	Yes	Yes	No	No	No
Maintenance					
Near-zero downtime major version upgrades by adding nodes	Yes	Yes	Yes - using logical replication	Yes	Yes
Near-zero downtime inplace major version upgrades	Yes	Yes	No	No	No

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

	PGD Standalone	PGD Managed	PSR + EFM	pglogical 2	PG Builtin Logical Replication
Rolling schema upgrades/green-blue (with application assistance)	Yes	Yes	No	No	No
Rolling maintenance operations	Yes	Yes	No	Yes	Yes
Connection Mgmt					
Automatic failover	Yes	Yes	Yes	N/A	N/A
Automatic connection failover for switchover	Yes	Yes	Yes	N/A	N/A
Cluster level connection routing	Yes	Yes	Yes	N/A	N/A
Region level connection routing	Yes	Yes	No	N/A	N/A
pgbouncer support	Yes	No	Yes	N/A	N/A
DDL Support					
General DDL replication	Yes	Yes	Yes	Manual	No
Granular (per-object) DDL locking	Yes	Yes	Yes	No	No
Create and drop objects	Yes	Yes	Yes	Manual	No
Add columns to table	Yes	Yes	Yes	Unsafe/manual	No
Change column type	Yes - rewrite requires permit_unsafe_commands	Yes - rewrite requires permit_unsafe_commands	Yes	Unsafe/manual	No
CREATE TABLE AS	Yes - with restrictions	Yes - with restrictions	Yes	Unsafe/manual	No
PG Compatibility					
Latest supported version	17	17	17	17	17
Works on standard PG	Yes	No	Yes	Yes	Yes
Supports TDE	Yes with EPAS/PGE	Yes with EPAS/PGE	Yes with EPAS/PGE	No	Yes with EPAS/PGE
Supports custom types (i.e. Postgis)	Yes	Yes	Yes	Yes	Yes
Supports extensions	Many	Many	All	Many	Many
CDC failover support	No	No	Yes	N/A	N/A
Large Object support	No	No	Yes	No	No
Multiple DB support	No	No	Yes	N/A	N/A
Management					
CLI	Yes	Yes	Yes	No	No
GUI	PEM	Yes	PEM	No	No
Monitoring options	- SQL - CLI - PEM	- SQL - CLI - UPM	- SQL - CLI - PEM	SQL	SQL
Licensing					
Source available	No	No	No	Yes	Yes
Open source	No	No	No	Yes	Yes

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7 Introducing PGD quick starts

Quick start

EDB Postgres Distributed (PGD) is a multi-master replicating implementation of Postgres designed for high performance and availability. You can create database clusters made up of many bidirectionally synchronizing database nodes. The clusters can have a number of proxy servers that direct your query traffic to the most available nodes, adding further resilience to your cluster configuration.

Other deployment options

- If you prefer to have a fully managed EDB Postgres Distributed experience, PGD is now available as an option on EDB Cloud Service, EDB's cloud platform for Postgres. See EDB Cloud Service distributed high-availability clusters.

- If you prefer to deploy PGD on Kubernetes, you can use the EDB PGD Operator for Kubernetes. See EDB PGD Operator for Kubernetes.

What's in this quick start

PGD is very configurable. To quickly evaluate and deploy PGD, use this quick start. It'll get you up and running with a fully configured PGD cluster using the same tools that you'll use to deploy to production. This quick start includes:

- A short introduction to Trusted Postgres Architect (TPA) and how it helps you configure, deploy, and manage EDB Postgres Distributed
- A guide to selecting Docker, Linux hosts, or AWS quick starts
    - The Docker quick start
    - The Linux host quick start
    - The AWS quick start

- Connecting applications to your cluster
- Further explorations with your cluster including
    - Replication
    - Conflicts
    - Failover

Introducing PGD and TPA

PGD is a multi-master replicating implementation of Postgres designed for high performance and availability. The installation of PGD is orchestrated by TPA.

We created TPA to make installing and managing various Postgres configurations easily repeatable. TPA orchestrates creating and deploying Postgres.

These quick starts are designed to let you quickly get a single region cluster.

In these quick starts, you install TPA first. If you already have TPA installed, you can skip those steps. TPA is more of a tool than a simple installer. You can use the same installation of TPA to deploy many different configurations of Postgres clusters.

You'll use TPA to generate a configuration file for a PGD demonstration cluster. This cluster will have three replicating database nodes, cohosting three high-availability proxies and one backup node.

You will then use TPA to provision and deploy the required configuration and software to each node.

Selecting Docker, Linux hosts, or AWS quick starts

Three quick starts are currently available:

- Docker — Provisions, deploys, and hosts the cluster on Docker containers on a single machine.
- Linux hosts — Deploys and hosts the cluster on Linux servers that you already provisioned with an operating system and SSH connectivity. These can be actual physical servers or virtual machines, deployed on-premises or in the cloud.
- AWS — Provisions, deploys, and hosts the cluster on AWS.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Docker quick start

The Docker quick start is ideal for those looking to initially explore PGD and its capabilities. This configuration of PGD isn't suitable for production use but can be valuable for testing the functionality and behavior of PGD clusters. You might also find it useful when familiarizing yourself with PGD commands and APIs to prepare for deploying on cloud, VM, or Linux hosts.

- Begin the Docker quick start.

Linux host quick start

The Linux hosts quick start is suited if you intend to install PGD on your own hosts, where you have complete control of the hardware and software, or in a private cloud. The overall configuration is similar to the Docker configuration but is more persistent over system restarts and closer to a single-region production deployment of PGD.

- Begin the Linux host quick start.

AWS quick start

The AWS quick start is more extensive and deploys the PGD cluster onto EC2 nodes on Amazon's cloud. The cluster's overall configuration is similar to the Docker quick start. However, instead of using Docker containers, it uses t3.micro instances of Amazon EC2 to provide the compute power. The AWS deployment is more persistent and not subject to the limitations of the Docker quick start deployment. However, it requires more initial setup to configure the AWS CLI.

- Begin the AWS quick start.

Further explorations with your cluster

- Connect applications to your PGD cluster.
- Find out how a PGD cluster stands up to downtime of data nodes or proxies.
- Learn about how EDB Postgres Distributed manages conflicting updates.
- Move beyond the quick starts.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.1 Deploying an EDB Postgres Distributed example cluster on Docker

This quick start uses TPA to set up PGD with an Always-on Single Location architecture using local Docker containers.

Introducing TPA and PGD

We created TPA to make installing and managing various Postgres configurations easily repeatable. TPA orchestrates creating and deploying Postgres. In this quick start, you install TPA first. If you already have TPA installed, you can skip those steps. You can use TPA to deploy various configurations of Postgres clusters.

PGD is a multi-master replicating implementation of Postgres designed for high performance and availability. The installation of PGD is orchestrated by TPA. You will use TPA to generate a configuration file for a PGD demonstration cluster.

This cluster uses local Docker containers to host the cluster's nodes: three replicating database nodes, three cohosted connection proxies, and one backup node. You can then use TPA to provision and deploy the required configuration and software to each node.

This configuration of PGD isn't suitable for production use but can be valuable for testing the functionality and behavior of PGD clusters. You might also find it useful when familiarizing yourself with PGD commands and APIs to prepare for deployment on cloud, VM, or Linux hosts.

> **Note**
>
> This set of steps is specifically for Ubuntu 22.04 LTS on Intel/AMD processors.

Prerequisites

To complete this example, you need a system with enough RAM and free storage. You also need curl and Docker installed.

RAM requirements

You need a minimum of 4GB of RAM on the system. You need this much RAM because you will be running four containers, three of which will be hosting Postgres databases.

Free disk space

You need at least 5GB of free storage, accessible by Docker, to deploy the cluster described by this example. We recommend that you have a bit more than that.

The curl utility

You will download and run scripts during this quick start using the curl utility, which might not be installed by default. To ensure that curl is installed, run:

```
sudo apt update
sudo apt install curl
```

Docker Engine

You will use Docker containers as the target platform for this PGD deployment. Install Docker Engine:

```
sudo apt update
sudo apt install docker.io
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Running as a non-root user**
>
> Once Docker Engine is installed, be sure to add your user to the Docker group:
>
> ```
> sudo usermod -aG docker <username>
> newgrp docker
> ```

Preparation

EDB account

To install both TPA and PGD, you will need an EDB Repos 2.0 token to gain access to the EDB private software repositories. For instructions on obtaining this token, see: Get your token.

Setting environment variables

First, set the `EDB_SUBSCRIPTION_TOKEN` environment variable to the value of your EDB repo token, obtained in the EDB account step.

```
export EDB_SUBSCRIPTION_TOKEN=<your-repo-token>
```

You can add this to your `.bashrc` script or similar shell profile to ensure it's always set.

Configure the repository

All the software needed for this example is available from the EDB Postgres Distributed package repository. The following command downloads and runs a script to configure the EDB Postgres Distributed repository. This repository also contains the TPA packages.

```
curl -1sLf "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.deb.sh" | sudo -E
bash
```

> **Troubleshooting repo access**
>
> The script should produce output starting with:
>
> ```
> Executing the  setup script for the 'enterprisedb/postgres_distributed' repository ...
> ```
>
> If it produces no output or an error, double-check that you entered your token correctly. It the problem persists,contact Support for assistance.

Installing Trusted Postgres Architect (TPA)

You'll use TPA to provision and deploy PGD. If you previously installed TPA, you can move on to thenext step. You'll find full instructions for installing TPA in theTrusted Postgres Architect documentation, which we've also included here.

Linux environment

TPA supports several distributions of Linux as a host platform. These examples are written for Ubuntu 22.04, but steps are similar for other supported platforms.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Install the TPA package

```
sudo apt install tpaexec
```

Configuring TPA

You now need to configure TPA, which configures TPA's Python environment. Call `tpaexec` with the command `setup`:

```
sudo /opt/EDB/TPA/bin/tpaexec setup
export PATH=$PATH:/opt/EDB/TPA/bin
```

You can add the `export` command to your shell's profile.

Testing the TPA installation

You can verify TPA is correctly installed by running `selftest`:

```
tpaexec selftest
```

TPA is now installed.

Installing PGD using TPA

Generating a configuration file

Run the `tpaexec configure` command to generate a configuration folder:

```
tpaexec configure democluster \
  --architecture PGD-Always-ON \
  --platform docker \
  --edb-postgres-advanced 16 \
  --redwood \
  --location-names dc1 \
  --pgd-proxy-routing local \
  --no-git \
  --hostnames-unsorted \
  --keyring-backend legacy
```

You specify the PGD-Always-ON architecture (`--architecture PGD-Always-ON`), which sets up the configuration for PGD's Always-on architectures. As part of the default architecture, it configures your cluster with three data nodes, cohosting three PGD Proxy servers, along with a Barman node for backup.

Specify that you're using Docker (`--platform docker`). By default, TPA configures Rocky Linux as the default image for all nodes.

> **Deployment platforms**
>
> Other Linux platforms are supported as deployment targets for PGD. See the EDB Postgres Distributed compatibility table for details.
>
> Observe that you don't have to deploy PGD to the same platform you're using to run TPA!

Specify that the data nodes will be running EDB Postgres Advanced Server v16 (`--edb-postgres-advanced 16`) with Oracle compatibility (`--redwood`).

You set the notional location of the nodes to `dc1` using `--location-names`. You then set `--pgd-proxy-routing` to `local` so that proxy routing can route traffic to all nodes in each location.

By default, TPA commits configuration changes to a Git repository. For this example, you don't need to do that, so pass the `--no-git` flag.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

You also ask TPA to generate repeatable hostnames for the nodes by passing `--hostnames-unsorted`. Otherwise, it selects hostnames at random from a predefined list of suitable words.

Finally, `--keyring-backend legacy` tells TPA to select the legacy version of the keyring backend. Secrets are stored with an older keyring backend, as the version of Ubuntu this example is based on doesn't support the newer keyring backend.

This command creates a subdirectory called `democluster` in the current working directory. It contains the `config.yml` configuration file TPA uses to create the cluster. You can view it using:

```
less democluster/config.yml
```

> **Further reading**
>
> - View the full set of available options by running:
>
>   ```
>   tpaexec configure --architecture PGD-Always-ON --help
>   ```
>
> - More details on PGD-Always-ON configuration options in Deploying with TPA
> - PGD-Always-ON in the TPA documentation
> - `tpaexec configure` in the TPA documentation
> - Docker platform in the TPA documentation

Deploying the cluster

You can now deploy the distributed cluster. For Docker deployments, deploying both provisions the required Docker containers and deploys the software to those containers:

```
tpaexec deploy democluster
```

TPA applies the configuration, installing the needed packages and setting up the actual EDB Postgres Distributed cluster.

> **Further reading**
>
> - `tpaexec deploy` in the Trusted Postgres Architect documentation

Connecting to the cluster

You're now ready to log in to one of the nodes of the cluster with SSH and then connect to the database. Part of the configuration process is to set up SSH logins for all the nodes, complete with keys. To use the SSH configuration, you need to be in the `democluster` directory created by the `tpaexec configure` command earlier:

```
cd democluster
```

From there, you can run `ssh -F ssh_config <hostname>` to establish an SSH connection. You will connect to kaboom, the first database node in the cluster:

```
ssh -F ssh_config kaboom
```

output

```
[root@kaboom ~]#
```

Notice that you're logged in as `root` on `kaboom`.

You now need to adopt the identity of the enterprisedb user. This user is preconfigured and authorized to connect to the cluster's nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
sudo -iu enterprisedb
```

output

```
enterprisedb@kaboom:~ $
```

You can now run the `psql` command to access the `bdrdb` database:

```
psql bdrdb
```

output

```
psql (16.2.0, server 16.2.0)
Type "help" for help.

bdrdb=#
```

You're directly connected to the Postgres database running on the kaboom node and can start issuing SQL commands.

To leave the SQL client, enter `exit`.

Using PGD CLI

The pgd utility, also known as the PGD CLI, lets you control and manage your EDB Postgres Distributed cluster. It's already installed on the node.

You can use it to check the cluster's health by running `pgd cluster show --health`:

```
pgd cluster show --health
```

output

```
Check             Status Details
----------------- ------ ------------------------------------------------
Connections       Ok     All BDR nodes are accessible
Raft              Ok     Raft Consensus is working correctly
Replication Slots Ok     All PGD replication slots are working correctly
Clock Drift       Ok     Clock drift is within permissible limit
Versions          Ok     All nodes are running the same PGD version
```

Or, you can use `pgd nodes list` to ask PGD to show you the data-bearing nodes in the cluster:

```
pgd nodes list
```

output

```
Node Name Group Name   Node Kind Join State Node Status
--------- ------------ --------- ---------- -----------
kaftan    dc1_subgroup data      ACTIVE     Up
kaolin    dc1_subgroup data      ACTIVE     Up
kaboom    dc1_subgroup data      ACTIVE     Up
```

Explore your cluster

- Connect to your database to applications.
- Explore replication with hands-on exercises.
- Explore failover with hands-on exercises.
- Understand conflicts by creating and monitoring them.
- Take the next steps for working with your cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.2 Deploying an EDB Postgres Distributed example cluster on Linux hosts

Introducing TPA and PGD

We created TPA to make installing and managing various Postgres configurations easily repeatable. TPA orchestrates creating and deploying Postgres. In this quick start, you install TPA first. If you already have TPA installed, you can skip those steps. You can use TPA to deploy various configurations of Postgres clusters.

PGD is a multi-master replicating implementation of Postgres designed for high performance and availability. The installation of PGD is orchestrated by TPA. You will use TPA to generate a configuration file for a PGD demonstration cluster.

The TPA Linux host option allows users of any cloud or VM platform to use TPA to configure EDB Postgres Distributed. All you need from TPA is for the target system to be configured with a Linux operating system and accessible using SSH. Unlike the other TPA platforms (Docker and AWS), the Linux host configuration doesn't provision the target machines. You need to provision them wherever you decide to deploy.

This cluster uses Linux server instances to host the cluster's nodes. The nodes include three replicating database nodes, three cohosted connection proxies, and one backup node. TPA can then provision, prepare, and deploy the required EDB Postgres Distributed software and configuration to each node.

> **On host compatibility**
>
> This set of steps is specifically for users running Ubuntu 22.04 LTS on Intel/AMD processors.

Prerequisites

Configure your Linux hosts

You need to provision four hosts for this quick start. Each host must have a supported Linux operating system installed. To eliminate prompts for password, each host also needs to be SSH accessible using certificate key pairs.

> **On machine provisioning**
>
> Azure users can follow a Microsoft guide on how to provision Azure VMs loaded with Linux. Google Cloud Platform users can follow a Google guide on how to provision GCP VMs with Linux loaded. You can use any virtual machine technology to host a Linux instance, too. Refer to your virtualization platform's documentation for instructions on how to create instances with Linux loaded on them.
>
> Whichever cloud or VM platform you use, you need to make sure that each instance is accessible by SSH and that each instance can connect to the other instances. They can connect through either the public network or over a VPC for the cloud platforms. You can connect through your local network for on-premises VMs.
>
> If you can't do this, you might want to consider the Docker or AWS quick start. These configurations are easier to set up and quicker to tear down. The AWS quick start, for example, automatically provisions compute instances and creates a VPC for those instances.

In this quick start, you will install PGD nodes onto four hosts configured in the cloud. Each of these hosts in this example is installed with Rocky Linux. Each has a public IP address to go with its private IP address.

Host name	Public IP	Private IP
linuxhost-1	172.19.16.27	192.168.2.247
linuxhost-2	172.19.16.26	192.168.2.41
linuxhost-3	172.19.16.25	192.168.2.254
linuxhost-4	172.19.16.15	192.168.2.30

These are example IP addresses. Substitute them with your own public and private IP addresses as you progress through the quick start.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Set up a host admin user

Each machine requires a user account to use for installation. For simplicity, use a user with the same name on all the hosts. On each host, also configure the user so that you can SSH into the host without being prompted for a password. Be sure to give that user sudo privileges on the host. On the four hosts, the user rocky is already configured with sudo privileges.

Preparation

EDB account

To install both TPA and PGD, you will need an EDB Repos 2.0 token to gain access to the EDB private software repositories. For instructions on obtaining this token, see: Get your token.

Setting environment variables

First, set the `EDB_SUBSCRIPTION_TOKEN` environment variable to the value of your EDB repo token, obtained in the EDB account step.

```
export EDB_SUBSCRIPTION_TOKEN=<your-repo-token>
```

You can add this to your `.bashrc` script or similar shell profile to ensure it's always set.

Configure the repository

All the software needed for this example is available from the EDB Postgres Distributed package repository. Download and run a script to configure the EDB Postgres Distributed repository. This repository also contains the TPA packages.

```
curl -1sLf "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.deb.sh" | sudo -E
bash
```

Installing Trusted Postgres Architect (TPA)

You'll use TPA to provision and deploy PGD. If you previously installed TPA, you can move on to thenext step. You'll find full instructions for installing TPA in theTrusted Postgres Architect documentation, which we've also included here.

Linux environment

TPA supports several distributions of Linux as a host platform. These examples are written for Ubuntu 22.04, but steps are similar for other supported platforms.

Install the TPA package

```
sudo apt install tpaexec
```

Configuring TPA

You now need to configure TPA, which configures TPA's Python environment. Call `tpaexec` with the command `setup`:

```
sudo /opt/EDB/TPA/bin/tpaexec setup
export PATH=$PATH:/opt/EDB/TPA/bin
```

You can add the `export` command to your shell's profile.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Testing the TPA installation

You can verify TPA is correctly installed by running `selftest`:

```
tpaexec selftest
```

TPA is now installed.

Installing PGD using TPA

Generating a configuration file

Run the `tpaexec configure` command to generate a configuration folder:

```
tpaexec configure democluster \
    --architecture PGD-Always-ON \
    --platform bare \
    --edb-postgres-advanced 16 \
    --redwood \
    --no-git \
    --location-names dc1 \
    --pgd-proxy-routing local \
    --hostnames-unsorted
```

You specify the PGD-Always-ON architecture (`--architecture PGD-Always-ON`), which sets up the configuration for PGD's Always-on architectures. As part of the default architecture, it configures your cluster with three data nodes, cohosting three PGD Proxy servers and a Barman node for backup.

For Linux hosts, specify that you're targeting a "bare" platform (`--platform bare`). TPA determines the Linux version running on each host during deployment. See the EDB Postgres Distributed compatibility table for details about the supported operating systems.

Specify that the data nodes will be running EDB Postgres Advanced Server v16 (`--edb-postgres-advanced 16`) with Oracle compatibility (`--redwood`).

You set the notional location of the nodes to `dc1` using `--location-names`. You then set `--pgd-proxy-routing` to `local` so that proxy routing can route traffic to all nodes in each location.

By default, TPA commits configuration changes to a Git repository. For this example, you don't need to do that, so pass the `--no-git` flag.

Finally, you ask TPA to generate repeatable hostnames for the nodes by passing `--hostnames-unsorted`. Otherwise, it selects hostnames at random from a predefined list of suitable words.

This command creates a subdirectory in the current working directory called `democluster`. It contains the `config.yml` configuration file TPA uses to create the cluster. You can view it using:

```
less democluster/config.yml
```

You now need to edit the configuration file to add details related to your Linux hosts, such as admin user names and public and private IP addresses.

Editing your configuration

Using your preferred editor, open `democluster/config.yml`.

Search for the line containing `ansible_user: root`. Change `root` to the name of the user you configured with SSH access and sudo privileges. Follow that with this line:

```
    manage_ssh_hostkeys: yes
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Your `instance_defaults` section now looks like this:

```
instance_defaults:
  platform: bare
  vars:
    ansible_user: rocky
    manage_ssh_hostkeys: yes
```

Next, search for `node: 1`, which is the configuration settings of the first node, kaboom.

After the `node: 1` line, add the public and private IP addresses of your node. Use `linuxhost-1` as the host for this node. Add the following to the file, substituting your IP addresses. Align the start of each line with the start of the `node:` line.

```
  public_ip: 172.19.16.27
  private_ip: 192.168.2.247
```

The whole entry for kaboom looks like this but with your own IP addresses:

```
- Name:
kaboom
  backup: kapok
  location:
dc1
  node: 1
  public_ip: 172.19.16.27
  private_ip: 192.168.2.247
  role:
  -
bdr
  - pgd-proxy
  vars:
    bdr_child_group: dc1_subgroup
    bdr_node_options:
      route_priority: 100
```

Repeat this process for the three other nodes.

Search for `node: 2`, which is the configuration settings for the node kaftan. Use `linuxhost-2` for this node. Substituting your IP addresses, add:

```
  public_ip: 172.19.16.26
  private_ip: 192.168.2.41
```

Search for `node: 3`, which is the configuration settings for the node kaolin. Use `linuxhost-3` for this node. Substituting your IP addresses, add:

```
  public_ip: 172.19.16.25
  private_ip: 192.168.2.254
```

Finally, search for `node: 4`, which is the configuration settings for the node kapok. Use `linuxhost-4` for this node. Substituting your IP addresses, add:

```
  public_ip: 172.19.16.15
  private_ip: 192.168.2.30
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Provisioning the cluster

You can now run:

```
tpaexec provision democluster
```

This command prepares for deploying the cluster. (On other platforms, such as Docker and AWS, this command also creates the required hosts. When using Linux hosts, your hosts must already be configured.)

> **Further reading**
>
> - `tpaexec provision` in the Trusted Postgres Architect documentation

One part of this process for Linux hosts is creating key-pairs for the hosts for SSH operations later. With those key-pairs created, you need to copy the public part of the key-pair to the hosts. You can do this with `ssh-copy-id`, giving the democluster identity (`-i`) and the login to each host. For this example, these are the commands:

```
ssh-copy-id -i democluster/id_democluster rocky@172.19.16.27
ssh-copy-id -i democluster/id_democluster rocky@172.19.16.26
ssh-copy-id -i democluster/id_democluster rocky@172.19.16.25
ssh-copy-id -i democluster/id_democluster rocky@172.19.16.15
```

You can now create the `tpa_known_hosts` file, which allows the hosts to be verified. Use `ssh-keyscan` on each host (`-H`) and append its output to `tpa_known_hosts`:

```
ssh-keyscan -H 172.19.16.27 >> democluster/tpa_known_hosts
ssh-keyscan -H 172.19.16.26 >> democluster/tpa_known_hosts
ssh-keyscan -H 172.19.16.25 >> democluster/tpa_known_hosts
ssh-keyscan -H 172.19.16.15 >> democluster/tpa_known_hosts
```

Deploy your cluster

You now have everything ready to deploy your cluster. To deploy, run:

```
tpaexec deploy democluster
```

TPA applies the configuration, installing the needed packages and setting up the actual EDB Postgres Distributed cluster.

> **Further reading**
>
> - `tpaexec deploy` in the Trusted Postgres Architect documentation

Connecting to the cluster

You're now ready to log in to one of the nodes of the cluster with SSH and then connect to the database. Part of the configuration process set up SSH logins for all the nodes, complete with keys. To use the SSH configuration, you need to be in the `democluster` directory created by the `tpaexec configure` command earlier:

```
cd democluster
```

From there, you can run `ssh -F ssh_config <hostname>` to establish an SSH connection. Connect to kaboom, the first database node in the cluster:

```
ssh -F ssh_config kaboom
```

output

```
[rocky@kaboom ~]#
```

Notice that you're logged in as rocky, the admin user and ansible user you configured earlier, on kaboom.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

You now need to adopt the identity of the enterprisedb user. This user is preconfigured and authorized to connect to the cluster's nodes.

```
sudo -iu enterprisedb
```

output

```
enterprisedb@kaboom:~ $
```

You can now run the `psql` command to access the `bdrdb` database:

```
psql bdrdb
```

output

```
psql (16.2.0, server 16.2.0)
Type "help" for help.

bdrdb=#
```

You're directly connected to the Postgres database running on the kaboom node and can start issuing SQL commands.

To leave the SQL client, enter `exit`.

Using PGD CLI

The pgd utility, also known as the PGD CLI, lets you control and manage your EDB Postgres Distributed cluster. It's already installed on the node.

You can use it to check the cluster's health by running `pgd cluster show --health`:

```
pgd cluster show --health
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

output

```
Connections
-----------
Checks if all BDR nodes are accessible.

Result: Ok, all BDR nodes are accessible


Raft
----
Raft Consensus status. Checks if all data and witness nodes are participating
in raft and have the same leader.

Result: Ok, raft Consensus is working correctly


Replication Slots
-----------------
Checks if all PGD replication slots are working correctly.

Result: Ok, all PGD replication slots are working correctly


Clock Drift
-----------
Clock drift between nodes. Uses raft leader as reference node to calculate
clock drift. High clock drift can affect conflict resolution and potentially
cause inconsistency.

Result: Ok, clock drift is within permissible limit


Versions
--------
Checks if all nodes are running the same PGD version.

Result: Ok, all nodes are running the same PGD version
```

Or, you can use `pgd nodes list` to ask PGD to show you the data-bearing nodes in the cluster:

```
pgd nodes list
```

output

```
Node Name Group Name   Node Kind Join State Node Status
--------- ------------ --------- ---------- -----------
kaftan    dc1_subgroup data      ACTIVE     Up
kaolin    dc1_subgroup data      ACTIVE     Up
kaboom    dc1_subgroup data      ACTIVE     Up
```

Explore your cluster

- Connect to your database to applications.
- Explore replication with hands-on exercises.
- Explore failover with hands-on exercises.
- Understand conflicts by creating and monitoring them.
- Take the next steps for working with your cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.3 Deploying an EDB Postgres Distributed example cluster on AWS

This quick start sets up EDB Postgres Distributed with an Always-on Single Location architecture using Amazon EC2.

Introducing TPA and PGD

We created TPA to make installing and managing various Postgres configurations easily repeatable. TPA orchestrates creating and deploying Postgres. In this quick start, you install TPA first. If you already have TPA installed, you can skip those steps. You can use TPA to deploy various configurations of Postgres clusters.

PGD is a multi-master replicating implementation of Postgres designed for high performance and availability. The installation of PGD is orchestrated by TPA. You'll use TPA to generate a configuration file for a PGD demonstration cluster. This cluster uses Amazon EC2 instances configures your cluster with three data nodes, cohosting three PGD Proxy servers, along with a Barman node for backup. You can then use TPA to provision and deploy the required configuration and software to each node.

Preparation

> **Note**
>
> This set of steps is specifically for Ubuntu 22.04 LTS on Intel/AMD processors.

EDB account

To install both TPA and PGD, you will need an EDB Repos 2.0 token to gain access to the EDB private software repositories. For instructions on obtaining this token, see: Get your token.

Install curl

You use the `curl` command to retrieve installation scripts from repositories. On Ubuntu, curl isn't installed by default. To see if it's present, run `curl` in the terminal:

```
$ curl
Command 'curl' not found, but can be installed with:
sudo apt install curl
```

If not found, run:

```
sudo apt -y install curl
```

Setting environment variables

First, set the `EDB_SUBSCRIPTION_TOKEN` environment variable to the value of your EDB repo token, obtained in the EDB account step.

```
export EDB_SUBSCRIPTION_TOKEN=<your-repo-token>
```

You can add this to your `.bashrc` script or similar shell profile to ensure it's always set.

Configure the repository

All the software needed for this example is available from the EDB Postgres Distributed package repository. The following command downloads and runs a script to configure the EDB Postgres Distributed repository. This repository also contains the TPA packages.

```
curl -1sLf "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.deb.sh" | sudo -E
bash
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Troubleshooting repo access**
>
> The script should produce output starting with:
>
> ```
> Executing the  setup script for the 'enterprisedb/postgres_distributed' repository ...
> ```
>
> If it produces no output or an error, double-check that you entered your token correctly. If the problem persists,contact Support for assistance.

Installing Trusted Postgres Architect (TPA)

You'll use TPA to provision and deploy PGD. If you previously installed TPA, you can move on to thenext step. You'll find full instructions for installing TPA in theTrusted Postgres Architect documentation, which we've also included here.

Linux environment

TPA supports several distributions of Linux as a host platform. These examples are written for Ubuntu 22.04, but steps are similar for other supported platforms.

Install the TPA package

```
sudo apt install tpaexec
```

Configuring TPA

You need to configure TPA, which configures TPA's Python environment. Call `tpaexec` with the command `setup`:

```
sudo /opt/EDB/TPA/bin/tpaexec setup
export PATH=$PATH:/opt/EDB/TPA/bin
```

You can add the `export` command to your shell's profile.

Testing the TPA installation

You can verify TPA is correctly installed by running `selftest`:

```
tpaexec selftest
```

TPA is now installed.

AWS Credentials

TPA uses your AWS credentials to perform the deployment onto AWS. Unless you have a corporate-managed account, you need to get your credentials from AWS. Corporate-managed accounts have their own process for obtaining credentials.

Your credentials consist of an AWS Access Key ID and a Secret Access Key. You also need to select an AWS default region for your work.

Set the environment variables `AWS_ACCESS_KEY_ID`, `AWS_SECRET_ACCESS_KEY`, and `AWS_DEFAULT_REGION` to the values of your AWS credentials. To ensure they're always set, you can add these to your `.bashrc` or similar shell profile.

```
$ export AWS_ACCESS_KEY_ID=THISISJUSTANEXAMPLE
$ export AWS_SECRET_ACCESS_KEY=d0ntU5E/Th1SAs1ts/jUs7anEXAMPLEKEY
$ export AWS_DEFAULT_REGION=us-west-2
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Your account needs the necessary permissions to create and manage the resources that TPA uses. TPA AWS platform details the permissions that you need. Consult your AWS administrator if you need help with this.

Installing PGD using TPA

Generating a configuration file

Run the `tpaexec configure` command to generate a configuration folder:

```
tpaexec configure democluster \
  --architecture PGD-Always-ON \
  --platform aws \
  --region eu-west-1 \
  --edb-postgres-advanced 16 \
  --redwood \
  --location-names dc1 \
  --pgd-proxy-routing local \
  --no-git \
  --hostnames-unsorted
```

You specify the PGD-Always-ON architecture (`--architecture PGD-Always-ON`), which sets up the configuration for PGD's Always-on architectures. As part of the default architecture, this configures your cluster with three data nodes, cohosting three PGD Proxy servers, along with a Barman node for backup.

Specify that you're using AWS (`--platform aws`) and eu-west-1 as the region (`--region eu-west-1`).

TPA defaults to t3.micro instances on AWS. This is enough for this demonstration and also suitable for use with an AWS free tier account.

> **AWS free tier limitations**
>
> AWS free tier limitations for EC2 are based on hours of instance usage. Depending on how much time you spend testing, you might exceed these limits and incur charges.

By default, TPA configures Debian as the default OS for all nodes on AWS.

> **Deployment platforms**
>
> Other Linux platforms are supported as deployment targets for PGD. See the EDB Postgres Distributed compatibility table for details.
>
> Observe that you don't have to deploy PGD to the same platform you're using to run TPA!

Specify that the data nodes will be running EDB Postgres Advanced Server v16 (`--edb-postgres-advanced 16`) with Oracle compatibility (`--redwood`).

You set the notional location of the nodes to `dc1` using `--location-names` . You then set `--pgd-proxy-routing` to `local` so that proxy routing can route traffic to all nodes in each location.

By default, TPA commits configuration changes to a Git repository. For this example, you don't need to do that, so you pass the `--no-git` flag.

Finally, you ask TPA to generate repeatable hostnames for the nodes by passing `--hostnames-unsorted` . Otherwise, it selects hostnames at random from a predefined list of suitable words.

This command creates a subdirectory in the current working directory called `democluster` . It contains the `config.yml` configuration file TPA uses to create the cluster. You can view it using:

```
less democluster/config.yml
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Further reading**
>
> - View the full set of available options by running:
>
>   ```
>   tpaexec configure --architecture PGD-Always-ON --help
>   ```
>
> - More details on PGD-Always-ON configuration options in Deploying with TPA
> - PGD-Always-ON in the TPA documentation
> - `tpaexec configure` in the TPA documentation
> - AWS platform in the TPA documentation

Provisioning the cluster:

Next, allocate the resources needed to run the configuration you just created using the `tpaexec provision` command:

```
tpaexec provision democluster
```

Since you specified AWS as the platform (the default platform), TPA provisions EC2 instances, VPCs, subnets, routing tables, internet gateways, security groups, EBS volumes, elastic IPs, and so on.

Because you didn't specify an existing one when configuring, TPA also prompts you to confirm the creation of an S3 bucket.

> **Remember to remove the bucket when you're done testing!**
>
> TPA doesn't remove the bucket that it creates in this step when you later deprovision the cluster. Take note of the name now, so that you can be sure to remove it later.

> **Further reading**
>
> - `tpaexec provision` in the Trusted Postgres Architect documentation

Deploying the cluster

With configuration in place and infrastructure provisioned, you can now deploy the distributed cluster:

```
tpaexec deploy democluster
```

TPA applies the configuration, installing the needed packages and setting up the actual EDB Postgres Distributed cluster.

> **Further reading**
>
> - `tpaexec deploy` in the Trusted Postgres Architect documentation

Connecting to the cluster

You're now ready to log in to one of the nodes of the cluster with SSH and then connect to the database. Part of the configuration process is to set up SSH logins for all the nodes, complete with keys. To use the SSH configuration, you need to be in the `democluster` directory created by the `tpaexec configure` command earlier:

```
cd democluster
```

From there, you can run `ssh -F ssh_config <hostname>` to establish an SSH connection. You will connect to kaboom, the first database node in the cluster:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
ssh -F ssh_config kaboom
```

output

```
[admin@kaboom ~]#
```

Notice that you're logged in as admin on kaboom.

You now need to adopt the identity of the enterprisedb user. This user is preconfigured and authorized to connect to the cluster's nodes.

```
sudo -iu enterprisedb
```

output

```
enterprisedb@kaboom:~ $
```

You can now run the `psql` command to access the bdrdb database:

```
psql bdrdb
```

output

```
psql (16.2.0, server 16.2.0)
Type "help" for help.

bdrdb=#
```

You're directly connected to the Postgres database running on the kaboom node and can start issuing SQL commands.

To leave the SQL client, enter `exit`.

Using PGD CLI

The pgd utility, also known as the PGD CLI, lets you control and manage your EDB Postgres Distributed cluster. It's already installed on the node.

You can use it to check the cluster's health by running `pgd cluster show --health`:

```
pgd cluster show --health
```

output

```
Check             Status Details
----------------- ------ ------------------------------------------------
Connections       Ok     All BDR nodes are accessible
Raft              Ok     Raft Consensus is working correctly
Replication Slots Ok     All PGD replication slots are working correctly
Clock Drift        Ok     Clock drift is within permissible limit
Versions          Ok     All nodes are running the same PGD version
```

Or, you can use `pgd nodes list` to ask PGD to show you the data-bearing nodes in the cluster:

```
pgd nodes list
```

output

```
Node Name Group Name   Node Kind Join State Node Status
--------- ------------ --------- ---------- -----------
kaftan    dc1_subgroup data      ACTIVE     Up
kaolin    dc1_subgroup data      ACTIVE     Up
kaboom    dc1_subgroup data      ACTIVE     Up
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Explore your cluster

- Connect your database to applications.
- Explore replication with hands-on exercises.
- Explore failover with hands-on exercises.
- Understand conflicts by creating and monitoring them.
- Take the next steps for working with your cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.4 Deploying an EDB Postgres Distributed example cluster on Azure and Google cloud platforms

Deploying on Azure and Google clouds

For most cloud platforms, such as Azure and Google Cloud Platform, you create Linux hosts on the cloud platform you're using. You can then use the Deploying on Linux hosts quick start to deploy PGD to those Linux hosts.

- Azure users can follow a Microsoft guide on how to provision Azure VMs loaded with Linux.
- Google Cloud Platform users can follow a Google guide on how to provision GCP VMs with Linux loaded.

Then continue with Deploying on Linux hosts.

For AWS users, see the Deploying on AWS quick start. Using this quick start, TPA provisions the hosts needed to create your cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.5 Connecting to your database

Connecting your application or remotely connecting to your new EDB Postgres Distributed cluster involves:

- Getting credentials and optionally creating a `.pgpass` file
- Establishing the IP address of any PGD Proxy hosts you want to connect to
- Ensuring that you can connect to that IP address
- Getting an appropriate Postgres client
- Connecting the client to the cluster

Getting credentials

The default user, enterprisedb, was created in the cluster by tpaexec. It also generated passwords for that user as part of the provisioning. To get the password, run:

```
tpaexec show-password democluster enterprisedb
```

This command returns a string that's the password for the enterprisedb user. If you want, you can use that string when prompted for a password.

Creating a .pgpass file

You can avoid entering passwords for psql and other Postgres clients by creating a `.pgpass` file in your home directory. It contains password details that applications can look up when connecting. After getting the password (see Getting credentials), you can open the `.pgpass` file using your preferred editor.

In the file, enter:

```
*:*:bdrdb:enterprisedb:<your password>
```

Save the file and exit the editor. To secure the file, run the following command. This command gives read and write access only to you.

```
chmod 0600 ~/.pgpass
```

Establishing the IP address

Docker

Your Docker quick start cluster is by default accessible on the IP addresses 10.33.111.18 (kaboom), 10.33.111.19 (kaftan), 10.33.111.20 (kaolin), and 10.33.111.21 (kapok). TPA generates these addresses.

AWS

You can refer to the IP addresses in `democluster/ssh_config`. Alternatively, run:

```
aws ec2 --region eu-west-1 describe-instances --query 'Reservations[*].Instances[*].
{PublicIpAddress:PublicIpAddress,Name:Tags[?Key==`Name`]|[0].Value}'
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

output

```
[
    [
        {
            "PublicIpAddress": "54.217.130.13",
            "Name": "kapok"
        }
    ],
    [
        {
            "PublicIpAddress": "54.170.119.101",
            "Name": "kaolin"
        }
    ],
    [
        {
            "PublicIpAddress": "3.250.235.130",
            "Name": "kaftan"
        }
    ],
    [
        {
            "PublicIpAddress": "34.247.188.211",
            "Name": "kaboom"
        }
    ]
]
```

This command shows you EC2's list of public IP addresses for the cluster instances.

Linux hosts

You set IP addresses for your Linux servers when you configured the cluster in the quick start. Use those addresses.

Ensure you can connect to your IP addresses

Linux hosts and Docker

You don't need to perform any configuration to connect these.

AWS

AWS is configured to allow outside access only to its SSH endpoints. To allow Postgres clients to connect from outside the AWS cloud, you need to enable the transit of traffic on port 6432.

Get your own external IP address or the external IP address of the system you want to connect to the cluster. One way to do this is to run:

```
curl https://checkip.amazonaws.com
```

output

```
89.97.100.108
```

You also need the security groupid for your cluster. Run:

```
aws ec2 --region eu-west-1 describe-security-groups --filter Name=group-name,Values="*democluster*" | grep GroupId
```

output

```
            "GroupId": "sg-072f996360ba20d5c",
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Enter the correct region for your cluster, which you set when you configured it.

```
aws ec2 authorize-security-group-ingress --group-id <SECURITYGROUPID> --protocol tcp --port 6432 --cidr <YOURIP>/32 --region eu-west-1
```

Again, make sure you put in the correct region for your cluster.

You can read more about this command in Add rules to your security group in the AWS CLI guide.

Getting an appropriate Postgres client

Unless you installed Postgres on your local system, you probably need to install a client application, such as psql, to connect to your database cluster.

On Ubuntu, for example, you can run:

```
sudo apt install postgresql-client
```

This command installs psql, along with some other tools but without installing the Postgres database locally.

Connecting the client to the cluster

After you install psql or a similar client, you can connect to the cluster. Run:

```
psql -h <ipaddressofnode> -p 6432 -U enterprisedb bdrdb
```

output

```
psql (16.2, server 16.2.0)
SSL connection (protocol: TLSv1.3, cipher: TLS_AES_256_GCM_SHA384, bits: 256, compression: off)
Type "help" for help.

bdrdb=#
```

Use the `.pgpass` file with clients that support it, or use the host, port, user, password, and database name to connect with other applications.

Using proxy failover to connect the client to the cluster

By listing all the addresses of proxies as the host, you can ensure that the client will always failover and connect to the first available proxy in the event of a proxy failing.

```
psql -h <ipaddressofnode1>,<ipaddressofnode2>,<ipaddressofnode3> -U enterprisedb -p 6432 bdrdb
```

output

```
psql (16.2, server 16.2.0)
SSL connection (protocol: TLSv1.3, cipher: TLS_AES_256_GCM_SHA384, bits: 256, compression: off)
Type "help" for help.

bdrdb=#
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Creating a connection URL

Many applications use a connection URL to connect to the database. To create a connection URL, you need to assemble a string in the format:

```
postgresql://<user>@<ipaddressofnode1>:6432,<ipaddressofnode2>:6432,<ipaddressofnode3>:6432/bdrdb
```

This format of the string can be used with the `psql` command, so if your database nodes are on IP addresses 192.168.9.10, 192.168.10.10, and 192.168.10.11, you can use:

```
psql postgresql://enterprisedb@192.168.9.10:6432,192.168.10.10:6432,192.168.11.10:6432/bdrdb
```

You can also embed the password in the created URL. If you're using the enterprisedb user, and the password for the enterprisedb user is `notasecret`, then the URL looks like:

```
psql postgresql://enterprisedb:notasecret@192.168.9.10:6432,192.168.10.10:6432,192.168.11.10:6432/bdrdb
```

Actual passwords are more complex than that and can contain special characters. You need to urlencode the password to ensure that it doesn't trip up the shell, the command, or the driver you're using.

> **Passwords should not be embedded**
>
> While we have shown you how to embed a password, we recommend that you do not do this. The password is easily extracted from the URL and can easily be saved in insecure locations. Consider other ways of passing the password.

Making a Java connection URL

Finally, the URL you created is fine for many Postgres applications and clients, but those based on Java require one change to allow Java to invoke the appropriate driver. Precede the URL with `jdbc:` to make a Java compatible URL:

```
jdbc:postgresql://enterprisedb@192.168.9.10:6432,192.168.10.10:6432,192.168.11.10:6432/bdrdb
```

Moving on

You're now equipped to connect your applications to your cluster, with all the connection credentials and URLs you need.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.6 Exploring replication with PGD

Explore replication with PGD

With the cluster up and running, it's useful to run some basic checks to see how effectively it's replicating.

The following example shows one quick way to do this, but you must ensure that any testing you perform is appropriate for your use case.

Preparation

Ensure your cluster is ready to perform replication. If you haven't installed a cluster yet, use one of the quick start guides to get going.

1. Log in to the database on the first host.
2. Run `select bdr.wait_slot_confirm_lsn(NULL, NULL);`.

When the query returns, the cluster is ready.

Create data

The simplest way to test that the cluster is replicating is to log in to a node, create a table, populate it, and see the data you populated appear on a second node. On the first node:

1. Create a table:

```
CREATE TABLE quicktest ( id SERIAL PRIMARY KEY, value INT );
```

2. Populate the table:

```
INSERT INTO quicktest (value) SELECT
random()*10000
FROM
generate_series(1,10000);
```

3. Monitor replication performance:

```
select * from bdr.node_replication_rates;
```

4. Get a sum of the value column (for checking):

```
select COUNT(*),SUM(value) from quicktest;
```

Check data

1. To confirm the data was successfully replicated, log in to a second node.
    1. Get a sum of the value column (for checking):

    ```
    select COUNT(*),SUM(value) from quicktest;
    ```

    2. Compare with the result from the first node.
2. Log in to a third node.
    1. Get a sum of the value column (for checking):

    ```
    select COUNT(*),SUM(value) from quicktest;
    ```

    2. Compare with the result from the first and second nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Worked example

Preparation

The cluster in this example has three data nodes: kaboom, kaftan, and kaolin. The example uses kaboom as the first node. Log in to kaboom and then into kaboom's Postgres server:

```
cd democluster
ssh -F ssh_config kaboom
sudo -iu enterprisedb psql bdrdb
```

Ensure the cluster is ready

To ensure that the cluster is ready to go, run:

```
select bdr.wait_slot_confirm_lsn(NULL, NULL);
```

output

```
 wait_slot_confirm_lsn
-----------------------

(1 row)
```

If the cluster is busy initializing, this query waits and returns when the cluster is ready.

Create data

On the first node (kaboom), create a table

Run:

```
CREATE TABLE quicktest ( id SERIAL PRIMARY KEY, value INT );
```

output

```
CREATE TABLE
```

On kaboom, populate the table

This command generates a table of 10000 rows of random values:

```
INSERT INTO quicktest (value) SELECT random()*10000 FROM generate_series(1,10000);
```

output

```
INSERT 0 10000
```

On kaboom, monitor performance

As soon as possible, run the following command. It shows statistics about how quickly that data was replicated to the other two nodes.

```
select * from bdr.node_replication_rates;
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

output

```
 peer_node_id | target_name | sent_lsn  | replay_lsn | replay_lag | replay_lag_bytes | replay_lag_size | apply_rate |
catchup_interval
--------------+-------------+-----------+------------+------------+------------------+-----------------+------------+--
-------------
   3490219809 | kaftan      | 0/F57D120 | 0/F57D120  | 00:00:00   |                0 | 0 bytes         |       9158 |
00:00:00
   2111777360 | kaolin      | 0/F57D120 | 0/F57D120  | 00:00:00   |                0 | 0 bytes         |       9293 |
00:00:00
(2 rows)
```

The `replay_lag` values are 0, showing no lag. The LSN values are in sync, meaning the data is already replicated.

On kaboom get a checksum

Run:

```
select COUNT(*),SUM(value) from quicktest;
```

This command calculates a sum of the values from the generated data:

```
bdrdb=# select COUNT(*),SUM(value) from quicktest;
```

output

```
 count  |    sum
--------+-----------
 100000 | 498884606
(1 row)
```

Your sum will be different because the values in the table are random numbers, but the count will be 100000.

Check data

The second host is kaftan. In another window or session, log in to kaftan's Postgres server:

```
cd democluster
ssh -F ssh_config kaftan
sudo -iu enterprisedb psql bdrdb
```

On the second node (kaftan), get a checksum

Run:

```
select COUNT(*),SUM(value) from quicktest;
```

This command gets the second node's values for the generated data:

```
bdrdb=# select COUNT(*),SUM(value) from quicktest;
```

output

```
 count  |    sum
--------+-----------
 100000 | 498884606
(1 row)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Compare with the result from the first node (kaboom)

The values are identical.

You can repeat the process with the third node (kaolin), or generate new data on any node and see it replicate to the other nodes.

Log in to the third node (kaolin)

The third and last node is kaolin. In another window or session, log in to kaolin and then to kaolin's Postgres server:

```
cd democluster
ssh -F ssh_config kaolin
sudo -iu enterprisedb psql bdrdb
```

On kaolin, get a checksum

Run:

```
select COUNT(*),SUM(value) from quicktest;
```

This command gets kaolin's values for the generated data:

```
bdrdb=# select COUNT(*),SUM(value) from quicktest;
```

output

```
 count  |    sum
--------+-----------
 100000 | 498884606
(1 row)
```

Compare the results

Compare the result from the first and second nodes (kaboom and kaftan) with the result from kaolin. The values are identical on all three nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.7 Exploring failover handling with PGD

With a high-availability cluster, the ability to failover is crucial to the overall resilience of the cluster. When the lead data nodes stops working for whatever reason, applications need to be able to continue working with the database with little or no interruption. For PGD, that means directing applications to the new lead data node, which takes over automatically. This is where PGD Proxy is useful. It works with the cluster and directs traffic to the lead data node automatically.

In this exercise, you'll create an application that sends data to the database regularly. Then you'll first softly switch lead data node by requesting a change through the PGD CLI. And then you'll forcibly shut down a database instance and see how PGD handles that.

Your quick started configuration

This exploration assumes that you created your PGD cluster using the quick start for Docker, the quick start for AWS, or the quick start for Linux hosts.

At the end of each quick start, you'll have a cluster with four nodes and these roles:

Host name	Host role
kaboom	PGD data node and pgd-proxy co-host
kaftan	PGD data node and pgd-proxy co-host
kaolin	PGD data node and pgd-proxy co-host
kapok	Barman backup node

You'll use these hostnames throughout this exercise.

> **A best practice recommendation**
>
> This example is based on the quick start configuration. For speed and simplicity, it uses the Barman backup server in place of creating a bastion server. It also uses the Barman login to the Postgres cluster.
>
> In a production environment, we recommend that you create a separate bastion server to run the failover experiment from and that you create an appropriate Postgres user to log in to the cluster.

Installing xpanes

> **Xpanes optional**
>
> We recommend the xpanes utility for this exercise. It allows you to easily switch between multiple terminal sessions. If you prefer to use multiple terminals, tmux, or another terminal multiplexer, you can do so. Just make sure you can easily switch between multiple terminal sessions.

You'll use xpanes, a utility that allows you to quickly create multiple terminal sessions that you can easily switch between. It isn't installed by default, so you have to install it. For this exercise, you launch xpanes from the system where you ran tpaexec to configure your quick-start cluster.

If the system is running Ubuntu, run:

```
sudo apt install software-properties-common
sudo add-apt-repository ppa:greymd/tmux-xpanes
sudo apt update
sudo apt install tmux-xpanes
```

These are the installation instructions from the xpanes repository. If you aren't on Ubuntu, the repository also contains installation instructions for other systems.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.


Connecting to the four servers

With xpanes installed, you can create an SSH session with all four servers by running:

```
cd democluster
xpanes -d -c "ssh -F ssh_config {}" "kaboom" "kaolin" "kaftan" "kapok"
```

After running these commands, there are four panes. The four panes are connected to kaboom, kaolin, kaftan, and kapok and you're logged in as the root user on each. You need this privilege so you can easily stop and start services later in the exercise.

Press **Control-b** followed by **q** to briefly display the numeric values for each pane.



To switch the focus between the panes, you can use **Control-b** and the cursor keys to navigate between them. Or you can use **Control-b** followed by **q** and the number of the pane you want to focus on. We'll show both ways.

Use **Control-b ↓ Control-b →** or **Control-b q 3** to move the focus to the bottom-right pane, which is the kapok host. This server is responsible for performing backups. You'll use this as the base of operations for your demo application. You can use Barman credentials to connect to the database servers and proxies:

```
sudo -iu barman
psql -h kaboom -p 6432 bdrdb
```

This code connects to the proxy on the kaboom host, which also runs a Postgres instance as part of the cluster.

The next step is to create the table for your application to write to:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
drop table if exists ping cascade;
CREATE TABLE ping (id SERIAL PRIMARY KEY, node TEXT, timestamp TEXT) ;
```

This code first drops the `ping` table. Then it re-creates the `ping` table with an id primary key and two text fields for a node and timestamp. The table should now be ready. To verify that it is, use **Control-b ← Control-b ↑** or **Control-b q 0** to move to the top left pane, which puts you on the kaboom server. In this pane, become the enterprisedb user so you can easily connect to the database:

```
sudo -iu enterprisedb
```

You can now connect to the local database by running:

```
psql bdrdb
```

This command connects you directly to the local database instance on kaboom. Use `\dt` to view the available tables:

```
bdrdb=# \dt
       List of relations
 Schema | Name | Type  | Owner
--------+------+-------+--------
 public | ping | table | barman
(1 row)
```

Running `\d ping` shows that the DDL to create ping is on the kaboom server:

```
bdrdb=# \d ping
                           Table "public.ping"
  Column   |  Type   | Collation | Nullable | Default
-----------+---------+-----------+----------+---------------------------------
 id        | integer |           | not null | nextval('ping_id_seq'::regclass)
 node      | text    |           |          |
 timestamp | text    |           |          |
Indexes:
    "ping_pkey" PRIMARY KEY, btree (id)
```

If you want to be sure that this table is replicated, you can connect to another node in the cluster and look. The `\c` command in psql lets you connect to another server. To connect to the kaftan node, run:

```
\c - - kaftan
```

You'll see a login message similar to this:

```
psql.bin (16.2.0, server 16.2.0) SSL connection (protocol: TLSv1.3, cipher: TLS_AES_256_GCM_SHA384, compression: off)
You are now connected to database "bdrdb" as user "enterprisedb" on host "kaftan" (address "10.33.25.233") at port
"5444".
bdrdb=#
```

Run `\dt` and `\d ping`, and you'll see the same results on the kaftan node.

To reconnect to the kaboom node, run:

```
\c - - kaboom
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Setting up a monitor

Next, you want to monitor the activity of the ping table. Enter this SQL to display the 10 most recent entries:

```
select * from ping order by timestamp desc limit 10;
```

To run this command more than once, use the `\watch` command in the shell, which executes the last query at regular intervals. To update every second, enter:

```
\watch 1
```

So far, there's nothing to see. You'll add activity soon.

Creating pings

Return to the Barman host kapok by using **Control-b ↓** **Control-b →** or **Control-b q 3**.

This session is still logged into the psql session. Since you next want to run a shell script, you need to exit psql. Press **Control-d**.

The shell prompt now reads:

```
barman@kapok:~$
```

If it says `admin@kapok` or `root@kapok`, run `sudo -iu barman` to become the Barman user again.

The application you'll create is simple. It gets the node to write to and a timestamp for the ping. Then, as quickly as it can, it writes a new ping to the ping table.

In the shell, enter:

```
while true; do psql -h kaftan,kaolin,kaboom -p 6432 bdrdb -c "INSERT INTO ping(node, timestamp) select node_name,
current_timestamp from bdr.local_node_summary;"; done
```

In a more readable form, that is:

```
while true;
    do psql -h kaftan,kaolin,kaboom -p 6432 bdrdb -c \
        "INSERT INTO ping(node, timestamp) select node_name, current_timestamp from bdr.local_node_summary;"
    done
```

In a constant loop, you call the `psql` command, telling it to connect to any of the three proxies as hosts, giving the proxy port and selecting the bdrdb database. You also pass a command that inserts two values into the ping table. One of the values comes from `bdr.local_node_summary`, which contains the name of the node you're actually connected to. The other value is the current time.

Once the loop is running, new entries appear in the table. You'll see them in the top-left pane where you set up the monitor.

You can now start testing failover.

Changing the write leader

For this part of the process, switch to the host kaftan, which is in the lower-left corner. Use **Control-b ←** or **Control-b q 2** to switch focus to it.

To gain appropriate privileges to run pgd, at the PGD command line interface, run:

```
sudo -iu enterprisedb
```

To see the state of the cluster, run:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
pgd groups list -v
```

You'll see output like this:

```
Group Name   Parent Group Name Group Type Nodes
------------ ----------------- ---------- -----
democluster                    global     0
dc1_subgroup democluster       data       3
```

The global group `democluster` includes all the subgroups. The `dc1_subgroup` is the data cluster you're working with. That group name value is derived from the location given in the quick start when you configured this cluster. Each location gets its own subgroup so you can manage it independently of other locations, or clusters.

Send a `group set-leader` command to the cluster group to change leader. Run this command:

```
pgd group dc1_subgroup set-leader kaolin
```

The node name is the host name for another data node in the dc1_subgroup group.

You'll see one of two responses. If kaolin was the write leader already. you will see:

```
Status Message
------ ----------------------------------------
OK     Node kaolin is already the write leader
```

This means that kaolin was already elected write leader, so switching has no effect. For this exercise, retry the switchover to another host, substituting kaboom or kaftan as the node name.

When you select a host that wasn't the current write leader, you'll see the other response:

```
Status Message
------ ----------------------------
OK     Command executed successfully
```

If you look in the top-left pane, you'll see the inserts from the script switching and being written to the node you just switched to.

> **Observe the id number**
>
> Notice that the id number being generated is from a completely different range of values, too. That's because the system transparently made the sequence generating the ID a global sequence. For more about global sequences and how they work, see Sequences.

You might also notice an error in the lower-right pane, as an inflight update is canceled by the switch in write leader. The script then continues writing.

Losing a node

Being able to switch leader is useful for planned maintenance; you tell the cluster to change configuration. What if unexpected changes happen? You'll create that scenario now.

In the lower-left pane, set the leader to kaolin.

```
pgd group dc1_subgroup set-leader kaolin
```

Then change focus to the top-right pane using **Control-b ↑ Control-b →** or **Control-b q 1**, which is the session on the kaolin host.

Turn off the Postgres server by running:

```
sudo systemctl stop postgres.service
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

In the top-left pane, you'll see the monitored table switch from kaolin to another node as the cluster subgroup picks a new leader. The script in the lower-right pane might show some errors as updates are canceled. However, as soon as a new leader is elected, it starts routing traffic to that leader.

Showing node states

Switch to the lower-left pane using **Control-b ↓** **Control-b ←** or **Control-b q 2**, and run:

```
pgd nodes list
```

You'll see something like:

```
Node Name Group Name   Node Kind Join State Node Status
--------- ------------ --------- ---------- -----------
kaftan    dc1_subgroup data      ACTIVE     Up
kaolin    dc1_subgroup data      ACTIVE     Unreachable
kaboom    dc1_subgroup data      ACTIVE     Up
```

The kaolin node is down, and updates are going to a different write leader.

Monitoring lag

While kaolin is down, the logical replication at the heart of PGD is tracking how far out of sync kaolin is with the cluster. To see the details, run:

```
psql bdrdb -c "select * from bdr.node_replication_rates;"
```

This command displays the current replication rates between servers:

```
 peer_node_id | target_name | sent_lsn  | replay_lsn |   replay_lag    | replay_lag_bytes | replay_lag_size |
apply_rate | catchup_interval
--------------+-------------+-----------+------------+-----------------+------------------+-----------------+----------
+------------------
   2710197610 | kaboom      | 0/769F650 | 0/769F650  | 00:00:00        |                0 | 0 bytes         |
1861 | 00:00:00
              | kaolin      | 0/7656648 | 0/7656648  | 00:03:07.252266 |           299016 | 292 kB          |
|
(2 rows)
```

Looking at this output, you can see kaolin has a three-minute replay lag and around 292KB of data to catch up on if it came back now. The longer kaolin is down, the larger the replay lag gets. If you rerun the monitoring command, you'll see the numbers went up:

```
 peer_node_id | target_name | sent_lsn  | replay_lsn |   replay_lag    | replay_lag_bytes | replay_lag_size |
apply_rate | catchup_interval
--------------+-------------+-----------+------------+-----------------+------------------+-----------------+----------
+------------------
   2710197610 | kaboom      | 0/76B1D28 | 0/76B1D28  | 00:00:00        |                0 | 0 bytes         |
1743 | 00:00:00
              | kaolin      | 0/7656648 | 0/7656648  | 00:03:53.045704 |           374496 | 366 kB          |
|
(2 rows)
```

Another 46 seconds have passed, and the lag has grown by 74KB. Next, bring back the node, and see how the system recovers.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Restarting a node

You can bring back the Postgres service on kaolin. Switch back to the top-right pane using **Control-b ↑** **Control-b →** or **Control-b q 1**, and run:

```
sudo systemctl start postgres.service
```

You won't see any change. Although the database service is back up and running, the cluster isn't holding an election, and so the leader remains in place. Switch to the lower-left pane using **Control-b ↓** **Control-b ←** or **Control-b q 2**, and run:

```
pgd nodes list
```

Now you'll see:

```
Node Name Group Name   Node Kind Join State Node Status
--------- ------------ --------- ---------- -----------
kaftan    dc1_subgroup data      ACTIVE     Up
kaolin    dc1_subgroup data      ACTIVE     Up
kaboom    dc1_subgroup data      ACTIVE     Up
```

As soon as kaolin is back in the cluster, it begins synchronizing with the cluster. It does that by catching up on that replay data. Run:

```
psql bdrdb -c "select * from bdr.node_replication_rates;"
```

The output looks like this:

```
 peer_node_id | target_name | sent_lsn  | replay_lsn | replay_lag | replay_lag_bytes | replay_lag_size | apply_rate |
catchup_interval
--------------+-------------+-----------+------------+------------+------------------+-----------------+------------+--
-------------
   2710197610 | kaboom      | 0/8092938 | 0/8092938  | 00:00:00   |                0 | 0 bytes         |       2321 |
00:00:00
   2111777360 | kaolin      | 0/8092938 | 0/8092938  | 00:00:00   |                0 | 0 bytes         |     337426 |
00:00:00
(2 rows)
```

As you can see, there's no replay lag now, as kaolin has completely caught up.

With kaolin fully back in service, you can leave everything as it is. There's no need to change the server that's write leader. The failover mechanism is always ready to bring another server up to write leader when needed.

If you want, you can make kaolin leader again by running:

```
pgd group dc1_subgroup set leader kaolin
```

This command returns kaolin to write lead. The application's updates will follow, as the proxies track the write leader.

Proxy failover

> **Note**
>
> The command `pgd show-proxies` is deprecated as of PGD v5.7.0. It is still accessible as a legacy command.

Proxies can also failover. To experience this, make sure your focus is still on the lower-left pane, and run:

```
pgd show-proxies
```

You'll see:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
Proxy  Group        Listen Addrs Listen Port Read Listen Addrs Read Listen Port
------ ------------ ------------ ----------- ----------------- ----------------
kaboom dc1_subgroup [0.0.0.0]    6432        [0.0.0.0]         6433
kaftan dc1_subgroup [0.0.0.0]    6432        [0.0.0.0]         6433
kaolin dc1_subgroup [0.0.0.0]    6432        [0.0.0.0]         6433
```

Enter `exit` to exit the enterprisedb user and return to the admin/root shell. You can now stop the proxy service on this node by running:

```
systemctl stop pgd-proxy.service
```

A brief error appears in the lower-right window as the script switches to another proxy. The write leader doesn't change, though, so the switch of proxy doesn't show in the top-left pane where the monitor query is running.

Bring the proxy service on kaftan back by running:

```
systemctl start pgd-proxy.service
```

> **Exiting tmux**
>
> You can quickly exit tmux and all the associated sessions. First terminate any running processes, as they otherwise continue running after the session is killed. Press **Control-B** and then enter `:kill-session`. This approach is simpler than quitting each pane's session one at a time using **Control-D** or `exit`.

Other scenarios

This example uses the quick start configuration of three data nodes and one backup node. You can configure a cluster to have two data nodes and a witness node, which is less resilient to a node failing. Or you can configure five data nodes, which is much more resilient to a node failing. With this configuration, you can explore how failover works for your applications. For clusters with multiple locations, the same basic rules apply: taking a server down elects a new write leader that proxies now point to.

Further reading

- Read more about the management capabilities of the PGD CLI.
- Learn more about monitoring replication using SQL.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.8 Exploring conflict handling with PGD

In a multi-master architecture like PGD, conflicts happen. PGD is built to handle them.

A conflict can occur when one database node has an update from an application to a row and another node has a different update to the same row. This type of conflict is called a *row-level conflict*. Conflicts aren't errors. Resolving them effectively is core to how Postgres Distributed maintains consistency.

The best way to handle conflicts is to prevent them! Use PGD's Always-on architecture with proxies to ensure that your applications write to the same server in the cluster. is When conflicts occur, though, it's useful to know how PGD resolves them, how you can control that resolution, and how you can find out that they're happening. Row insertion and row updates are two actions that can cause conflicts.

To see how it works, you need to open a command line view of all the servers.

Your quick start configuration

This exploration assumes that you created your PGD cluster using the quick start for Docker, the quick start for AWS, or the quick start for Linux hosts.

At the end of each quick start, you'll have a cluster with four nodes and these roles:

Host name	Host role
kaboom	PGD data node and pgd-proxy co-host
kaftan	PGD data node and pgd-proxy co-host
kaolin	PGD data node and pgd-proxy co-host
kapok	Barman backup node

You'll use these hostnames throughout this exercise.

Installing xpanes

> **Xpanes optional**
>
> We recommend the `xpanes` utility for this exercise. It allows you to easily switch between multiple terminal sessions. If you prefer to use multiple terminals, tmux or another terminal multiplexer, you can do so. Just make sure you can easily switch between multiple terminal sessions.

You'll use `xpanes`, a utility that allows you to quickly create multiple terminal sessions that you can easily switch between. It isn't installed by default, so you'll have to install it. Start by connecting to the kaboom node with ssh:

```
cd democluster && ssh -F ssh_config kaboom
```

If you're running the quick start on Docker, you'll be using Rocky Linux, a Red Hat derivative. To perform the xpanes install, run:

```
dnf -y install xpanes
```

If you're running the quick start on AWS, you'll be using Debian Linux. To perform the xpanes install, run:

```
wget https://github.com/greymd/tmux-xpanes/releases/download/v4.1.4/tmux-xpanes_v4.1.4.deb
sudo apt -y install ./tmux-xpanes*.deb
rm tmux-xpanes*.deb
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Connecting to four servers

You need to be logged in as the enterprisedb user to allow authentication to work:

```
sudo -iu enterprisedb
```

Then, run the following command to connect to three database servers and a proxy server:

```
xpanes -d -c "psql postgresql://enterprisedb@{}/bdrdb?sslmode=require" "kaboom:5444" "kaftan:5444" "kaolin:5444"
"kaboom:6432"
```

xpanes takes the command after `-c` and uses the values in the arguments that follow to create a command to run. That means that, after you run it, there will be four panes. Three panes will be connected to the database nodes kaboom, kaftan, and kaolin on port 5444. One will be connected to the pgd-proxy running on kaboom on port 6432. Each one will be logged into the database as enterprisedb.

Press **Control-b** followed by **q** to briefly display the numeric values for each pane.



To switch the focus between the panes, you can use **Control-b** and the cursor keys to navigate between them. Or you can use **Control-b** followed by **q** and the number of the pane you want to focus on. We'll show both ways.

Move to the bottom-left pane using **Control-b ↓ Control-b → or **Control-b q 3**.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Preparing for conflicts

To make a conflict, you first need a simple table. In the pane that currently has focus, enter:

```
drop table if exists test_conflict;
create table test_conflict(
  id integer primary key ,
  value_1 text);
```

Monitoring conflicts

In the pane that currently has focus, enter:

```
select * from bdr.conflict_history_summary
\watch 1
```

The `select` command displays the conflict history for the cluster. The `\watch 1` command is a psql command that reruns the preceding command every second.

You are now ready to generate a conflict.

Creating a conflict

The most basic form of conflict is when an insert happens to a table on two different nodes and both have the same primary key. You can now create that scenario and observe it.

Move to the top-left pane using **Control-b ↑** **Control-b ←** or **Control-b q 0**. This pane is the kaboom node. Start a transaction there, and insert a row:

```
start transaction;
insert into test_conflict values (1, 'from kaboom');
```

Next, move to the top-right pane using **Control-b →** or **Control-b q 1**. This pane is the kaftan node. Here, you'll also start a transaction and insert into the same row with different data:


```
start transaction;
insert into test_conflict values (1, 'from kaftan');
```

You now have two transactions open on different servers, with an insert operation already performed successfully. You need to commit both transactions at this point:

- Use **Control-b ←** or **Control-b q 0**, and then enter `commit;`.
- Use **Control-b →** or **Control-b q 1**, and then enter `commit;`.

You'll see that both commits are working. However, in the bottom-right pane, you can see the conflict being detected.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.



A row in the conflict history now notes a conflict in the table where the `insert_exists`. It also notes that the resolution for this conflict is that the newer record, based on the timing of the commit, is retained. This conflict is called an INSERT/INSERT conflict. You can read more about this type of conflict in INSERT/INSERT conflicts.

Creating an update conflict

When different updates to the same records take place on different nodes, a conflict occurs. You can create that scenario with the current configuration, too. Leave `\watch 1` running in the bottom-right pane.

Move to the top-left pane using **Control-b ←** or **Control-b q 0**. This pane is the kaboom node. Here, start a transaction and update a row:

```
start transaction;
update test_conflict set value_1 = 'update from kaboom' where id = 1;
```

Next, move to the top-right pane using **Control-b →** or **Control-b q 1**. This pane is the kaftan node. Here, also start a transaction, and update the same row with different data:


```
start transaction;
update test_conflict set value_1 = 'update from kaftan' where id = 1;
```

You now have two transactions open on different servers, with an update operation already performed successfully. You need to commit both transactions at this point:

- Use **Control-b ←** or **Control-b q 0**, and then enter `commit;`.
- Use **Control-b →** or **Control-b q 1**, and then enter `commit;`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Again you'll see both commits working. And, again, in the bottom-right pane, you can see the update conflict being detected.



An additional row in the conflict history shows an `update_origin_change` conflict occurred and that the resolution was `apply_remote`. This resolution means that the remote change was applied, updating the record. This conflict is called an UPDATE/UPDATE conflict and is explained in more detail in UPDATE/UPDATE conflicts.

> **Exiting tmux**
>
> You can quickly exit tmux and all the associated sessions. First terminate any running processes, as they will otherwise continue running after the session is killed. Press **Control-b** and then enter `:kill-session`. This approach is simpler than quitting each pane's session one at a time using **Control-D** or `exit`.

Other conflicts

You're now equipped to explore all the possible conflict scenarios and resolutions that can occur. For full details of how conflicts are managed, see Conflict management. While ideally you should avoid conflicts, it's important to know that, when they do happen, they're recorded and managed by Postgres Distributed's integrated and configurable conflict resolver.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

7.9 Next steps with PGD

Going further with your PGD cluster

Architecture

This quick start created a single region cluster of high-availability Postgres databases. This is the Always-on Single Location architecture, one of a range of available PGD architectures. Other architectures include Always-on Multi-Location, with clusters in multiple data centers working together, and variations of both with witness nodes enhancing resilience. See architectural options.

Postgres versions

This quick start deployed EDB Postgres Advanced Server to the database nodes. PGD can deploy three different kinds of Postgres distributions, EDB Postgres Advanced Server, EDB Postgres Extended Server, and open-source PostgreSQL. The selection of database affects PGD, offering different capabilities, depending on server.

- Open-source PostgreSQL doesn't support CAMO.
- EDB Postgres Extended Server supports CAMO but doesn't offer Oracle compatibility.
- EDB Postgres Advanced Server supports CAMO and offers optional Oracle compatibility.

Further reading

- Learn PGD's terminology, from asynchronous replication to write scalability.
- Find out how applications work with PGD and how common Postgres features like sequences are globally distributed.
- Discover how PGD supports rolling upgrades of your clusters.
- Take control of routing and use SQL to control the PGD proxies.
- Engage with the PGD CLI to manage and monitor your cluster.

Deprovisioning the cluster

When you're done testing the cluster, deprovision it.

```
tpaexec deprovision democluster
```

- With a Docker deployment, deprovisioning tears down the Docker containers, network, and other local configuration.
- With an AWS deployment, deprovisioning removes the EC2 instances, VPC configuration, and other associated resources. Note that it leaves the S3 bucket it created. You must manually remove it.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

8 Planning your PGD deployment

Planning your PGD deployment involves understanding the requirements of your application and the capabilities of PGD. This section provides an overview of the key considerations for planning your PGD deployment.

- Choosing your architecture: Understand the different architectures that PGD supports and choose the one that best fits your requirements.
- Choosing a Postgres distribution: Choose the Postgres distribution to deploy with PGD.
- Choosing your deployment method: Pick the deployment method that suits your needs.
- Other considerations: Consider other factors that may affect your deployment.
- Limitations: Know the limitations of PGD and their effect on your plans.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

8.1 Choosing your architecture

Always-on architectures reflect EDB's Trusted Postgres architectures. They encapsulate practices and help you to achieve the highest possible service availability in multiple configurations. These configurations range from single-location architectures to complex distributed systems that protect from hardware failures and data center failures. The architectures leverage EDB Postgres Distributed's multi-master capability and its ability to achieve 99.999% availability, even during maintenance operations.

You can use EDB Postgres Distributed for architectures beyond the examples described here. Use-case-specific variations have been successfully deployed in production. However, these variations must undergo rigorous architecture review first.

Always-on architectures can be deployed using EDB's standard deployment tool
Trusted Postgres Architect (TPA) or configured manually.

Standard EDB Always-on architectures

EDB has identified a set of standardized architectures to support single- or multi-location deployments with varying levels of redundancy, depending on your recovery point objective (RPO) and recovery time objective (RTO) requirements.

The Always-on architecture uses three database node groups as a basic building block. You can also use a five-node group for extra redundancy.

EDB Postgres Distributed consists of the following major building blocks:

- Bi-Directional Replication (BDR) — A Postgres extension that creates the multi-master mesh network
- PGD Proxy — A connection router that makes sure the application is connected to the right data nodes.

All Always-on architectures protect an increasing range of failure situations. For example, a single active location with two data nodes protects against local hardware failure but doesn't provide protection from location (data center or availability zone) failure. Extending that architecture with a backup at a different location ensures some protection in case of the catastrophic loss of a location. However, you still must restore the database from backup first, which might violate RTO requirements. Adding a second active location connected in a multi-master mesh network ensures that service remains available even if a location goes offline. Finally, adding a third location (this can be a witness-only location) allows global Raft functionality to work even if one location goes offline. The global Raft is primarily needed to run administrative commands. Also, some features like DDL or sequence allocation might not work without it, while DML replication can continue to work even without global Raft.

Each architecture can provide zero RPO, as data can be streamed synchronously to at least one local master, guaranteeing zero data loss in case of local hardware failure.

Increasing the availability guarantee always drives added cost for hardware and licenses, networking requirements, and operational complexity. It's important to carefully consider the availability and compliance requirements before choosing an architecture.

Architecture details


By default, application transactions don't require cluster-wide consensus for DML (selects, inserts, updates, and deletes), allowing for lower latency and better performance. However, for certain operations, such as generating new global sequences or performing distributed DDL, EDB Postgres Distributed requires an odd number of nodes to make decisions using a Raft-based consensus model. Thus, even the simpler architectures always have three nodes, even if not all of them are storing data.

Applications connect to the standard Always-on architectures by way of multi-host connection strings, where each PGD Proxy server is a distinct entry in the multi-host connection string. You must always have at least two proxy nodes in each location to ensure high availability. You can colocate the proxy with the database instance, in which case we recommend putting the proxy on every data node.

Other connection mechanisms have been successfully deployed in production. However, they aren't part of the standard Always-on architectures.

Always-on Single Location


Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.



- Additional replication between data nodes 1 and 3 isn't shown but occurs as part of the replication mesh
- Redundant hardware to quickly restore from local failures
    - 3 PGD nodes
        - Can be 3 data nodes (recommended)
        - Can be 2 data nodes and 1 witness that doesn't hold data (not depicted)
    - A PGD Proxy for each data node with affinity to the applications
        - Can be colocated with data node (recommended)
        - Can be located on a separate node
    - Configuration and infrastructure symmetry of data nodes is expected to ensure proper resources are available to handle application workload when rerouted
- Barman for backup and recovery (not depicted)
    - Offsite is optional but recommended
    - Can be shared by multiple PGD clusters
- Postgres Enterprise Manager (PEM) for monitoring (not depicted)
    - Can be shared by multiple PGD clusters

Always-on Multi-location

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.



- Application can be Active/Active in each location or can be Active/Passive or Active DR with only one location taking writes.
- Additional replication between data nodes 1 and 3 isn't shown but occurs as part of the replication mesh.
- Redundant hardware to quickly restore from local failures.
  - 6 PGD nodes total, 3 in each location
    - Can be 3 data nodes (recommended)
    - Can be 2 data nodes and 1 witness which does not hold data (not depicted)
  - A PGD Proxy for each data node with affinity to the applications
    - Can be colocated with data node (recommended)
    - Can be located on a separate node
  - Configuration and infrastructure symmetry of data nodes and locations is expected to ensure proper resources are available to handle application workload when rerouted
- Barman for backup and recovery (not depicted).
  - Can be shared by multiple PGD clusters
- Postgres Enterprise Manager (PEM) for monitoring (not depicted).
  - Can be shared by multiple PGD clusters
- An optional witness node must be placed in a third region to increase tolerance for location failure.
  - Otherwise, when a location fails, actions requiring global consensus are blocked, such as adding new nodes and distributed DDL.

Choosing your architecture

All architectures provide the following:

- Hardware failure protection
- Zero downtime upgrades
- Support for availability zones in public/private cloud

Use these criteria to help you to select the appropriate Always-on architecture.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

	Single-data location	Two data locations	Two data locations + witness	Three or more data locations
Locations needed	1	2	3	3
Fast restoration of local HA after data node failure	Yes - if 3 PGD data nodes No - if 2 PGD data nodes	Yes - if 3 PGD data nodes No - if 2 PGD data nodes	Yes - if 3 PGD data nodes No - if 2 PGD data nodes	Yes - if 3 PGD data nodes No - if 2 PGD data nodes
Data protection in case of location failure	No (unless offsite backup)	Yes	Yes	Yes
Global consensus in case of location failure	N/A	No	Yes	Yes
Data restore required after location failure	Yes	No	No	No
Immediate failover in case of location failure	No - requires data restore from backup	Yes - alternate Location	Yes - alternate Location	Yes - alternate Location
Cross-location network traffic	Only if backup is offsite	Full replication traffic	Full replication traffic	Full replication traffic
License cost	2 or 3 PGD data nodes	4 or 6 PGD data nodes	4 or 6 PGD data nodes	6+ PGD data nodes

Adding flexibility to the standard architectures

To provide the data resiliency needed and proximity to applications and to the users maintaining the data, you can deploy the single-location architecture in as many locations as you want. While EDB Postgres Distributed has a variety of conflict-handling approaches available, do take care to minimize the number of expected collisions if allowing write activity from geographically disparate locations.

You can also expand the standard architectures with two additional types of nodes:

- *Subscriber-only nodes*, which you can use to achieve additional read scalability and to have data closer to users when the majority of an application's workload is read intensive with infrequent writes. You can also leverage them to publish a subset of the data for reporting, archiving, and analytic needs.

- *Logical standbys*, which receive replicated data from another node in the PGD cluster but don't participate in the replication mesh or consensus. They contain all the same data as the other PGD data nodes and can quickly be promoted to a master if one of the data nodes fails to return the cluster to full capacity/consensus. You can use them in environments where network traffic between data centers is a concern. Otherwise, three PGD data nodes per location is always preferred.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

8.2 Choosing a Postgres distribution

EDB Postgres Distributed can be deployed with three different Postgres distributions: PostgreSQL, EDB Postgres Extended Server, or EDB Postgres Advanced Server. The availability of particular EDB Postgres Distributed features depends on the Postgres distribution being used. Therefore, it's essential to adopt the Postgres distribution best suited to your business needs. For example, if having the Commit At Most Once (CAMO) feature is mission critical to your use case, don't adopt open source PostgreSQL, which doesn't have the core capabilities required to handle CAMO.

The following table lists features of EDB Postgres Distributed that are dependent on the Postgres distribution and version.

Feature	PostgreSQL	EDB Postgres Extended	EDB Postgres Advanced
Rolling application and database upgrades	Y	Y	Y
Row-level last-update wins conflict resolution	Y	Y	Y
DDL replication	Y	Y	Y
Granular DDL Locking	Y	Y	Y
Streaming of large transactions	v14+	v13+	v14+
Distributed sequences	Y	Y	Y
Subscriber-only nodes	Y	Y	Y
Monitoring	Y	Y	Y
OpenTelemetry support	Y	Y	Y
Parallel apply	Y	Y	Y
Conflict-free replicated data types (CRDTs)	Y	Y	Y
Column-level conflict resolution	Y	Y	Y
Transform triggers	Y	Y	Y
Conflict triggers	Y	Y	Y
Asynchronous replication	Y	Y	Y
Legacy synchronous replication	Y	Y	Y
Group Commit	N	Y	14+
Commit At Most Once (CAMO)	N	Y	14+
Eager Conflict Resolution	N	Y	14+
Lag Control	N	Y	14+
Decoding Worker	N	13+	14+
Lag tracker	N	Y	14+
Missing partition conflict	N	Y	14+
No need for UPDATE Trigger on tables with TOAST	N	Y	14+
Automatically hold back FREEZE	N	Y	14+
Transparent Data Encryption	N	15+	15+

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

8.3 Choosing your deployment method

You can deploy and install EDB Postgres Distributed products using the following methods:

- Trusted Postgres Architect (TPA) is an orchestration tool that uses Ansible to build Postgres clusters using a set of reference architectures that document how to set up and operate Postgres in various scenarios. TPA represents the best practices followed by EDB, and its recommendations apply to quick testbed setups just as they do to production environments. TPA's flexibility allows deployments to virtual machines, AWS cloud instances, or Linux host hardware. See Deploying with TPA for more information.

- EDB Postgres AI Cloud Service is a fully managed database-as-a-service with built-in Oracle compatibility that runs in your cloud account or Cloud Service's cloud account where it's operated by EDB's Postgres experts. EDB Postgres AI Cloud Service makes it easy to set up, manage, and scale your databases. The addition of distributed high-availability support powered by EDB Postgres Distributed (PGD) enables single- and multi-region Always-on clusters. See Distributed high availability in the Cloud Service documentation for more information.

- EDB Postgres Distributed for Kubernetes is a Kubernetes operator designed, developed, and supported by EDB. It covers the full lifecycle of highly available Postgres database clusters with a multi-master architecture, using PGD replication. It's based on the open source CloudNativePG operator and provides additional value, such as compatibility with Oracle using EDB Postgres Advanced Server, Transparent Data Encryption (TDE) using EDB Postgres Extended or Advanced Server, and additional supported platforms including IBM Power and OpenShift.

	TPA	EDB Postgres AI Cloud Service	Kubernetes
Single region	✓	✓	✓
Active-Active support	2+ regions	2 regions	2 regions
Write/Read routing	Local or global	Local	Local
Automated failover	AZ or Region	AZ	AZ
Major version upgrades	✓	-	-
Subscriber-only nodes (read replicas)	✓	-	-
Logical standby nodes	✓	-	-
PgBouncer	✓	-	-
Selective data replication	✓	✓	✓
Maintenance windows per region	✓	✓	✓
Target availability	99.999% SLO	99.99 SLA (single) 99.995% SLA (multi)	99.999% SLO

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

8.4 Other considerations

Review these other considerations when planning your deployment.

Data consistency

Read about Conflicts to understand the implications of the asynchronous operation mode in terms of data consistency.

Deployment

PGD is intended to be deployed in one of a small number of known-good configurations, using either Trusted Postgres Architect or a configuration management approach and deployment architecture approved by Technical Support.

Log messages and documentation are currently available only in English.

Sizing considerations

For production deployments, EDB recommends a minimum of 4 cores for each Postgres data node. Witness nodes don't participate in the data replication operation and don't have to meet this requirement. One core is enough without subgroup Raft. Two cores are enough when using subgroup Raft. Always size logical standbys exactly like the data nodes to avoid performance degradations in case of a node promotion. In production deployments, PGD Proxy nodes require a minimum of 1 core and must increase incrementally with an increase in the number of database cores in approximately a 1:10 ratio. We recommend detailed benchmarking of your specific performance requirements to determine appropriate sizing based on your workload. The EDB Professional Services team is available to assist if needed.

For development purposes, don't assign Postgres data nodes fewer than two cores. The sizing of Barman nodes depends on the database size and the data change rate.

You can deploy Postgres data nodes, Barman nodes, and PGD Proxy nodes on virtual machines or in a bare metal deployment mode. However, don't deploy multiple data nodes on VMs that are on the same physical hardware, as that reduces resiliency. Also don't deploy multiple PGD Proxy nodes on VMs on the same physical hardware, as that, too, reduces resiliency.

Single PGD Proxy nodes can be colocated with single PGD data nodes.

Clocks and timezones

EDB Postgres Distributed is designed to operate with nodes in multiple timezones, allowing a truly worldwide database cluster. Individual servers don't need to be configured with matching timezones, though we do recommend using `log_timezone = UTC` to ensure the human readable server log is more accessible and comparable.

Synchronize server clocks using NTP or other solutions.

Clock synchronization isn't critical to performance, as it is with some other solutions. Clock skew can affect origin conflict detection, though EDB Postgres Distributed provides controls to report and manage any skew that exists. EDB Postgres Distributed also provides row-version conflict detection, as described in Conflict detection.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

8.5 Limitations

Take these EDB Postgres Distributed (PGD) design limitations into account when planning your deployment.

Nodes

- PGD can run hundreds of nodes, assuming adequate hardware and network. However, for mesh-based deployments, we generally don't recommend running more than 48 nodes in one cluster. If you need extra read scalability beyond the 48-node limit, you can add subscriber-only nodes without adding connections to the mesh network.
- The minimum recommended number of nodes in a group is three to provide fault tolerance for PGD's consensus mechanism. With just two nodes, consensus would fail if one of the nodes were unresponsive. Consensus is required for some PGD operations, such as distributed sequence generation. For more information about the consensus mechanism used by EDB Postgres Distributed, see Architectural details.

Multiple databases on single instances

Support for using PGD for multiple databases on the same Postgres instance is **deprecated** beginning with PGD 5 and will no longer be supported with PGD 6. As we extend the capabilities of the product, the added complexity introduced operationally and functionally is no longer viable in a multi-database design.

It's best practice and we recommend that you configure only one database per PGD instance.

The deployment automation with TPA and the tooling such as the CLI and PGD Proxy already codify that recommendation.

While it's still possible to host up to 10 databases in a single instance, doing so incurs many immediate risks and current limitations:

- If PGD configuration changes are needed, you must execute administrative commands for each database. Doing so increases the risk for potential inconsistencies and errors.
- You must monitor each database separately, adding overhead.
- TPAexec assumes one database. Additional coding is needed by customers or by the EDB Professional Services team in a post-deploy hook to set up replication for more databases.
- PGD Proxy works at the Postgres instance level, not at the database level, meaning the leader node is the same for all databases.
- Each additional database increases the resource requirements on the server. Each one needs its own set of worker processes maintaining replication, for example, logical workers, WAL senders, and WAL receivers. Each one also needs its own set of connections to other instances in the replication cluster. These needs might severely impact performance of all databases.
- Synchronous replication methods, for example, CAMO and Group Commit, won't work as expected. Since the Postgres WAL is shared between the databases, a synchronous commit confirmation can come from any database, not necessarily in the right order of commits.
- CLI and OTEL integration (new with v5) assumes one database.

Durability options (Group Commit/CAMO)

There are various limits on how the PGD durability options work. These limitations are a product of the interactions between Group Commit and CAMO, and how they interact with PGD features such as the WAL decoder and transaction streaming.

Also, there are limitations on interoperability with legacy synchronous replication, interoperability with explicit two-phase commit, and unsupported combinations within commit scope rules.

See Durability limitations for a full and current listing.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Mixed PGD versions

While PGD was developed to enable rolling upgrades of PGD by allowing mixed versions of PGD to operate during the upgrade process, we expect users to run mixed versions only during upgrades and for users to complete their upgrades as quickly as possible. We also recommend that you test any rolling upgrade process in a non-production environment before attempting it in production.

When a node is upgraded, it returns to the cluster and communicates with the other nodes in the cluster using the lowest version of the inter-node protocol that is supported by all the other nodes in the cluster. This means that the upgraded node will be able to communicate with all other nodes in the cluster, but it will not be able to take advantage of any new features or improvements that were introduced in the newer version of PGD.

That will stay the case until all nodes in the cluster have been upgraded to the same newer version.
The longer you run mixed versions, the longer you will be without the benefits of the new version, and the longer you will be exposed to any potential interoperability issues that might arise from running mixed versions. Mixed version clusters are not supported for extended periods of time.

Therefore, once an PGD cluster upgrade has begun, you should complete the whole cluster upgrade as quickly as possible.

We don't support running mixed versions of PGD except during an upgrade, and we don't support clusters running mixed versions even while being upgraded, for extended periods.

For more information on rolling upgrades and mixed versions, see Rolling upgrade considerations.

Other limitations

This noncomprehensive list includes other limitations that are expected and are by design. We don't expect to resolve them in the future. Consider these limitations when planning your deployment:

- A `galloc` sequence might skip some chunks if you create the sequence in a rolled back transaction and then create it again with the same name. Skipping chunks can also occur if you create and drop the sequence when DDL replication isn't active and then you create it again when DDL replication is active. The impact of the problem is mild because the sequence guarantees aren't violated. The sequence skips only some initial chunks. Also, as a workaround, you can specify the starting value for the sequence as an argument to the `bdr.alter_sequence_set_kind()` function.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9 Deploying and configuring EDB Postgres Distributed

This section covers how to deploy EDB Postgres Distributed and how to configure it.

There are four main ways to deploy PGD:

- Manual deployment and administration describes how to manually deploy and configure EDB Postgres Distributed on a set of servers.
- Trusted Postgres Architect (TPA) describes how to use TPA to deploy and configure EDB Postgres Distributed to a Docker environment, Linux hosts, or AWS.
- EDB Postgres Distributed for Kubernetes describes how to deploy and configure EDB Postgres Distributed to a Kubernetes environment.
- EDB Postgres AI Cloud Service describes how to deploy and configure EDB Postgres Distributed on the EDB Postgres AI Cloud Service.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1 Manual deployment and configuration of PGD

This section covers how to manually deploy and configure EDB Postgres Distributed.

- Deploying manually works through the steps needed to:
  - Provision hosts
  - Install Postgres
  - Configure repositories
  - Install the PGD software
  - Create a cluster
  - Check a cluster
  - Configure PGD proxies
  - Install and use PGD CLI

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1 Deploying PGD manually

EDB offers automated PGD deployment using Trusted Postgres Architect (TPA) because it's generally more reliable than manual processes. SeeDeploying with TPA for full details about how to install TPA and use its automated best-practice-driven PGD deployment options. Or refer to any of the Quick start walkthroughs, which use TPA to get you up and running quickly.

To complement automated deployment, and to enable alternative installation and deployment processes, this section looks at the basic operations needed to manually configure a three-node PGD cluster (with a local subgroup), PGD Proxy, and PGD CLI.

Each step is outlined and followed by a worked example with further detail. This isn't a quick start guide but an exploration of PGD installation. It configures a basic deployment that will be used for further examples of PGD administration tasks.

The examples deploy a 3-node cluster of EDB Postgres Advanced Server 16 on Red Hat Enterprise Linux 9. These instructions also apply to RHEL derivatives like Alma Linux, Rocky Linux, or Oracle Linux.

At the highest level, manually deploying PGD involves the following steps. (For completeness, the steps also include instructions for installing PostgreSQL. If you're familiar with that, then skip to step 3.)

1: Provisioning and configuring hosts to run the cluster on

2: Installing your selected Postgres version on each of the hosts

3: Configuring repositories to install PGD to add PGD capabilities to each host

4: Initializing Postgres and installing PGD software on each host

5: Connecting the cluster by connecting to each node and telling it to join the cluster

6: Checking the cluster by running SQL commands and confirming replication has happened

7: Configuring proxies by creating a proxy config file

8: Using PGD CLI, including how to install PGD CLI and how to use it to inspect and manage your cluster

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.1 Step 1 - Provisioning hosts

Provisioning hosts

The first step in the process of deploying PGD is to provision and configure hosts.

You can deploy to virtual machine instances in the cloud with Linux installed, on-premises virtual machines with Linux installed, or on-premises physical hardware, also with Linux installed.

Whichever supported Linux operating system and whichever deployment platform you select, the result of provisioning a machine must be a Linux system that you can access using SSH with a user that has superuser, administrator, or sudo privileges.

Each machine provisioned must be able to make connections to any other machine you're provisioning for your cluster.

On cloud deployments, you can do this over the public network or over a VPC.

On-premises deployments must be able to connect over the local network.

> **Cloud provisioning guides**
>
> If you're new to cloud provisioning, these guides may provide assistance:
>
> | Vendor | Platform | Guide |
> |---|---|---|
> | Amazon | AWS | Tutorial: Get started with Amazon EC2 Linux instances |
> | Microsoft | Azure | Quickstart: Create a Linux virtual machine in the Azure portal |
> | Google | GCP | Create a Linux VM instance in Compute Engine |

Configuring hosts

Create an admin user

We recommend that you configure an admin user for each provisioned instance. The admin user must have superuser or sudo (to superuser) privileges. We also recommend that the admin user be configured for passwordless SSH access using certificates.

Ensure networking connectivity

With the admin user created, ensure that each machine can communicate with the other machines you're provisioning.

In particular, the PostgreSQL TCP/IP port (5444 for EDB Postgres Advanced Server, 5432 for EDB Postgres Extended and community PostgreSQL) must be open to all machines in the cluster. If you plan to deploy PGD Proxy, its port must be open to any applications that will connect to the cluster. Port 6432 is typically used for PGD Proxy.

Worked example

For this example, three hosts with Red Hat Enterprise Linux 9 were provisioned:

- host-one
- host-two
- host-three

Each is configured with an admin user named admin.

These hosts were configured in the cloud. As such, each host has both a public and private IP address.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Public IP	Private IP
host-one	172.24.117.204	192.168.254.166
host-two	172.24.113.247	192.168.254.247
host-three	172.24.117.23	192.168.254.135

For the example cluster, `/etc/hosts` was also edited to use those private IP addresses:

```
192.168.254.166 host-one
192.168.254.247 host-two
192.168.254.135 host-three
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.2 Step 2 - Installing Postgres

Installing Postgres

You need to install Postgres on all the hosts.

An EDB account is required to use the EDB Repos 2.0 page where you can get installation instructions. Select your platform and Postgres edition. You're presented with 2 steps of instructions. The first step covers how to configure the required package repository. The second step covers how to install the packages from that repository.

Run both steps.

Worked example

This example installs EDB Postgres Advanced Server 16 on Red Hat Enterprise Linux 9 (RHEL 9).

EDB account

You need an EDB account to install both Postgres and PGD.

Use your EDB account to sign in to the EDB Repos 2.0 page where you can select your platform. Then scroll down the list to select the Postgres version you want to install:

- EDB Postgres Advanced Server
- EDB Postgres Extended
- PostgreSQL

When you select the version of the Postgres server you want, two steps are displayed.

1: Configuring repositories

For step 1, you can choose to use the automated script or step through the manual install instructions that are displayed. Your EDB repository token is inserted into these scripts by the EDB Repos 2.0 site. In the examples, it's shown as `XXXXXXXXXXXXXXXX`.

On each provisioned host, you either run the automatic repository installation script or use the manual installation steps. The automatic script looks like this:

```
curl -1sLf 'https://downloads.enterprisedb.com/XXXXXXXXXXXXXXXX/enterprise/setup.rpm.sh' | sudo -E bash
```

The manual installation steps look like this:

```
dnf install yum-utils
rpm --import 'https://downloads.enterprisedb.com/XXXXXXXXXXXXXXXX/enterprise/gpg.E71EB0829F1EF813.key'
curl -1sLf 'https://downloads.enterprisedb.com/XXXXXXXXXXXXXXXX/enterprise/config.rpm.txt?distro=el&codename=9' >
/tmp/enterprise.repo
dnf config-manager --add-repo '/tmp/enterprise.repo'
dnf -q makecache -y --disablerepo='*' --enablerepo='enterprisedb-enterprise'
```

2: Install Postgres

For step 2, run the command to install the packages:

```
sudo dnf -y install edb-as16-server
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.3 Step 3 - Configuring PGD repositories

Configuring PGD repositories

To install and run PGD requires that you configure repositories so that the system can download and install the appropriate packages.

Perform the following operations on each host. For the purposes of this exercise, each host is a standard data node, but the procedure would be the same for othernode types, such as witness or subscriber-only nodes.

- Use your EDB account.
    - Obtain your EDB repository token: Get your token.
- Set environment variables.
    - Set the `EDB_SUBSCRIPTION_TOKEN` environment variable to the repository token:

      ```
      export EDB_SUBSCRIPTION_TOKEN=<your-repo-token>
      ```
- Configure the repository.
    - Run the automated installer to install the repositories:

      > **Red Hat**
      >
      > ```
      > curl -1sLf
      > "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.rpm.sh" | sudo
      > -E bash
      > ```

      > **Ubuntu/Debian**
      >
      > ```
      > curl -1sLf
      > "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.deb.sh" | sudo
      > -E bash
      > ```

Worked example

Use your EDB account

To install both TPA and PGD, you will need an EDB Repos 2.0 token to gain access to the EDB private software repositories. For instructions on obtaining this token, see: Get your token.

Set environment variables

Set the `EDB_SUBSCRIPTION_TOKEN` environment variable to the value of your EDB repo token, obtained in the EDB account step.

```
export EDB_SUBSCRIPTION_TOKEN=<your-repo-token>
```

You can add this to your `.bashrc` script or similar shell profile to ensure it's always set.

> **Note**
>
> Your preferred platform may support storing this variable as a secret, which can appear as an environment variable. If this is the case, add it to your platform's secret manager, and don't add the setting to `.bashrc`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Configure the repository

All the software you need is available from the EDB Postgres Distributed package repository. You have the option to download and run a script to configure the EDB Postgres Distributed repository. You can also download, inspect, and then run that same script.

The following instructions also include the essential steps that the scripts take for any user wanting to manually run the installation process or to automate it.

RHEL/Other RHEL-based

You can autoinstall with automated OS detection:

```
curl -1sLf "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.rpm.sh" | sudo -E
bash
```

If you want to inspect the script that's generated for you, run:

```
curl -1sLfO "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.rpm.sh"
```

Then inspect the resulting `setup.rpm.sh` file. When you're ready to proceed, run:

```
sudo -E bash setup.rpm.sh
```

If you want to perform all steps manually or use your own preferred deployment mechanism, you can use the following example as a guide.

You will need to pass details of your Linux distribution and version. You may need to change the codename to match the version of RHEL you're using. This example sets it for RHEL-compatible Linux version 9:

```
export DISTRO="el"
export CODENAME="9"
```

Now install the yum-utils package:

```
sudo dnf install -y yum-utils
```

The next step imports a GPG key for the repositories:

```
sudo rpm --import
"https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/gpg.B09F406230DA0084.key"
```

Now you can import the repository details, add them to the local configuration, and enable the repository.

```
curl -1sLf "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/config.rpm.txt?
distro=$DISTRO&codename=$CODENAME" > /tmp/enterprise.repo
sudo dnf config-manager --add-repo '/tmp/enterprise.repo'
sudo dnf -q makecache -y --disablerepo='*' --enablerepo='enterprisedb-postgres_distributed'
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.4 Step 4 - Installing the PGD software

Installing the PGD software

With the repositories configured, you can now install the Postgres Distributed software. You must perform these steps on each host before proceeding to the next step.

- **Install the packages.**
  - Install the PGD packages, which include a server-specific BDR package and generic PGD Proxy and CLI packages. (`edb-bdr5-<postgresversion>` , `edb-pgd5-proxy` , and `edb-pgd5-cli`)
- **Ensure the Postgres database server has been initialized and started.**
  - Use `systemctl status` to check that the service is running.
  - If the service isn't running, initialize the database and start the service.
- **Configure the BDR extension.**
  - Add the BDR extension (`$libdir/bdr`) at the start of the `shared_preload_libraries` setting in `postgresql.conf` .
  - Set the `wal_level` GUC variable to `logical` in `postgresql.conf` .
  - Turn on commit timestamp tracking by setting `track_commit_timestamp` to `'on'` in `postgresql.conf` .
  - Increase the maximum worker processes to 16 or higher by setting `max_worker_processes` to `'16'` in `postgresql.conf` .

    > **The `max_worker_processes` value**
    >
    > The `max_worker_processes` value is derived from the topology of the cluster, the number of peers, number of databases, and other factors. To calculate the needed value, see Postgres configuration/settings. The value of 16 was calculated for the size of cluster being deployed in this example. It must be increased for larger clusters.

  - Set a password on the EnterprisedDB/Postgres user.
  - Add rules to `pg_hba.conf` to allow nodes to connect to each other.
    - Ensure that these lines are present in `pg_hba.conf` :

```
host all all all md5
host replication all all md5
```

  - Add a `.pgpass` file to allow nodes to authenticate each other.
    - Configure a user with sufficient privileges to log in to the other nodes.
    - See The Password File in the Postgres documentation for more on the `.pgpass` file.
- **Restart the server.**
  - Verify the restarted server is running with the modified settings and the BDR extension is available.
- **Create the replicated database.**
  - Log in to the server's default database (`edb` for EDB Postgres Advanced Server, `postgres` for PGE and community Postgres).
  - Use `CREATE DATABASE bdrdb` to create the default PGD replicated database.
  - Log out and then log back in to `bdrdb` .
  - Use `CREATE EXTENSION bdr` to enable the BDR extension and PGD to run on that database.

The worked example that follows shows the steps for EDB Postgres Advanced Server in detail.

If you're installing PGD with EDB Postgres Extended Server or community Postgres, the steps are similar, but details such as package names and paths are different. These differences are summarized in Installing PGD for EDB Postgres Extended Server and Installing PGD for Postgresql.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Worked example

Install the packages

The first step is to install the packages. Each Postgres package has an `edb-bdr5-<postgresversion>` package to go with it. For example, if you're installing EDB Postgres Advanced Server (epas) version 16, you'd install `edb-bdr5-epas16`.

There are two other packages to also install:

- `edb-pgd5-proxy` for PGD Proxy
- `edb-pgd5-cli` for the PGD command line tool

To install all of these packages on a RHEL or RHEL compatible Linux, run:

```
sudo dnf -y install edb-bdr5-epas16 edb-pgd5-proxy edb-pgd5-cli
```

Ensure the database is initialized and started

If the server wasn't initialized and started by the database's package initialization (or you're repeating the process), you need to initialize and start the server.

To see if the server is running, you can check the service. The service name for EDB Advanced Server is `edb-as-16`, so run:

```
sudo systemctl status edb-as-16
```

If the server isn't running, the response is:

```
○ edb-as-16.service - EDB Postgres Advanced Server 16
     Loaded: loaded (/usr/lib/systemd/system/edb-as-16.service; disabled; preset: disabled)
     Active: inactive (dead)
```

`Active: inactive (dead)` tells you that you need to initialize and start the server.

You need to know the path to the setup script for your particular Postgres flavor.

For EDB Postgres Advanced Server, you can find this script in `/usr/edb/as16/bin` as `edb-as-16-setup`. Run this command with the `initdb` parameter and pass an option to set the database to use UTF-8:

```
sudo PGSETUP_INITDB_OPTIONS="-E UTF-8" /usr/edb/as16/bin/edb-as-16-setup initdb
```

Once the database is initialized, start it so that you can continue configuring the BDR extension:

```
sudo systemctl start edb-as-16
```

Configure the BDR extension

Installing EDB Postgres Advanced Server creates a system user enterprisedb with admin capabilities when connected to the database. You'll use this user to configure the BDR extension.

Preload the BDR library

You need to preload the BDR library with other libraries. EDB Postgres Advanced Server has a number of libraries already preloaded, so you have to prefix the existing list with the BDR library.

```
echo -e "shared_preload_libraries = '\$libdir/bdr,\$libdir/dbms_pipe,\$libdir/edb_gen,\$libdir/dbms_aq'" | sudo -u
enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf >/dev/null
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Tip**
>
> This command format (`echo ... | sudo ... tee -a ...`) appends the echoed string to the end of the `postgresql.conf` file, which is owned by another user.

Set the `wal_level`

The BDR extension needs to set the server to perform logical replication. Do this by setting `wal_level` to `logical` :

```
echo -e "wal_level = 'logical'" | sudo -u enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf >/dev/null
```

Enable commit timestamp tracking

The BDR extension also needs the commit timestamp tracking enabled:

```
echo -e "track_commit_timestamp = 'on'" | sudo -u enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf
>/dev/null
```

Increase `max_worker_processes`

To communicate between multiple nodes, Postgres Distributed nodes run more worker processes than usual. The default limit (8) is too low even for a small cluster.

The `max_worker_processes` value is derived from the topology of the cluster, the number of peers, number of databases, and other factors. To calculate the needed value, see Postgres configuration/settings.

This example, with a 3-node cluster, uses the value of 16.

Increase the maximum number of worker processes to 16:

```
echo -e "max_worker_processes = '16'" | sudo -u enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf >/dev/null
```

This value must be increased for larger clusters.

Add a password to the Postgres enterprisedb user

To allow connections between nodes, a password needs to be set on the Postgres enterprisedb user. This example uses the password `secret` . Select a different password for your deployments. You will need this password to Enable authentication between nodes.

```
sudo -u enterprisedb psql edb -c "ALTER USER enterprisedb WITH PASSWORD 'secret'"
```

Enable inter-node authentication in pg_hba.conf

Out of the box, Postgres allows local authentication and connections with the database but not external network connections. To enable this, edit `pg_hba.conf` and add appropriate rules, including rules for the replication users. To simplify the process, use this command:

```
echo -e "host all all all md5\nhost replication all all md5" | sudo tee -a /var/lib/edb/as16/data/pg_hba.conf
```

The command appends the following to `pg_hba.conf` :

```
host all all all md5
host replication all all md5
```

These commands enable the nodes to replicate.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Enable authentication between nodes

As part of the process of connecting nodes for replication, PGD logs into other nodes. It performs that login as the user that Postgres is running under. For EDB Postgres Advanced server, this is the enterprisedb user. That user needs credentials to log into the other nodes. Supply these credentials using the `.pgpass` file, which needs to reside in the user's home directory. The home directory for `enterprisedb` is `/var/lib/edb`.

Run this command to create the file:

```
echo -e "*:*:*:enterprisedb:secret" | sudo -u enterprisedb tee /var/lib/edb/.pgpass; sudo chmod 0600
/var/lib/edb/.pgpass
```

You can read more about the `.pgpass` file in The Password File in the PostgreSQL documentation.

Restart the server

After all these configuration changes, we recommend that you restart the server with:

```
sudo systemctl restart edb-as-16
```

Check the extension has been installed

At this point, it's worth checking whether the extension is actually available and the configuration was correctly loaded. You can query the `pg_available_extensions` table for the BDR extension like this:

```
sudo -u enterprisedb psql edb -c "select * from pg_available_extensions where name like 'bdr'"
```

This command returns an entry for the extension and its version:

```
 name | default_version | installed_version |                  comment
------+-----------------+-------------------+-------------------------------------------
 bdr  | 5.3.0           |                   | Bi-Directional Replication for PostgreSQL
```

You can also confirm the other server settings using this command:

```
sudo -u enterprisedb psql edb -c "show all" | grep -e wal_level -e track_commit_timestamp -e max_worker_processes
```

Create the replicated database

The server is now prepared for PGD. You need to next create a database named `bdrdb` and install the BDR extension when logged into it:

```
sudo -u enterprisedb psql edb -c "CREATE DATABASE bdrdb"
sudo -u enterprisedb psql bdrdb -c "CREATE EXTENSION bdr"
```

Finally, test the connection by logging in to the server.

```
sudo -u enterprisedb psql bdrdb
```

You're connected to the server. Execute the command "\dx" to list extensions installed:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
bdrdb=# \dx
                                List of installed extensions
       Name       | Version |   Schema   |                   Description
------------------+---------+------------+--------------------------------------------------
 bdr              | 5.3.0   | pg_catalog | Bi-Directional Replication for PostgreSQL
 edb_dblink_libpq | 1.0     | pg_catalog | EnterpriseDB Foreign Data Wrapper for PostgreSQL
 edb_dblink_oci   | 1.0     | pg_catalog | EnterpriseDB Foreign Data Wrapper for Oracle
 edbspl           | 1.0     | pg_catalog | EDB-SPL procedural language
 plpgsql          | 1.0     | pg_catalog | PL/pgSQL procedural language
(5 rows)
```

Notice that the BDR extension is listed in the table, showing that it's installed.

Summaries

Installing PGD for EDB Postgres Advanced Server

For your convenience, here's a summary of the commands used in this example.

```
sudo dnf -y install edb-bdr5-epas16 edb-pgd5-proxy edb-pgd5-cli
sudo PGSETUP_INITDB_OPTIONS="-E UTF-8" /usr/edb/as16/bin/edb-as-16-setup initdb
sudo systemctl start edb-as-16
echo -e "shared_preload_libraries = '\$libdir/bdr,\$libdir/dbms_pipe,\$libdir/edb_gen,\$libdir/dbms_aq'" | sudo -u
enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf >/dev/null
echo -e "wal_level = 'logical'" | sudo -u enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf >/dev/null
echo -e "track_commit_timestamp = 'on'" | sudo -u enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf
>/dev/null
echo -e "max_worker_processes = '16'" | sudo -u enterprisedb tee -a /var/lib/edb/as16/data/postgresql.conf >/dev/null
sudo -u enterprisedb psql edb -c "ALTER USER enterprisedb WITH PASSWORD 'secret'"
echo -e "host all all all md5\nhost replication all all md5" | sudo tee -a /var/lib/edb/as16/data/pg_hba.conf
>/dev/null
echo -e "*:*:*:enterprisedb:secret" | sudo -u enterprisedb tee /var/lib/edb/.pgpass >/dev/null; sudo chmod 0600
/var/lib/edb/.pgpass
sudo systemctl restart edb-as-16
sudo -u enterprisedb psql edb -c "CREATE DATABASE bdrdb"
sudo -u enterprisedb psql bdrdb -c "CREATE EXTENSION bdr"
sudo -u enterprisedb psql bdrdb
```

Installing PGD for EDB Postgres Extended Server

Installing PGD with EDB Postgres Extended Server has a number of differences from the EDB Postgres Advanced Server installation:

- The BDR package to install is named `edb-bdrV-pgextendedNN` (where V is the PGD version and NN is the PGE version number).
- Call a different setup utility: `/usr/edb/pgeNN/bin/edb-pge-NN-setup`.
- The service name is `edb-pge-NN`.
- The system user is postgres (not enterprisedb).
- The home directory for the postgres user is `/var/lib/pgqsl`.
- There are no preexisting libraries to add to `shared_preload_libraries`.

Summary: Installing PGD for EDB Postgres Extended Server 16

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
sudo dnf -y install edb-bdr5-pgextended16 edb-pgd5-proxy edb-pgd5-cli
sudo PGSETUP_INITDB_OPTIONS="-E UTF-8" /usr/edb/pge16/bin/edb-pge-16-setup ekend initdb
sudo systemctl start edb-pge-16
echo -e "shared_preload_libraries = '\$libdir/bdr'" | sudo -u postgres tee -a /var/lib/edb-
pge/16/data/postgresql.conf >/dev/null
echo -e "wal_level = 'logical'" | sudo -u postgres tee -a /var/lib/edb-pge/16/data/postgresql.conf >/dev/null
echo -e "track_commit_timestamp = 'on'" | sudo -u postgres tee -a /var/lib/edb-pge/16/data/postgresql.conf >/dev/null
echo -e "max_worker_processes = '16'" | sudo -u postgres tee -a /var/lib/edb-pge/16/data/postgresql.conf >/dev/null
sudo -u postgres psql postgres -c "ALTER USER postgres WITH PASSWORD 'secret'"
echo -e "host all all all md5\nhost replication all all md5" | sudo tee -a /var/lib/edb-pge/16/data/pg_hba.conf
>/dev/null
echo -e "*:*:*:postgres:secret" | sudo -u postgres tee /var/lib/pgsql/.pgpass >/dev/null; sudo chmod 0600
/var/lib/pgsql/.pgpass
sudo systemctl restart edb-pge-16
sudo -u postgres psql postgres -c "CREATE DATABASE bdrdb"
sudo -u postgres psql bdrdb -c "CREATE EXTENSION bdr"
sudo -u postgres psql bdrdb
```

Installing PGD for Postgresql

Installing PGD with PostgresSQL has a number of differences from the EDB Postgres Advanced Server installation:

- The BDR package to install is named `edb-bdrV-pgNN` (where V is the PGD version and NN is the PostgreSQL version number).
- Call a different setup utility: `/usr/pgsql-NN/bin/postgresql-NN-setup`.
- The service name is `postgresql-NN`.
- The system user is postgres (not enterprisedb).
- The home directory for the postgres user is `/var/lib/pgqsl`.
- There are no preexisting libraries to add to `shared_preload_libraries`.

Summary: Installing PGD for Postgresql 16

```
sudo dnf -y install edb-bdr5-pg16 edb-pgd5-proxy edb-pgd5-cli
sudo PGSETUP_INITDB_OPTIONS="-E UTF-8" /usr/pgsql-16/bin/postgresql-16-setup initdb
sudo systemctl start postgresql-16
echo -e "shared_preload_libraries = '\$libdir/bdr'" | sudo -u postgres tee -a /var/lib/pgsql/16/data/postgresql.conf
>/dev/null
echo -e "wal_level = 'logical'" | sudo -u postgres tee -a /var/lib/pgsql/16/data/postgresql.conf >/dev/null
echo -e "track_commit_timestamp = 'on'" | sudo -u postgres tee -a /var/lib/pgsql/16/data/postgresql.conf >/dev/null
echo -e "max_worker_processes = '16'" | sudo -u postgres tee -a /var/lib/pgsql/16/data/postgresql.conf >/dev/null
sudo -u postgres psql postgres -c "ALTER USER postgres WITH PASSWORD 'secret'"
echo -e "host all all all md5\nhost replication all all md5" | sudo tee -a /var/lib/pgsql/16/data/pg_hba.conf
>/dev/null
echo -e "*:*:*:postgres:secret" | sudo -u postgres tee /var/lib/pgsql/.pgpass; sudo chmod 0600 /var/lib/pgsql/.pgpass
sudo systemctl restart postgresql-16
sudo -u postgres psql postgres -c "CREATE DATABASE bdrdb"
sudo -u postgres psql bdrdb -c "CREATE EXTENSION bdr"
sudo -u postgres psql bdrdb
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.5 Step 5 - Creating the PGD cluster

Creating the PGD cluster

- **Create connection strings for each node**.
  For each node, create a connection string that will allow PGD to perform replication.

  The connection string is a key/value string that starts with a `host=` and the IP address of the host. (If you have resolvable named hosts, the name of the host is used instead of the IP address.)

  That's followed by the name of the database. In this case, use `dbname=bdrdb`, as a `bdrdb` database was created when installing the software.

  We recommend you also add the port number of the server to your connection string as `port=5444` for EDB Postgres Advanced Server and `port=5432` for EDB Postgres Extended and community PostgreSQL.

- **Prepare the first node.** To create the cluster, select and log in to the `bdrdb` database on any host's Postgres server.

- **Create the first node.**
  Run `bdr.create_node` and give the node a name and its connection string where *other* nodes can connect to it.

  - Create the top-level group. Create a top-level group for the cluster with `bdr.create_node_group`, giving it a single parameter: the name of the top-level group.
  - Create a subgroup. Create a subgroup as a child of the top-level group with `bdr.create_node_group`, giving it two parameters: the name of the subgroup and the name of the parent (and top-level) group. This process initializes the first node.

- **Add the second node.**

  - Create the second node. Log in to another initialized node's `bdrdb` database. Run `bdr.create_node` and give the node a different name and its connection string where *other* nodes can connect to it.
  - Join the second node to the cluster. Next, run `bdr.join_node_group`, passing two parameters: the connection string for the first node and the name of the subgroup you want the node to join.

- **Add the third node.**

  - Create the third node. Log in to another initialized node's `bdrdb` database. Run `bdr.create_node` and give the node a different name and its connection string where *other* nodes can connect to it.
  - Join the third node to the cluster. Next, run `bdr.join_node_group`, passing two parameters: the connection string for the first node and the name of the subgroup you want the node to join.

Worked example

So far, this example has:

- Created three hosts.
- Installed a Postgres server on each host.
- Installed Postgres Distributed on each host.
- Configured the Postgres server to work with PGD on each host.

To create the cluster, you tell host-one's Postgres instance that it's a PGD node—node-one—and create PGD groups on that node. Then you tell host-two and host-three's Postgres instances that they are PGD nodes—node-two and node-three—and that they must join a group on node-one.

Create connection strings for each node

Calculate the connection strings for each of the nodes in advance. Following are the connection strings for this 3-node example.

Name	Node name	Private IP	Connection string
host-one	node-one	192.168.254.166	host=host-one dbname=bdrdb port=5444

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Node name	Private IP	Connection string
host-two	node-two	192.168.254.247	host=host-two dbname=bdrdb port=5444
host-three	node-three	192.167.254.135	host=host-three dbname=bdrdb port=5444

Preparing the first node

Log in to host-one's Postgres server.

```
ssh admin@host-one
sudo -iu enterprisedb psql bdrdb
```

Create the first node

Call the `bdr.create_node` function to create a node, passing it the node name and a connection string that other nodes can use to connect to it.

```
select bdr.create_node('node-one','host=host-one dbname=bdrdb port=5444');
```

Create the top-level group

Call the `bdr.create_node_group` function to create a top-level group for your PGD cluster. Passing a single string parameter creates the top-level group with that name. This example creates a top-level group named `pgd`.

```
select bdr.create_node_group('pgd');
```

Create a subgroup

Using subgroups to organize your nodes is preferred, as it allows services like PGD Proxy, which you'll configure later, to coordinate their operations. In a larger PGD installation, multiple subgroups can exist. These subgroups provide organizational grouping that enables geographical mapping of clusters and localized resilience. For that reason, this example creates a subgroup for the first nodes to enable simpler expansion and the use of PGD Proxy.

Call the `bdr.create_node_group` function again to create a subgroup of the top-level group. The subgroup name is the first parameter, and the parent group is the second parameter. This example creates a subgroup `dc1` as a child of `pgd`.

```
select bdr.create_node_group('dc1','pgd');
```

Adding the second node

Log in to host-two's Postgres server

```
ssh admin@host-two
sudo -iu enterprisedb psql bdrdb
```

Create the second node

Call the `bdr.create_node` function to create this node, passing it the node name and a connection string that other nodes can use to connect to it.

```
select bdr.create_node('node-two','host=host-two dbname=bdrdb port=5444');
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Join the second node to the cluster

Using `bdr.join_node_group`, you can ask node-two to join node-one's `dc1` group. The function takes as a first parameter the connection string of a node already in the group and the group name as a second parameter.

```
select bdr.join_node_group('host=host-one dbname=bdrdb port=5444','dc1');
```

Add the third node

Log in to host-three's Postgres server.

```
ssh admin@host-three
sudo -iu enterprisedb psql bdrdb
```

Create the third node

Call the `bdr.create_node` function to create this node, passing it the node name and a connection string that other nodes can use to connect to it.

```
select bdr.create_node('node-three','host=host-three dbname=bdrdb port=5444');
```

Join the third node to the cluster

Using `bdr.join_node_group`, you can ask node-three to join node-one's `dc1` group. The function takes as a first parameter the connection string of a node already in the group and the group name as a second parameter.

```
select bdr.join_node_group('host=host-one dbname=bdrdb port=5444','dc1');
```

A PGD cluster is now created.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.6 Step 6 - Checking the cluster

Checking the cluster

With the cluster up and running, it's worthwhile to run some basic checks to see how effectively it's replicating.

The following example shows one quick way to do this, but you must ensure that any testing you perform is appropriate for your use case.

- **Preparation**
  - Ensure the cluster is ready:
    - Log in to the database on host-one/node-one.
    - Run `select bdr.wait_slot_confirm_lsn(NULL, NULL);`.
    - When the query returns, the cluster is ready.
- **Create data** The simplest way to test that the cluster is replicating is to log in to one node, create a table, and populate it.
  - On node-one, create a table:

    ```
    CREATE TABLE quicktest ( id SERIAL PRIMARY KEY, value INT );
    ```

  - On node-one, populate the table:

    ```
    INSERT INTO quicktest (value) SELECT random()*10000 FROM
    generate_series(1,10000);
    ```

  - On node-one, monitor performance:

    ```
    select * from bdr.node_replication_rates;
    ```

  - On node-one, get a sum of the value column (for checking):

    ```
    select COUNT(*),SUM(value) from quicktest;
    ```

- **Check data**
  - Log in to node-two. Log in to the database on host-two/node-two.
  - On node-two, get a sum of the value column (for checking):

    ```
    select COUNT(*),SUM(value) from quicktest;
    ```

  - Compare with the result from node-one.
  - Log in to node-three. Log in to the database on host-three/node-three.
  - On node-three, get a sum of the value column (for checking):

    ```
    select COUNT(*),SUM(value) from quicktest;
    ```

  - Compare with the result from node-one and node-two.

Worked example

Preparation

Log in to host-one's Postgres server.

```
ssh admin@host-one
sudo -iu enterprisedb psql bdrdb
```

This is your connection to PGD's node-one.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Ensure the cluster is ready

To ensure that the cluster is ready to go, run:

```
select bdr.wait_slot_confirm_lsn(NULL, NULL)
```

This query blocks while the cluster is busy initializing and returns when the cluster is ready.

In another window, log in to host-two's Postgres server:

```
ssh admin@host-two
sudo -iu enterprisedb psql bdrdb
```

Create data

On node-one, create a table

Run:

```
CREATE TABLE quicktest ( id SERIAL PRIMARY KEY, value INT );
```

On node-one, populate the table

```
INSERT INTO quicktest (value) SELECT random()*10000 FROM generate_series(1,10000);
```

This command generates a table of 10000 rows of random values.

On node-one, monitor performance

As soon as possible, run:

```
select * from bdr.node_replication_rates;
```

The command shows statistics about how quickly that data was replicated to the other two nodes:

```
bdrdb=# select * from bdr.node_replication_rates;
 peer_node_id | target_name | sent_lsn  | replay_lsn | replay_lag | replay_lag_bytes | replay_lag_size | apply_rate |
catchup_interv
al
--------------+-------------+-----------+------------+------------+------------------+-----------------+------------+--
----------
---
   1954860017 | node-three  | 0/DDAA908 | 0/DDAA908  | 00:00:00   |                0 | 0 bytes         |      13682 |
00:00:00
   2299992455 | node-two    | 0/DDAA908 | 0/DDAA908  | 00:00:00   |                0 | 0 bytes         |      13763 |
00:00:00
(2 rows)
```

And it's already replicated.

On node-one get a checksum

Run:

```
select COUNT(*),SUM(value) from quicktest;
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

This command gets some values from the generated data:

```
bdrdb=# select COUNT(*),SUM(value) from quicktest;
```

output

```
 count  |    sum
--------+-----------
 100000 | 498884606
(1 row)
```

Check data

Log in to host-two's Postgres server

```
ssh admin@host-two
sudo -iu enterprisedb psql bdrdb
```

This is your connection to PGD's node-two.

On node-two, get a checksum

Run:

```
select COUNT(*),SUM(value) from quicktest;
```

This command gets node-two's values for the generated data:

```
bdrdb=# select COUNT(*),SUM(value) from quicktest;
```

output

```
 count  |    sum
--------+-----------
 100000 | 498884606
(1 row)
```

Compare with the result from node-one

The values are identical.

You can repeat the process with node-three or generate new data on any node and see it replicate to the other nodes.

Log in to host-three's Postgres server

```
ssh admin@host-two
sudo -iu enterprisedb psql bdrdb
```

This is your connection to PGD's node-three.

On node-three, get a checksum

Run:

```
select COUNT(*),SUM(value) from quicktest;
```

This command gets node-three's values for the generated data:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
bdrdb=# select COUNT(*),SUM(value) from quicktest;
```

output

```
 count  |    sum
--------+-----------
 100000 | 498884606
(1 row)
```

Compare with the result from node-one and node-two

The values are identical.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.7 Step 7 - Configure proxies

Configure proxies

PGD can use proxies to direct traffic to one of the cluster's nodes, selected automatically by the cluster. There are performance and availability reasons for using a proxy:

- Performance: By directing all traffic (in particular, write traffic) to one node, the node can resolve write conflicts locally and more efficiently.
- Availability: When a node is taken down for maintenance or goes offline for other reasons, the proxy can direct new traffic to a new write leader that it selects.

It's best practice to configure PGD Proxy for clusters to enable this behavior.

Configure the cluster for proxies

To set up a proxy, you need to first prepare the cluster and subgroup the proxies will be working with by:

- Logging in and setting the `enable_raft` and `enable_proxy_routing` node group options to `true` for the subgroup. Use `bdr.alter_node_group_option`, passing the subgroup name, option name, and new value as parameters.
- Create as many uniquely named proxies as you plan to deploy using `bdr.create_proxy` and passing the new proxy name and the subgroup to attach it to. The `bdr.create_proxy` does not create a proxy, but creates a space for a proxy to register itself with the cluster. The space contains configuration values which can be modified later. Initially it is configured with default proxy options such as setting the `listen_address` to `0.0.0.0`.
- Configure proxy routes to each node by setting route_dsn for each node in the subgroup. The route_dsn is the connection string that the proxy should use to connect to that node. Use `bdr.alter_node_option` to set the route_dsn for each node in the subgroup.
- Create a pgdproxy user on the cluster with a password or other authentication.

Configure each host as a proxy

Once the cluster is ready, you need to configure each host to run pgd-proxy:

- Create a pgdproxy local user.
- Create a `.pgpass` file for that user that allows the user to log into the cluster as pgdproxy.
- Modify the systemd service file for pgdproxy to use the pgdproxy user.
- Create a proxy config file for the host that lists the connection strings for all the nodes in the subgroup, specifies the name for the proxy to use when fetching proxy options like `listen_address` and `listen_port`.
- Install that file as `/etc/edb/pgd-proxy/pgd-proxy-config.yml`.
- Restart the systemd service and check its status.
- Log in to the proxy and verify its operation.

Further detail on all these steps is included in the worked example.

Worked example

Preparing for proxies

For proxies to function, the `dc1` subgroup must enable Raft and routing.

Log in to any node in the cluster, using psql to connect to the `bdrdb` database as the enterprisedb user. Execute:

```
SELECT bdr.alter_node_group_option('dc1', 'enable_raft', 'true');
SELECT bdr.alter_node_group_option('dc1', 'enable_proxy_routing', 'true');
```

You can use the `bdr.node_group_summary` view to check the status of options previously set with `bdr.alter_node_group_option()`:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
SELECT node_group_name, enable_proxy_routing,
enable_raft
            FROM bdr.node_group_summary
           WHERE parent_group_name IS NOT NULL;
```

output

```
 node_group_name | enable_proxy_routing | enable_raft
-----------------+----------------------+-------------
 dc1             | t                    | t
(1 row)

bdrdb=#
```

Next, create a PGD proxy within the cluster using the `bdr.create_proxy` function. This function takes two parameters: the proxy's unique name and the group you want it to be a proxy for.

In this example, you want a proxy on each host in the `dc1` subgroup:

```
SELECT bdr.create_proxy('pgd-proxy-one','dc1');
SELECT bdr.create_proxy('pgd-proxy-two','dc1');
SELECT bdr.create_proxy('pgd-proxy-three','dc1');
```

You can use the `bdr.proxy_config_summary` view to check that the proxies were created:

```
SELECT proxy_name,
node_group_name
             FROM bdr.proxy_config_summary;
```

output

```
   proxy_name    | node_group_name
-----------------+-----------------
 pgd-proxy-one   | dc1
 pgd-proxy-two   | dc1
 pgd-proxy-three | dc1

 bdrdb=#
```

Create a pgdproxy user on the database

Create a user named pgdproxy and give it a password. This example uses `proxysecret`.

On any node, log into the `bdrdb` database as enterprisedb/postgres.

```
CREATE USER pgdproxy PASSWORD 'proxysecret';
GRANT bdr_superuser TO pgdproxy;
```

Configure proxy routes to each node

Once a proxy has connected, it gets its dsn values (connection strings) from the cluster. The cluster needs to know the connection details that a proxy should use for each node in the subgroup. This is done by setting the `route_dsn` option for each node to a connection string that the proxy can use to connect to that node.

Please note that when a proxy starts, it gets the initial dsn from the proxy's config file. The route_dsn value set in this step and in config file should match.

On any node, log into the bdrdb database as enterprisedb/postgres.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
SELECT bdr.alter_node_option('node-one', 'route_dsn', 'host=host-one dbname=bdrdb port=5444
user=pgdproxy');
SELECT bdr.alter_node_option('node-two', 'route_dsn', 'host=host-two dbname=bdrdb port=5444
user=pgdproxy');
SELECT bdr.alter_node_option('node-three', 'route_dsn', 'host=host-three dbname=bdrdb port=5444
user=pgdproxy');
```

Note that the endpoints in this example specify `port=5444`. This is necessary for EDB Postgres Advanced Server instances. For EDB Postgres Extended and community PostgreSQL, you can omit this.

Create a pgdproxy user on each host

```
sudo adduser pgdproxy
```

This user needs credentials to connect to the server. Create a `.pgpass` file with the `proxysecret` password in it. Then lock down the `.pgpass` file so it's accessible only by its owner.

```
echo -e "*:*:*:pgdproxy:proxysecret" | sudo tee /home/pgdproxy/.pgpass
sudo chown pgdproxy /home/pgdproxy/.pgpass
sudo chmod 0600 /home/pgdproxy/.pgpass
```

Configure the systemd service on each host

Switch the service file from using root to using the pgdproxy user.

```
sudo sed -i s/root/pgdproxy/ /usr/lib/systemd/system/pgd-proxy.service
```

Reload the systemd daemon.

```
sudo systemctl daemon-reload
```

Create a proxy config file for each host

The proxy configuration file is slightly different for each host. It's a YAML file that contains a cluster object. The cluster object has three properties:

- The name of the PGD cluster's top-level group (as `name`)
- An array of endpoints of databases (as `endpoints`)
- The proxy definition object with a name and endpoint (as `proxy`)

The first two properties are the same for all hosts:

```
cluster:
  name: pgd
  endpoints:
    - "host=host-one dbname=bdrdb port=5444 user=pgdproxy"
    - "host=host-two dbname=bdrdb port=5444 user=pgdproxy"
    - "host=host-three dbname=bdrdb port=5444 user=pgdproxy"
```

Remember that host-one, host-two, and host-three are the systems on which the cluster nodes (node-one, node-two, node-three) are running. You use the name of the host, not the node, for the endpoint connection.

Again, note that the endpoints in this example specify `port=5444`. This is necessary for EDB Postgres Advanced Server instances. For EDB Postgres Extended and community PostgreSQL, you can set this to `port=5432`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

The third property, `proxy`, has a `name` property. The `name` property is a name created with `bdr.create_proxy` earlier, and it's different on each host. A proxy can't be on the same port as the Postgres server and, ideally, should be on a commonly used port different from direct connections, even when no Postgres server is running on the host. Typically, you use port 6432 for PGD proxies.

```
  proxy:
    name: pgd-proxy-one
```

In this case, using `localhost` in the endpoint specifies that this proxy will listen on the host where the proxy is running.

Install a PGD proxy configuration on each host

For each host, create the `/etc/edb/pgd-proxy` directory:

```
sudo mkdir -p /etc/edb/pgd-proxy
```

Then, on each host, write the appropriate configuration to the `pgd-proxy-config.yml` file in the `/etc/edb/pgd-proxy` directory.

For this example, you can run this on host-one to create the file:

```
cat <<EOF | sudo tee /etc/edb/pgd-proxy/pgd-proxy-config.yml
cluster:
  name: pgd
  endpoints:
    - "host=host-one dbname=bdrdb port=5444 user=pgdproxy"
    - "host=host-two dbname=bdrdb port=5444 user=pgdproxy"
    - "host=host-three dbname=bdrdb port=5444 user=pgdproxy"
  proxy:
    name: pgd-proxy-one
EOF
```

Restart the service

On each host where the proxy is being installed, restart the pgd-proxy service.

```
sudo systemctl restart pgd-proxy
```

Confirm it's running correctly:

```
sudo systemctl status pgd-proxy
```

When running, it shows `Active: (running)` in the opening details.

Test the proxy

At this point, connecting to the PGD Proxy port on any host in the cluster results in the connection being routed to the current write lead node.

For example, and assuming you've installed the proxy on all three hosts, then connecting to the proxy on host-three results in the connection being routed to node-one.

This example passes connection details, using the `-d` flag of psql with the hostname for the proxy you just configured and the proxy port number:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
sudo -iu enterprisedb psql -d "host=host-three dbname=bdrdb port=6432"
```

output

```
psql (16.1.0, server 16.1.0)
Type "help" for help.

bdrdb=#
```

Once connected to the proxy, you can query the server to find out which node the proxy connected you to:

```
SELECT node_name FROM bdr.local_node_summary;
```

output

```
 node_name
-----------
 node-one
(1 row)
bdrdb#
```

You should have connected to the current write leader of the subgroup. You can confirm that by querying which node is the write leader for the subgroup you're connected to:

```
SELECT node_group_name, write_lead FROM
bdr.node_group_routing_summary;
```

output

```
 node_group_name | write_lead
-----------------+------------
 dc1             | node-one
(1 row)

bdrdb=#
```

And the write_lead is node-one, too, so you confirm you're being proxy-connected to the write leader.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.1.1.8 Step 8 - Using PGD CLI

Using PGD CLI

The PGD CLI command uses a configuration file to work out the hosts to connect to. There are options that allow you to override this to use alternative configuration files or explicitly point at a server. But, by default, PGD CLI looks for a configuration file in preset locations.

The connection to the database is authenticated in the same way as other command line utilities, like the psql command, are authenticated.

Unlike other commands, PGD CLI doesn't interactively prompt for your password. Therefore, you must pass your password using one of the following methods:

- Adding an entry to your `.pgpass` password file, which includes the host, port, database name, user name, and password
- Setting the password in the `PGPASSWORD` environment variable
- Including the password in the connection string

We recommend the first option, as the other options don't scale well with multiple database clusters, or they compromise password confidentiality.

Configuring and connecting PGD CLI

- Ensure PGD CLI is installed.
  - If PGD CLI was already installed, move to the next step.
  - For any system, repeat the configure repositories step on that system.
  - Then run the package installation command appropriate for that platform.
    - RHEL and derivatives: `sudo dnf install edb-pgd5-cli`
    - Debian, Ubuntu, and derivatives: `sudo apt-get install edb-pgd5-cli`

- Create a configuration file.
  - This is a YAML file that specifies the cluster and endpoints for PGD CLI to use.

- Install the configuration file.
  - Copy the YAML configuration file to a default config directory `/etc/edb/pgd-cli/` as `pgd-cli-config.yml`.
  - Repeat this process on any system where you want to run PGD CLI.

- Run pgd-cli.

Use PGD CLI to explore the cluster

- Check the health of the cluster with the `cluster show --health` command.
- Show the nodes in the cluster with the `nodes list` command.
- Show the groups in the cluster with the `groups list` command.
- Set a group option with the `group set-option` command.
- Switch write leader with the `group set-leader` command.

For more details about these commands, see the worked example that follows.

Also consult the PGD CLI documentation for details of other configuration options and a full command reference.

Worked example

Ensure PGD CLI is installed

In this worked example, you configure and use PGD CLI on host-one, where you've already installed Postgres and PGD. You don't need to install PGD CLI again.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Create a configuration file

The PGD CLI configuration file is similar to the PGD Proxy configuration file. It's a YAML file that contains a cluster object. This has two properties:

- The name of the PGD cluster's top-level group (as `name`)
- An array of endpoints of databases (as `endpoints`)

```
cluster:
  name: pgd
  endpoints:
    - host=host-one dbname=bdrdb port=5444
    - host=host-two dbname=bdrdb port=5444
    - host=host-three dbname=bdrdb port=5444
```

Note that the endpoints in this example specify `port=5444`. This is necessary for EDB Postgres Advanced Server instances. For EDB Postgres Extended and community PostgreSQL, you can omit this.

Install the configuration file

Create the PGD CLI configuration directory:

```
sudo mkdir -p /etc/edb/pgd-cli
```

Then, write the configuration to the `pgd-cli-config.yml` file in the `/etc/edb/pgd-cli` directory.

For this example, you can run this on host-one to create the file:

```
cat <<EOF | sudo tee /etc/edb/pgd-cli/pgd-cli-config.yml
cluster:
  name: pgd
  endpoints:
    - host=host-one dbname=bdrdb port=5444
    - host=host-two dbname=bdrdb port=5444
    - host=host-three dbname=bdrdb port=5444
EOF
```

You can repeat this process on any system where you need to use PGD CLI.

Run PGD CLI

With the configuration file in place, and logged in as the enterprisedb system user, you can run pgd-cli. For example, you can use the `nodes list` command to list the nodes in your cluster and their status:

```
pgd nodes list
```

output

```
Node Name Group Name   Node Kind Join State Node Status
---------  ----------- --------- ---------- -----------
node-one   dc1         data      ACTIVE     Up
node-three dc1         data      ACTIVE     Up
node-two   dc1         data      ACTIVE     Up
```

Using PGD CLI to explore the cluster

Once PGD CLI is configured, you can use it to get PGD-level views of the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Check the health of the cluster

The `cluster show --health` command provides a quick way to view the health of the cluster:

```
pgd cluster show --health
```

output

```
Check             Status Details
----------------- ------ ------------------------------------------------
Connections       Ok     All BDR nodes are accessible
Raft              Ok     Raft Consensus is working correctly
Replication Slots Ok     All PGD replication slots are working correctly
Clock Drift        Ok     Clock drift is within permissible limit
Versions          Ok     All nodes are running the same PGD version
```

Show the nodes in the cluster

As previously seen, the `nodes list` command lists the nodes in the cluster:

```
pgd nodes list
```

output

```
Node Name  Group Name  Node Kind Join State Node Status
---------- ----------- --------- ---------- -----------
node-one   dc1         data      ACTIVE     Up
node-three dc1         data      ACTIVE     Up
node-two   dc1         data      ACTIVE     Up
```

This view shows the group the node is a member of and its current status. To find out what versions of PGD and Postgres are running on the nodes, use `nodes list --versions`:

```
pgd nodes list --versions
```

output

```
Node Name BDR Version                 Postgres Version
---------- --------------------------  --------------------------------
node-one   5.7.0 (snapshot e2534db6d)   16.6 (Debian 16.6-1EDB.bullseye)
node-three 5.7.0 (snapshot e2534db6d)   16.6 (Debian 16.6-1EDB.bullseye)
node-two   5.7.0 (snapshot e2534db6d)   16.6 (Debian 16.6-1EDB.bullseye)
```

Show the groups in the cluster

Finally, the `groups list` command for PGD CLI shows which groups are configured, and more:

```
pgd groups list
```

output

```
Group Name   Parent Group Name Group Type Nodes
------------ ----------------- ---------- -----
pgd                            global     0
dc1          pgd               data       3
```

This command shows:

- The groups
- Their types
- Their parent group
- The number of nodes in each group

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Set a group option

You can set group options using PGD CLI, too, using the `group set-option` command. If you wanted to set the `dc1` group's location to `London`, you would run:

```
pgd group dc1 set-option location London
```

output

```
Status Message
------ ------------------------------
OK     Command executed successfully
```

You can verity the new location using the `group get-option` command:

```
pgd group dc1 get-option location
```

output

```
Option Name Option Value
----------- ------------
location    London
```

Set the write leader

If you need to change write leader in a group, to enable maintenance on a host, PGD CLI offers the `group set-leader` command. You enter a group name after `group` and the name of the node you want to switch to after `set leader`:

```
pgd group dc1 set-leader node-two
```

output

```
Status Message
------ ------------------------------
OK     Command executed successfully
```

You can verify the write leader using the `group show command` with the `--summary option`:

```
pgd group dc1 show --summary
```

output

```
Group Property    Value
----------------- ------------
Group Name        dc1
Parent Group Name pgd
Group Type        data
Write Leader      node-two
Commit Scope
```

More details on the available commands in PGD CLI are available in the PGD CLI command reference.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.2 Deployment and management with TPA

TPA (Trusted Postgres Architect) is a standard automated way of installing PGD and Postgres on physical and virtual machines, both self-hosted and in the cloud (with AWS EC2).

> **Get started with TPA and PGD quickly**
>
> If you want to experiment with a local deployment as quickly as possible, you can deploying an EDB Postgres Distributed example cluster on Docker to configure, provision, and deploy a PGD 5 Always-on cluster on Docker.
>
> If deploying to the cloud is your aim, you can deploying an EDB Postgres Distributed example cluster on AWS to get a PGD 5 cluster on your own Amazon account.
>
> If you want to run on your own Linux systems or VMs, you can use also use TPA to deploy EDB Postgres Distributed directly to your own Linux hosts

This section covers how to use TPA to deploy and administer EDB Postgres Distributed.

- Deploying with TPA works through the steps needed to:
  - Install TPA.
  - Use TPA to create a configuration.
  - Deploy the configuration with TPA.

The installing section provides an example cluster that will be used in future examples.

You can also perform a rolling major version upgrade with PGD administered by TPA.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.2.1 Deploying PGD using TPA

The standard way of automatically deploying EDB Postgres Distributed in a self-managed setting is to use EDB's deployment tool: Trusted Postgres Architect (TPA). This applies to physical and virtual machines, both self-hosted and in the cloud (EC2),

> **Get started with TPA and PGD quickly**
>
> If you want to experiment with a local deployment as quickly as possible, you can deploy an EDB Postgres Distributed example cluster on Docker to configure, provision, and deploy a PGD 5 Always-on cluster on Docker.
>
> If deploying to the cloud is your aim, you can deploy an EDB Postgres Distributed example cluster on AWS to get a PGD 5 cluster on your own Amazon account.
>
> If you want to run on your own Linux systems or VMs, you can also use TPA to deploy EDB Postgres Distributed directly to your own Linux hosts.

Prerequisite: Install TPA

Before you can use TPA to deploy PGD, you must install TPA. Follow the installation instructions in the Trusted Postgres Architect documentation before continuing.

At the highest level, using TPA to deploy PGD involves the following steps:

1: Use TPA to create a configuration for your PGD cluster.

2: Provision, deploy, and test your PGD cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.2.1.1 Configuring a PGD cluster with TPA

The `tpaexec configure` command generates a simple YAML configuration file to describe a cluster, based on the options you select. The configuration is ready for immediate use, and you can modify it to better suit your needs. Editing the configuration file is the usual way to make any configuration changes to your cluster both before and after it's created.

The syntax is:

```
tpaexec configure <cluster_dir> --architecture <architecture_name> [options]
```

The available configuration options include:

Flags	Description
`--architecture`	Required. Set to `PGD-Always-ON` for EDB Postgres Distributed deployments.
`--postgresql <version>` or `--edb-postgres-advanced <version>` or `--edb-postgres-extended <version>`	Required. Specifies the distribution and version of Postgres to use. For more details, seeCluster configuration: Postgres flavour and version.
`--redwood` or `--no-redwood`	Required when `--edb-postgres-advanced` flag is present. Specifies whether Oracle database compatibility features are desired.
`--location-names l1 l2 l3`	Required. Specifies the names of the locations to deploy PGD to.
`--data-nodes-per-location N`	Specifies the number of data nodes per location. Default is 3.
`--add-witness-node-per-location`	For an even number of data nodes per location, adds witness nodes to allow for local consensus. Enabled by default for 2-data-node locations.
`--add-proxy-nodes-per-location`	Specifies whether to separate PGD proxies from data nodes and how many to configure. By default one proxy is configured and cohosted for each data node.
`--pgd-proxy-routing global|local`	Specifies whether PGD Proxy routing is handled on a global or local (per-location) basis.
`--add-witness-only-location loc`	Designates one of the cluster locations as witness-only (no data nodes are present in that location).
`--enable-camo`	Sets up a CAMO pair in each location. Works only with 2 data nodes per location.

More configuration options are listed in the TPA documentation for PGD-Always-ON.

For example:

```
[tpa]$ tpaexec configure ~/clusters/speedy \
         --architecture PGD-Always-ON \
         --platform aws \
         --edb-postgres-advanced 16 \
         --redwood \
         --location-names eu-west-1 eu-north-1 eu-central-1 \
         --data-nodes-per-location 3 \
         --pgd-proxy-routing global
```

The first argument must be the cluster directory, for example, `speedy` or `~/clusters/speedy`. (The cluster is named `speedy` in both cases.) We recommend that you keep all your clusters in a common directory, for example, `~/clusters`. The next argument must be `--architecture` to select an architecture, followed by options.

The command creates a directory named `~/clusters/speedy` and generates a configuration file named `config.yml` that follows the layout of the PGD-Always-ON architecture. You can use the `tpaexec configure --architecture PGD-Always-ON --help` command to see the values that are supported for the configuration options in this architecture.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

In the example, the options select:

- An AWS deployment (`--platform aws`)
- EDB Postgres Advanced Server, version 16 and Oracle compatibility (`--edb-postgres-advanced 16` and `--redwood`)
- Three locations (`--location-names eu-west-1 eu-north-1 eu-central-1`)
- Three data nodes at each location (`--data-nodes-per-location 3`)
- Proxy routing policy of global (`--pgd-proxy-routing global`)

Common configuration options

Other configuration options include the following.

Owner

Every cluster must be directly traceable to a person responsible for the provisioned resources.

By default, a cluster is tagged as being owned by the login name of the user running `tpaexec provision` . If this name doesn't identify a person (for example, `postgres` , `ec2-user`), you must specify `--owner SomeId` to set an identifiable owner.

You can use your initials, "Firstname Lastname", or any text that identifies you uniquely.

Platform options

The default value for `--platform` is `aws` , which is the platform supported by the PGD-Always-ON architecture.

Specify `--region` to specify any existing AWS region that you have access to and that allows you to create the required number of instances. The default region is eu-west-1.

Specify `--instance-type` with any valid instance type for AWS. The default is t3.micro.

Subnet selection

By default, each cluster is assigned a random /28 subnet under 10.33/16. However, depending on the architecture, there can be one or more subnets, and each subnet can be anywhere between a /24 and a /29.

Specify `--subnet` to use a particular subnet, for example, `--subnet 192.0.2.128/27` .

Disk space

Specify `--root-volume-size` to set the size of the root volume in GB, for example, `--root-volume-size 64` . The default is 16GB. Depending on the image used to create instances, there might be a minimum size for the root volume.

For architectures that support separate Postgres and Barman volumes:

- Specify `--postgres-volume-size` to set the size of the Postgres volume in GB. The default is 16GB.
- Specify `--barman-volume-size` to set the size of the Barman volume in GB. The default is 32GB.

Distribution

Specify `--os` or `--distribution` to specify the OS to use on the cluster's instances. The value is case sensitive.

The selected platform determines the distributions that are available and the one that's used by default. For more details, see `tpaexec info platforms/<platformname>` .

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

In general, you can use `Debian`, `RedHat`, and `Ubuntu` to select TPA images that have Postgres and other software preinstalled (to reduce deployment times). To use stock distribution images instead, append `-minimal` to the value, for example, `--distribution Debian-minimal`.

Repositories

When using TPA to deploy PDG 5 and later, TPA selects repositories from EDB Repos 2.0. All software is sourced from these repositories.

To use EDB Repos 2.0, you must use `export EDB_SUBSCRIPTION_TOKEN=xxx` before you run tpaexec. For instructions on obtaining this token, see:Get your token.

Optionally, use `--edb-repositories repository …` to specify EDB repositories in addition to the default repository to install on each instance.

Software versions

By default, TPA uses the latest major version of Postgres. Specify `--postgres-version` to install an earlier supported major version, or specify both version and distribution using one of the flags described under Configure.

By default, TPA installs the latest version of every package, which is usually the desired behavior. However, in some testing scenarios, you might need to select specific package versions. For example:

```
--postgres-package-version 10.4-2.pgdg90+1
--repmgr-package-version 4.0.5-1.pgdg90+1
--barman-package-version 2.4-1.pgdg90+1
--pglogical-package-version '2.2.0*'
--bdr-package-version '3.0.2*'
--pgbouncer-package-version '1.8*'
```

Specify `--extra-packages` or `--extra-postgres-packages` to install more packages. The former lists packages to install along with system packages. The latter lists packages to install later along with Postgres packages. (If you mention packages that depend on Postgres in the former list, the installation fails because Postgres isn't yet installed.) The arguments are passed on to the package manager for installation without any modifications.

The `--extra-optional-packages` option behaves like `--extra-packages`, but it's not an error if the named packages can't be installed.

Hostnames

By default, `tpaexec configure` randomly selects as many hostnames as it needs from a preapproved list of several dozen names, which is enough for most clusters.

Specify `--hostnames-from` to select names from a different list, for example, if you need more names than are available in the supplied list. The file must contain one hostname per line.

Specify `--hostnames-pattern` to restrict hostnames to those matching the egrep-syntax pattern. If you choose to do this, you must ensure that the pattern matches only valid hostnames ([a-zA-Z0-9-]) and finds enough of them.

Locations

By default, `tpaexec configure` uses the names first, second, and so on for any locations used by the selected architecture.

Specify `--location-names` to provide more meaningful names for each location.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.2.1.2 Provisioning, deploying, and testing

Provision

> **Note**
>
> TPA now runs the `provision` command as part of the `deploy` command. The `provision` command is still available for use, but you don't need to run it separately.

The `tpaexec provision` command creates instances and other resources required by the cluster. The details of the process depend on the architecture (for example, PGD-Always-ON) and platform (for example, AWS) that you selected while configuring the cluster.

For example, given AWS access with the necessary privileges, TPA provisions EC2 instances, VPCs, subnets, routing tables, internet gateways, security groups, EBS volumes, elastic IPs, and so on.

You can also provision existing servers by selecting the `bare` platform and providing connection details. Whether these are bare metal servers or those provisioned separately on a cloud platform, you can use them as if they were created by TPA.

You aren't restricted to a single platform. You can spread your cluster out across some AWS instances in multiple regions and some on-premises servers or servers in other data centres, as needed.

At the end of the provisioning stage, you will have the required number of instances with the basic operating system installed, which TPA can access using SSH (with sudo to root).

Deploy

The `tpaexec deploy` command installs and configures Postgres and other software on the provisioned servers. This includes setting up replication, backups, and so on. TPA can create the servers, but it doesn't matter who created them so long as SSH and sudo access are available.

At the end of the deployment stage, EDB Postgres Distributed is up and running.

Test

The `tpaexec test` command executes various architecture and platform-specific tests against the deployed cluster to ensure that it's working as expected.

At the end of the testing stage, you have a fully functioning cluster.

For more information, see Trusted Postgres Architect.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.3 Deploying and configuring PGD on Kubernetes

EDB CloudNativePG Global Cluster is a Kubernetes operator designed, developed, and supported by EDB. It covers the full lifecycle of highly available Postgres database clusters with a multi-master architecture, using PGD replication. It's based on the open source CloudNativePG operator and provides additional value, such as compatibility with Oracle using EDB Postgres Advanced Server, Transparent Data Encryption (TDE) using EDB Postgres Extended or Advanced Server, and additional supported platforms including IBM Power and OpenShift.

This section covers how to deploy and configure EDB Postgres Distributed using the EDB CloudNativePG Global Cluster operator.

- Quick start in the EDB CloudNativePG Global Cluster documentation works through the steps needed to:
    - Create a Kind/Minikube cluster.
    - Install Helm and the Helm chart for EDB CloudNativePG Global Cluster.
    - Create a simple configuration file for a PGD cluster.
    - Deploy a PGD cluster from that simple configuration file.
- Installation and upgrade provides detailed instructions for installing and upgrading EDB CloudNativePG Global Cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

9.4 Deploying and configuring PGD on EDB Postgres AI Cloud Service

EDB Postgres AI Cloud Service is a fully managed database-as-a-service with built-in Oracle compatibility. It runs in your cloud account where it's operated by our Postgres experts. EDB Postgres AI Cloud Service makes it easy to set up, manage, and scale your databases. The addition of distributed high-availability support powered by EDB Postgres Distributed (PGD) enables single and multi-region Always-on clusters.

This section covers how to work with EDB Postgres Distributed when deployed on EDB Postgres AI Cloud Service:

- Creating a distributed high-availability cluster in the Cloud Service documentation works through the steps needed to:
  - Prepare your cloud environment for a distributed high-availability cluster.
  - Sign in to Cloud Service.
  - Create a distributed high-availability cluster, including:
    - Creating and configuring a data group.
    - Optionally creating and configuring a second data group in a different region.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10 Application use

Developing an application with PGD is mostly the same as working with any PostgreSQL database. What's different, though, is that you need to be aware of how your application interacts with replication. You need to know how PGD behaves with applications, the SQL that is and isn't replicated, how different nodes are handled, and other important information.

- Application behavior looks at how PGD replication appears to an application, such as:
    - The commands that are replicated
    - The commands that run locally
    - When row-level locks are acquired
    - How and where triggers fire
    - Large objects
    - Toast
- DML and DDL replication shows the differences between the two classes of SQL statements and how PGD handles replicating them. It also looks at the commands PGD doesn't replicate at all.
- Nodes with differences examines how PGD works with configurations where there are differing table structures and schemas on replicated nodes. Also covered is how to compare between such nodes with LiveCompare and how differences in PostgreSQL versions running on nodes can be handled.
- Application rules offers some general rules for applications to avoid data anomalies.
- Timing considerations shows how the asynchronous/synchronous replication might affect an application's view of data and notes functions to mitigate stale reads.
- Extension usage explains how to select, install, and configure extensions on PGD.
- Table access methods (TAMs) notes the TAMs available with PGD and how to enable them.
- Feature compatibility shows which server features work with which commit scopes and which commit scopes can be daisy chained together.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.1 Application behavior

Much of PGD's replication behavior is transparent to applications. Understanding how it achieves that and the elements that aren't transparent is important to successfully developing an application that works well with PGD.

Replication behavior

PGD supports replicating changes made on one node to other nodes.

PGD, by default, replicates all changes from INSERT, UPDATE, DELETE, and TRUNCATE operations from the source node to other nodes. Only the final changes are sent, after all triggers and rules are processed. For example, `INSERT ... ON CONFLICT UPDATE` sends either an insert or an update, depending on what occurred on the origin. If an update or delete affects zero rows, then no changes are sent.

You can replicate INSERT without any preconditions.

For updates and deletes to replicate on other nodes, PGD must be able to identify the unique rows affected. PGD requires that a table have either a PRIMARY KEY defined, a UNIQUE constraint, or an explicit REPLICA IDENTITY defined on specific columns. If one of those isn't defined, a warning is generated, and later updates or deletes are explicitly blocked. If REPLICA IDENTITY FULL is defined for a table, then a unique index isn't required. In that case, updates and deletes are allowed and use the first non-unique index that's live, valid, not deferred, and doesn't have expressions or WHERE clauses. Otherwise, a sequential scan is used.

Truncate

You can use TRUNCATE even without a defined replication identity. Replication of TRUNCATE commands is supported, but take care when truncating groups of tables connected by foreign keys. When replicating a truncate action, the subscriber truncates the same group of tables that was truncated on the origin, either explicitly specified or implicitly collected by CASCADE, except in cases where replication sets are defined. See Replication sets for details and examples. This works correctly if all affected tables are part of the same subscription. But if some tables to truncate on the subscriber have foreign-key links to tables that aren't part of the same (or any) replication set, then applying the truncate action on the subscriber fails.

Row-level locks

Row-level locks taken implicitly by INSERT, UPDATE, and DELETE commands are replicated as the changes are made. Table-level locks taken implicitly by INSERT, UPDATE, DELETE, and TRUNCATE commands are also replicated. Explicit row-level locking (`SELECT ... FOR UPDATE/FOR SHARE`) by user sessions isn't replicated, nor are advisory locks. Information stored by transactions running in SERIALIZABLE mode isn't replicated to other nodes. The transaction isolation level of SERIALIAZABLE is supported, but transactions aren't serialized across nodes in the presence of concurrent transactions on multiple nodes.

If DML is executed on multiple nodes concurrently, then potential conflicts might occur if executing with asynchronous replication. You must either handle these or avoid them. Various avoidance mechanisms are possible, discussed in Conflicts.

Sequences

Sequences need special handling, described in Sequences. This is because in a cluster, sequences must be global to avoid nodes creating conflicting values. Global sequences are available with global locking to ensure integrity.

Binary objects

Binary data in BYTEA columns is replicated normally, allowing "blobs" of data up to 1 GB. Use of the PostgreSQL "large object" facility isn't supported in PGD.

Rules

Rules execute only on the origin node so aren't executed during apply, even if they're enabled for replicas.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Base tables only

Replication is possible only from base tables to base tables. That is, the tables on the source and target on the subscription side must be tables, not views, materialized views, or foreign tables. Attempts to replicate tables other than base tables result in an error. DML changes that are made through updatable views are resolved to base tables on the origin and then applied to the same base table name on the target.

Partitioned tables

PGD supports partitioned tables transparently, meaning that you can add a partitioned table to a replication set and changes that involve any of the partitions are replicated downstream.

Triggers

By default, triggers execute only on the origin node. For example, an INSERT trigger executes on the origin node and is ignored when you apply the change on the target node. You can specify for triggers to execute on both the origin node at execution time and on the target when it's replicated (*apply time*) by using `ALTER TABLE ... ENABLE ALWAYS TRIGGER`. Or, use the `REPLICA` option to execute only at apply time: `ALTER TABLE ... ENABLE REPLICA TRIGGER`.

Some types of trigger aren't executed on apply, even if they exist on a table and are currently enabled. Trigger types not executed are:

- Statement-level triggers (`FOR EACH STATEMENT`)
- Per-column UPDATE triggers (`UPDATE OF column_name [, ...]`)

PGD replication apply uses the system-level default search_path. Replica triggers, stream triggers, and index expression functions can assume other search_path settings that then fail when they execute on apply. To prevent this from occurring, use any of these techniques:

- Resolve object references clearly using only the default search_path.
- Always use fully qualified references to objects, for example, `schema.objectname`.
- Set the search path for a function using `ALTER FUNCTION ... SET search_path = ...` for the functions affected.

PGD assumes that there are no issues related to text or other collatable datatypes, that is, all collations in use are available on all nodes, and the default collation is the same on all nodes. Replicating changes uses equality searches to locate Replica Identity values, so this doesn't have any effect except where unique indexes are explicitly defined with nonmatching collation qualifiers. Row filters might be affected by differences in collations if collatable expressions were used.

Toast

PGD handling of very long "toasted" data in PostgreSQL is transparent to the user. The TOAST "chunkid" values likely differ between the same row on different nodes, but that doesn't cause any problems.

> **REPLICA IDENTITY FULL required for tables with TOAST-able columns**
>
> Tables that hold `TOAST`-able column types (`text`, `bytea`, `jsonb`, large `varchar`, and so on) must use `REPLICA IDENTITY FULL`. BDR 4 doesn't set this behavior by default. Enable it explicitly on every table that can store `TOAST` values:
>
> ```
> ALTER TABLE your_table REPLICA IDENTITY
> FULL;
> ```

When an `UPDATE` doesn't change a `TOAST` column, the column is sent in the replication stream as an unchanged marker rather than as full data. Under `REPLICA IDENTITY FULL`, Postgres flattens the entire pre-update row (including its `TOAST` data) into WAL, so the receiver always has an authoritative source for unchanged columns. Under `REPLICA IDENTITY DEFAULT` (or `USING INDEX`), the receiver fills unchanged `TOAST` columns from its local copy of the row, which may be stale if a concurrent update on another node modified a different column of the same row, resulting in data divergence between nodes.

> **Note**
>
> `REPLICA IDENTITY FULL` doesn't enable replicating rows whose total `TOAST` data exceeds approximately 1 GB. Updates on such rows fail at the source with `invalid memory alloc request size` because Postgres must flatten the entire pre-update row in memory before WAL logging, and the flattened tuple exceeds `MaxAllocSize`. There's currently no replication-safe path for rows of that size. Avoid creating them.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Other restrictions

PGD can't work correctly if Replica Identity columns are marked as external.

PostgreSQL allows CHECK() constraints that contain volatile functions. Since PGD reexecutes CHECK() constraints on apply, any subsequent reexecution that doesn't return the same result as before causes data divergence.

PGD doesn't restrict the use of foreign keys. Cascading FKs are allowed.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.2 DML and DDL replication and nonreplication

The two major classes of SQL statement are DML and DDL.

- DML is the data modification language and is concerned with the SQL statements that modify the data stored in tables. It includes UPDATE, DELETE, and INSERT.
- DDL is the data definition language and is concerned with the SQL statements that modify how the data is stored. It includes CREATE, ALTER, and DROP.

PGD handles each class differently.

DML replication

PGD doesn't replicate the DML statement. It replicates the changes caused by the DML statement. For example, an UPDATE that changed two rows replicates two changes, whereas a DELETE that didn't remove any rows doesn't replicate anything. This means that the results of executing volatile statements are replicated, ensuring there's no divergence between nodes as might occur with statement-based replication.

DDL replication

DDL replication works differently from DML. For DDL, PGD replicates the statement, which then executes on all nodes. So a `DROP TABLE IF EXISTS` might not replicate anything on the local node, but the statement is still sent to other nodes for execution if DDL replication is enabled. For details, see DDL replication.

PGD works to ensure that intermixed DML and DDL statements work correctly, even in the same transaction.

Nonreplicated statements

Outside of those two classes are SQL commands that PGD, by design, doesn't replicate. None of the following user commands are replicated by PGD, so their effects occur on the local/origin node only:

- Cursor operations (DECLARE, CLOSE, FETCH)
- Execution commands (DO, CALL, PREPARE, EXECUTE, EXPLAIN)
- Session management (DEALLOCATE, DISCARD, LOAD)
- Parameter commands (SET, SHOW)
- Constraint manipulation (SET CONSTRAINTS)
- Locking commands (LOCK)
- Table maintenance commands (VACUUM, ANALYZE, CLUSTER)
- Async operations (NOTIFY, LISTEN, UNLISTEN)

Since the `NOTIFY` SQL command and the `pg_notify()` functions aren't replicated, notifications aren't reliable in case of failover. This means that notifications can easily be lost at failover if a transaction is committed just when the server crashes. Applications running `LISTEN` might miss notifications in case of failover.

This is true in standard PostgreSQL replication, and PGD doesn't yet improve on this.

CAMO and Eager Replication options don't allow the `NOTIFY` SQL command or the `pg_notify()` function.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.3 Nodes with differences

Replicating between nodes with differences

By default, DDL is sent to all nodes. You can control this behavior, as described in DDL replication, and you can use it to create differences between database schemas across nodes. PGD is designed to allow replication to continue even with minor differences between nodes. These features are designed to allow application schema migration without downtime or to allow logical standby nodes for reporting or testing.

Currently, replication requires the same table name on all nodes. A future feature might allow a mapping between different table names.

It's possible to replicate between tables with dissimilar partitioning definitions, such as a source that's a normal table replicating to a partitioned table, including support for updates that change partitions on the target. It can be faster if the partitioning definition is the same on the source and target since dynamic partition routing doesn't need to execute at apply time. For details, see Replication sets.

By default, all columns are replicated.

PGD replicates data columns based on the column name. If a column has the same name but a different data type, PGD attempts to cast from the source type to the target type, if casts were defined that allow that.

PGD supports replicating between tables that have a different number of columns.

If the target has missing columns from the source, then PGD raises a `target_column_missing` conflict, for which the default conflict resolver is `ignore_if_null`. This throws an error if a non-NULL value arrives. Alternatively, you can also configure a node with a conflict resolver of `ignore`. This setting doesn't throw an error but silently ignores any additional columns.

If the target has additional columns not seen in the source record, then PGD raises a `source_column_missing` conflict, for which the default conflict resolver is `use_default_value`. Replication proceeds if the additional columns have a default, either NULL (if nullable) or a default expression. If not, it throws an error and halts replication.

Transform triggers can also be used on tables to provide default values or alter the incoming data in various ways before apply.

If the source and the target have different constraints, then replication is attempted, but it might fail if the rows from source can't be applied to the target. Row filters can help here.

Replicating data from one schema to a more relaxed schema doesn't cause failures. Replicating data from a schema to a more restrictive schema can be a source of potential failures. The right way to solve this is to place a constraint on the more relaxed side, so bad data can't be entered. That way, no bad data ever arrives by replication, so it never fails the transform into the more restrictive schema. For example, if one schema has a column of type TEXT and another schema defines the same column as XML, add a CHECK constraint onto the TEXT column to enforce that the text is XML.

You can define a table with different indexes on each node. By default, the index definitions are replicated. To specify how to create an index on only a subset of nodes or just locally, see DDL replication .

Storage parameters, such as `fillfactor` and `toast_tuple_target`, can differ between nodes for a table without problems. An exception to that behavior is that the value of a table's storage parameter `user_catalog_table` must be identical on all nodes.

A table being replicated must be owned by the same user/role on each node. See Security and roles for details.

Roles can have different passwords for connection on each node, although by default changes to roles are replicated to each node. See DDL replication to specify how to alter a role password on only a subset of nodes or locally.

Comparison between nodes with differences

LiveCompare is a tool for data comparison on a database against PGD and non-PGD nodes. It needs a minimum of two connections to compare against and reach a final result.

Starting with LiveCompare 1.3, you can configure with `all_bdr_nodes` set. This setting saves you from clarifying all the relevant DSNs for each separate node in the cluster. An EDB Postgres Distributed cluster has N amount of nodes with connection information, but it's only the initial and output connection that LiveCompare 1.3 and later needs to complete its job. Setting `logical_replication_mode` states how all the nodes are communicating.

All the configuration is done in a `.ini` file named `bdrLC.ini`, for example. Find templates for this configuration file in `/etc/2ndq-livecompare/`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

While LiveCompare executes, you see N+1 progress bars, N being the number of processes. Once all the tables are sourced, a time displays as the transactions per second (tps) was measured. This mechanism continues to count the time, giving you an estimate and then a total execution time at the end.

This tool offers a lot of customization and filters, such as tables, schemas, and replication_sets. LiveCompare can use stop-start without losing context information, so it can run at convenient times. After the comparison, a summary and a DML script are generated so you can review it. Apply the DML to fix any differences found.

Replicating between different release levels

The other difference between nodes that you might encounter is where there are different major versions of PostgreSQL on the nodes. PGD is designed to replicate between different major release versions. This feature is designed to allow major version upgrades without downtime.

PGD is also designed to replicate between nodes that have different versions of PGD software. This feature is designed to allow version upgrades and maintenance without downtime.

However, while it's possible to join a node with a major version in a cluster, you can't add a node with a minor version if the cluster uses a newer protocol version. Doing so returns an error.

Both of these features might be affected by specific restrictions. See Release notes for any known incompatibilities.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.4 General rules for applications

Background

PGD uses replica identity values to identify the rows to change. Applications can cause difficulties if they insert, delete, and then later reuse the same unique identifiers. This is known as the ABA problem. PGD can't know whether the rows are the current row, the last row, or much older rows.

Similarly, since PGD uses table names to identify the table against which changes are replayed, a similar ABA problem exists with applications that create, drop, and then later reuse the same object names.

Rules for applications

These issues give rise to some simple rules for applications to follow:

- Use unique identifiers for rows (INSERT).
- Avoid modifying unique identifiers (UPDATE).
- Avoid reusing deleted unique identifiers.
- Avoid reusing dropped object names.

In the general case, breaking those rules can lead to data anomalies and divergence. Applications can break those rules as long as certain conditions are met. However, use caution: while anomalies are unlikely, they aren't impossible. For example, you can reuse a row value as long as the DELETE was replayed on all nodes, including down nodes. This might normally occur in less than a second but can take days if a severe issue occurred on one node that prevented it from restarting correctly.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.5 Timing considerations and synchronous replication

Being asynchronous by default, peer nodes might lag behind. This behavior makes it possible for a client connected to multiple PGD nodes or switching between them to read stale data.

A queue wait function is provided for clients or proxies to prevent such stale reads.

The synchronous replication features of Postgres are available to PGD as well. In addition, PGD provides multiple variants for more synchronous replication. See Commit scopes for an overview and comparison of all variants available and their different modes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.6 Using extensions with PGD

PGD and other PostgreSQL extensions

PGD is implemented as a PostgreSQL extension (see Supported Postgres database servers). It takes advantage of PostgreSQL's expandability and flexibility to modify low-level system behavior to provide multi-master replication.

In principle, extensions provided by community PostgreSQL, EDB Postgres Advanced Server, and third-party extensions can be used with PGD. However, the distributed nature of PGD means that you need to carefully consider and plan the extensions you select and install.

Extensions providing logical decoding

Extensions providing logical decoding, such as wal2json, may in theory work with PGD. However, there's no support for failover, meaning any WAL stream being read from such an extension can be interrupted.

Extensions providing replication or HA functionality

Any extension extending PostgreSQL with functionality related to replication or HA/failover is unlikely to work well with PGD and may even be detrimental to the health of the PGD cluster. We recommend avoiding these.

Supported extensions

These extensions are explicitly supported by PGD.

EDB Advanced Storage table access methods

The EDB Advanced Storage Pack provides a selection of table access methods (TAMs) implemented as extensions. The following TAMs are certified for use with PGD:

- Autocluster
- Refdata

For more details, see Table access methods.

pgaudit

PGD was modified to ensure compatibility with the pgaudit extension. See Postgres settings for configuration information.

Installing extensions

PostgreSQL extensions provide SQL objects, such as functions, datatypes, and, optionally, one or more shared libraries. These must be loaded into the PostgreSQL backend before you can install and use the extension.

> **Warning**
>
> The relevant extension packages must be available on all nodes in the cluster. Otherwise extension installation can fail and impact cluster stability.

If PGD is deployed using Trusted Postgres Architect, configure extensions using that tool. For details, see Adding Postgres extensions.

The following is relevant for manually configured PGD installations.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Configuring shared_preload_libraries

If an extension provides a shared library, include this library in the `shared_preload_libraries` configuration parameter before installing the extension.

`shared_preload_libraries` consists of a comma-separated list of extension names. It must include `bdr`. The order in which you specify other extensions generally doesn't matter.

Configure `shared_preload_libraries` on all nodes in the cluster before installing the extension with `CREATE EXTENSION`. You must restart PostgreSQL to activate the new configuration.

See also Postgres settings.

Installing the extension

Install the extension using the `CREATE EXTENSION` command. You need to do this on only one node in the cluster. PGD's DDL replication will ensure that it propagates to all other nodes.

> **Warning**
>
> Do not attempt to install extensions manually on each node by, for example, disabling DDL replication before executing `CREATE EXTENSION`.
>
> Do not use a command such as `bdr.replicate_ddl_command()` to execute `CREATE EXTENSION`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.7 Use of table access methods (TAMs) in PGD

The EDB Advanced Storage Pack provides a selection of table access methods (TAMs), available from EDB Postgres 15.0.

The following TAMs were certified for use with PGD 5.0:

- Autocluster
- Refdata

Usage of any other TAM is restricted until certified by EDB.

To use one of these TAMs on a PGD cluster, the appropriate extension library (`autocluster` and/or `refdata`) must be added to the `shared_preload_libraries` parameter on each node, and the PostgreSQL server restarted.

Once the extension library is present in `shared_preload_libraries` on all nodes in the cluster, the extension itself can be created with `CREATE EXTENSION autocluster;` or `CREATE EXTENSION refdata;` . The `CREATE EXTENSION` command only needs to be executed on one node; it will be replicated to the other nodes in the cluster.

After you create the extension, use `CREATE TABLE test USING autocluster;` or `CREATE TABLE test USING refdata;` to create a table with the specified TAM. These commands replicate to all PGD nodes in the cluster.

For more information on these table access methods, see:

- Autocluster example
- Refdata example

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

10.8 Feature compatibility

Server feature/commit scope interoperability

Not all server features work with all commit scopes. This table shows the ones that interoperate.

	Async (default)	Parallel Apply	Transaction Streaming	Single Decoding Worker
Group Commit				
CAMO				
Lag Control				
Synchronous Commit				

Legend: Not applicable | Does not interoperate | Interoperates

Notes

: The Async column in the table represents PGD without a synchronous commit scope in use. Lag Control isn't a synchronous commit scope. It's a controlling commit scope and is therefore available with asynchronous operations.

: Attempting to use Group Commit and Transaction Streaming presents a warning. The warning suggests that you disable transaction streaming, and the transaction appears to take place. In the background, Group Commit was disabled to allow the transaction to occur.

Commit scope/commit scope interoperability

Although you can't mix commit scopes, you can combine rules with an `AND` operator. This table shows where commit scopes can be combined.

	Group Commit	CAMO	Lag Control	Synchronous Commit
Group Commit				
CAMO				
Lag Control				
Synchronous Commit				

Legend: Not applicable | Does not combine | Combines

Notes

Each commit scope implicitly works with itself.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11 DDL replication

DDL stands for data definition language, the subset of the SQL language that creates, alters, and drops database objects.

PGD provides automatic DDL replication, which makes certain DDL changes easier. With automatic replication, you don't have to manually distribute the DDL change to all nodes and ensure that they're consistent.

This section looks at how DDL replication is handled in PGD.

- Overview provides a general outline of what PGD's DDL replication is capable of.
- Replication options looks at the options for controlling replication.
- Locking examines how DDL replication uses locks to safely replicate DDL.
- Managing DDL with PGD replication gives best practice advice on why and how to limit the impact of DDL changes so they don't overly affect the smooth running of the cluster.
- Command handling is a reference to all DDL commands, the locks they take, and any special handling involved in their use and execution.
- DDL role manipulation notes issues around manipulating roles over multiple databases in a cluster.
- Workarounds gives a range of options for handling situations where DDL replication may present restrictions, such as altering columns, constraints, and types.
- DDL-like PGD functions details the PGD functions that behave like DDL and therefore behave in a similar way and are subject to similar restrictions.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.1 DDL overview

DDL stands for data definition language, the subset of the SQL language that creates, alters, and drops database objects.

Replicated DDL

For operational convenience and correctness, PGD replicates most DDL actions, with these exceptions:

- Temporary relations
- Certain DDL statements (mostly long running)
- Locking commands (`LOCK`)
- Table maintenance commands (`VACUUM` , `ANALYZE` , `CLUSTER`)
- Actions of autovacuum
- Operational commands (`CHECKPOINT` , `ALTER SYSTEM`)
- Actions related to databases or tablespaces

Automatic DDL replication makes certain DDL changes easier without having to manually distribute the DDL change to all nodes and ensure that they're consistent.

In the default replication set, DDL is replicated to all nodes by default.

Differences from PostgreSQL

PGD is significantly different from standalone PostgreSQL when it comes to DDL replication. Treating it the same is the most common issue with PGD.

The main difference from table replication is that DDL replication doesn't replicate the result of the DDL. Instead, it replicates the statement. This works very well in most cases, although it introduces the requirement that the DDL must execute similarly on all nodes. A more subtle point is that the DDL must be immutable with respect to all datatype-specific parameter settings, including any datatypes introduced by extensions (not built in). For example, the DDL statement must execute correctly in the default encoding used on each node.

Executing DDL on PGD systems

A PGD group isn't the same as a standalone PostgreSQL server. It's based on asynchronous multi-master replication without central locking and without a transaction coordinator. This has important implications when executing DDL.

DDL that executes in parallel continues to do so with PGD. DDL execution respects the parameters that affect parallel operation on each node as it executes, so you might notice differences in the settings between nodes.

Prevent the execution of conflicting DDL, otherwise DDL replication causes errors and the replication stops.

PGD offers three levels of protection against those problems:

`ddl_locking = 'all'` is the strictest option and is best when DDL might execute from any node concurrently and you want to ensure correctness. This is the default.

`ddl_locking = 'dml'` is an option that is safe only when you execute DDL from one node at any time. Use this setting only if you can completely control where DDL is executed. Executing DDL from a single node ensures that there are no inter-node conflicts. Intra-node conflicts are already handled by PostgreSQL.

`ddl_locking = 'off'` is the least strict option and is dangerous in general use. This option skips locks altogether, avoiding any performance overhead, which makes it a useful option when creating a new and empty database schema.

These options can be set only by the bdr_superuser, by the superuser, or in the `postgres.conf` configuration file.

When using the `bdr.replicate_ddl_command` , you can set this parameter directly with the third argument, using the specified `bdr.ddl_locking` setting only for the DDL commands passed to that function.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

DDL and mixed PostgreSQL versions

PGD does not support DDL replication between different major Postgres versions in a cluster. Most of the time, this is not an issue because clusters will be running the same major version of Postgres. This is not the case though when performing a rolling upgrade of a cluster from one major version to another. In this case, DDL replication is not supported until all nodes have been upgraded to the same major version and should not be used.

Special care should be taken in the upgrade process when updating extensions as the scripts may trigger DDL replication. In this case, if the scripts must be run before upgrading is complete, `bdr.ddl_replication` setting should be set to `off` while running the script. See the Rolling upgrade guide for more information on how to perform a rolling upgrade of a PGD cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.2 DDL replication options

The `bdr.ddl_replication` parameter specifies replication behavior.

`bdr.ddl_replication = on` is the default. This setting replicates DDL to the default replication set, which by default means all nodes. Non-default replication sets don't replicate DDL unless they have a DDL filter defined for them.

You can also replicate DDL to specific replication sets using the function `bdr.replicate_ddl_command()`. This function can be helpful if you want to run DDL commands when a node is down. It's also helpful if you want to have indexes or partitions that exist on a subset of nodes or rep sets, for example, all nodes at site1.

```
SELECT bdr.replicate_ddl_command(
                'CREATE INDEX CONCURRENTLY ON foo (col7);',
                ARRAY['site1'],     -- the replication sets
                'all');              -- ddl_locking to apply
```

While we don't recommend it, you can skip automatic DDL replication and execute it manually on each node using the `bdr.ddl_replication` configuration parameter.

```
SET bdr.ddl_replication = off;
```

When set, it makes PGD skip both the global locking and the replication of executed DDL commands. You must then run the DDL manually on all nodes.

> **Warning**
>
> Executing DDL manually on each node without global locking can cause the whole PGD group to stop replicating if conflicting DDL or DML executes concurrently.

Only the bdr_superuser or superuser can set the `bdr.ddl_replication` parameter. It can also be set in the `postgres.conf` configuration file.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.3 DDL locking details

Two kinds of locks enforce correctness of replicated DDL with PGD: the global DDL lock and the global DML lock.

The global DDL lock

A global DDL lock is used only when `ddl_locking = 'all'`. This kind of lock prevents any other DDL from executing on the cluster while each DDL statement runs. This behavior ensures full correctness in the general case but is too strict for many simple cases. PGD acquires a global lock on DDL operations the first time in a transaction where schema changes are made. This effectively serializes the DDL-executing transactions in the cluster. In other words, while DDL is running, no other connection on any node can run another DDL command, even if it affects different tables.

To acquire a lock on DDL operations, the PGD node executing DDL contacts the other nodes in a PGD group and asks them to grant it the exclusive right to execute DDL.

The lock request is sent by the regular replication stream, and the nodes respond by the replication stream as well. So it's important that nodes (or at least a majority of the nodes) run without much replication delay. Otherwise it might take a long time for the node to acquire the DDL lock. Once the majority of nodes agree, the DDL execution is carried out.

The ordering of DDL locking is decided using the Raft protocol. DDL statements executed on one node are executed in the same sequence on all other nodes.

To ensure that the node running a DDL has seen effects of all prior DDLs run in the cluster, it waits until it catches up with the node that ran the previous DDL. If the node running the current DDL is lagging behind in replication with respect to the node that ran the previous DDL, then it might take a long time to acquire the lock. Hence it's preferable to run DDLs from a single node or the nodes that have nearly caught up with replication changes originating at other nodes.

A global DDL lock must be granted by a majority of data and witness nodes, where a majority is N/2+1 of the eligible nodes. Subscriber-only nodes aren't eligible to participate.

The global DML lock

Known as a global DML lock or relation DML lock, this kind of lock is used when either `ddl_locking = all` or `ddl_locking = dml`, and the DDL statement might cause in-flight DML statements to fail. These failures can occur when you add or modify a constraint, such as a unique constraint, check constraint, or NOT NULL constraint. Relation DML locks affect only one relation at a time. These locks ensure that no DDL executes while changes are in the queue that might cause replication to halt with an error.

To acquire the global DML lock on a table, the PGD node executing the DDL contacts all other nodes in a PGD group, asking them to lock the table against writes and waiting while all pending changes to that table are drained. Once all nodes are fully caught up, the originator of the DML lock is free to perform schema changes to the table and replicate them to the other nodes.

The global DML lock holds an EXCLUSIVE LOCK on the table on each node, so it blocks DML, other DDL, VACUUM, and index commands against that table while it runs. This is true even if the global DML lock is held for a command that normally doesn't take an EXCLUSIVE LOCK or higher.

Waiting for pending DML operations to drain can take a long time and even longer if replication is currently lagging. This means that, unlike with data changes, schema changes affecting row representation and constraints can be performed only while all configured nodes can be reached and are keeping up reasonably well with the current write rate. If such DDL commands must be performed while a node is down, first remove the down node from the configuration.

All eligible data nodes must agree to grant a global DML lock before the lock is granted. Witness and subscriber-only nodes aren't eligible to participate.

If a DDL statement isn't replicated, no global locks are acquired.

Specify locking behavior with the `bdr.ddl_locking` parameter, as explained in Executing DDL on PGD systems:

- `ddl_locking = all` takes global DDL lock and, if needed, takes relation DML lock.
- `ddl_locking = dml` skips global DDL lock and, if needed, takes relation DML lock.
- `ddl_locking = off` skips both global DDL lock and relation DML lock.

Some PGD functions make DDL changes. For those functions, DDL locking behavior applies, which is noted in the documentation for each function.

Thus, `ddl_locking = dml` is safe only when you can guarantee that no conflicting DDL is executed from other nodes. With this setting, the statements that require only the global DDL lock don't use the global locking at all.

`ddl_locking = off` is safe only when you can guarantee that there are no conflicting DDL and no conflicting DML operations on the database objects DDL executes on. If you turn locking off and then experience difficulties, you might lose in-flight changes to data. The user application team needs to resolve any issues caused.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

In some cases, concurrently executing DDL can properly be serialized. If these serialization failures occur, the DDL might reexecute.

DDL replication isn't active on logical standby nodes until they're promoted.

Some PGD management functions act like DDL, meaning that they attempt to take global locks, and their actions are replicated if DDL replication is active. The full list of replicated functions is listed in PGD functions that behave like DDL.

DDL executed on temporary tables never need global locks.

ALTER or DROP of an object created in the current transaction doesn't required global DML lock.

Monitoring of global DDL locks and global DML locks is shown in Monitoring.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.4 Managing DDL with PGD replication

Minimizing the impact of DDL

Minimizing the impact of DDL is good operational advice for any database. These points become even more important with PGD:

- To minimize the impact of DDL, make transactions performing DDL short. Don't combine them with lots of row changes, and avoid long-running foreign key or other constraint rechecks.
- For `ALTER TABLE`, use `ADD CONSTRAINT NOT VALID` followed by another transaction with `VALIDATE CONSTRAINT` rather than using `ADD CONSTRAINT` alone. `VALIDATE CONSTRAINT` waits until replayed on all nodes, which gives a noticeable delay to receive confirmations.
- When indexing, use the `CONCURRENTLY` option whenever possible.

An alternative way of executing long-running DDL is to disable DDL replication and then to execute the DDL statement separately on each node. You can still do this using a single SQL statement, as shown in the following example. Global locking rules still apply, so be careful not to lock yourself out with this type of usage, which is more of a workaround.

```
SELECT
bdr.run_on_all_nodes($ddl$
        CREATE INDEX CONCURRENTLY index_a ON
table_a(i);
$ddl$);
```

We recommend using the `bdr.run_on_all_nodes()` technique with `CREATE INDEX CONCURRENTLY`, noting that DDL replication must be disabled for the whole session because `CREATE INDEX CONCURRENTLY` is a multi-transaction command. Avoid `CREATE INDEX` on production systems since it prevents writes while it executes. `REINDEX` is replicated in versions 3.6 and earlier but not with PGD 3.7 or later. Avoid using `REINDEX` because of the AccessExclusiveLocks it holds.

Instead, use `REINDEX CONCURRENTLY` (or `reindexdb --concurrently`), which is available in PG12+ or 2QPG11+.

You can disable DDL replication when using command-line utilities like this:

```
$ export PGOPTIONS="-c
bdr.ddl_replication=off"
$ pg_restore --section=post-data
```

Multiple DDL statements might benefit from bunching into a single transaction rather than fired as individual statements, so take the DDL lock only once. This might not be desirable if the table-level locks interfere with normal operations.

If DDL is holding up the system for too long, you can safely cancel the DDL on the originating node with **Control-C** in psql or with `pg_cancel_backend()`. You can't cancel a DDL lock from any other node.

You can control how long the global lock takes with optional global locking timeout settings. `bdr.global_lock_timeout` limits how long the wait for acquiring the global lock can take before it's canceled. `bdr.global_lock_statement_timeout` limits the runtime length of any statement in transaction that holds global locks, and `bdr.global_lock_idle_timeout` sets the maximum allowed idle time (time between statements) for a transaction holding any global locks. You can disable all of these timeouts by setting their values to zero.

Once the DDL operation has committed on the originating node, you can't cancel or abort it. The PGD group must wait for it to apply successfully on other nodes that confirmed the global lock and for them to acknowledge replay. For this reason, keep DDL transactions short and fast.

Handling DDL with down nodes

If the node initiating the global DDL lock goes down after it acquired the global lock (either DDL or DML), the lock stays active. The global locks don't time out, even if timeouts were set. In case the node comes back up, it releases all the global locks that it holds.

If it stays down for a long time or indefinitely, remove the node from the PGD group to release the global locks. This is one reason for executing emergency DDL using the `SET` command as the bdr_superuser to update the `bdr.ddl_locking` value.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

If one of the other nodes goes down after it confirmed the global lock but before the command acquiring it executed, the execution of that command requesting the lock continues as if the node were up.

As mentioned earlier, the global DDL lock requires only a majority of the nodes to respond, and so it works if part of the cluster is down, as long as a majority is running and reachable. But the DML lock can't be acquired unless the whole cluster is available.

With global DDL or global DML lock, if another node goes down, the command continues normally, and the lock is released.

Statement-specific DDL replication concerns

Not all commands can be replicated automatically. Such commands are generally disallowed, unless DDL replication is turned off by turning `bdr.ddl_replication` off.

PGD prevents some DDL statements from running when it's active on a database. This protects the consistency of the system by disallowing statements that can't be replicated correctly or for which replication isn't yet supported.

If a statement isn't permitted under PGD, you can often find another way to do the same thing. For example, you can't do an `ALTER TABLE`, which adds a column with a volatile default value. But generally you can rephrase that as a series of independent `ALTER TABLE` and `UPDATE` statements that work.

Generally, unsupported statements are prevented from executing, raising a `feature_not_supported` (SQLSTATE `0A000`) error.

Any DDL that references or relies on a temporary object can't be replicated by PGD and throws an error if executed with DDL replication enabled.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.5 DDL command handling matrix

The following table describes the utility or DDL commands that are allowed, the ones that are replicated, and the type of global lock they take when they're replicated.

For some more complex statements like `ALTER TABLE`, these can differ depending on the subcommands executed. Every such command has detailed explanation under the following table.

Command matrix

Command	Allowed	Replicated	Lock
ALTER AGGREGATE	Y	Y	DDL
ALTER CAST	Y	Y	DDL
ALTER COLLATION	Y	Y	DDL
ALTER CONVERSION	Y	Y	DDL
ALTER DATABASE	Y	N	N
ALTER DATABASE LINK	Y	Y	DDL
ALTER DEFAULT PRIVILEGES	Y	Y	DDL
ALTER DIRECTORY	Y	Y	DDL
ALTER DOMAIN	Y	Y	DDL
ALTER EVENT TRIGGER	Y	Y	DDL
ALTER EXTENSION	Y	Y	DDL
ALTER FOREIGN DATA WRAPPER	Y	Y	DDL
ALTER FOREIGN TABLE	Y	Y	DDL
ALTER FUNCTION	Y	Y	DDL
ALTER INDEX	Y	Y	DDL
ALTER LANGUAGE	Y	Y	DDL
ALTER LARGE OBJECT	N	N	N
ALTER MATERIALIZED VIEW	Y	N	N
ALTER OPERATOR	Y	Y	DDL
ALTER OPERATOR CLASS	Y	Y	DDL
ALTER OPERATOR FAMILY	Y	Y	DDL
ALTER PACKAGE	Y	Y	DDL
ALTER POLICY	Y	Y	DDL
ALTER PROCEDURE	Y	Y	DDL
ALTER PROFILE	Y	Y	Details
ALTER PUBLICATION	Y	Y	DDL
ALTER QUEUE	Y	Y	DDL
ALTER QUEUE TABLE	Y	Y	DDL
ALTER REDACTION POLICY	Y	Y	DDL
ALTER RESOURCE GROUP	Y	N	N
ALTER ROLE	Y	Y	DDL
ALTER ROUTINE	Y	Y	DDL
ALTER RULE	Y	Y	DDL
ALTER SCHEMA	Y	Y	DDL
ALTER SEQUENCE	Details	Y	DML
ALTER SERVER	Y	Y	DDL
ALTER SESSION	Y	N	N
ALTER STATISTICS	Y	Y	DDL
ALTER SUBSCRIPTION	Y	Y	DDL
ALTER SYNONYM	Y	Y	DDL

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Command	Allowed	Replicated	Lock
ALTER SYSTEM	Y	N	N
ALTER TABLE	Details	Y	Details
ALTER TABLESPACE	Y	N	N
ALTER TEXT SEARCH CONFIGURATION	Y	Y	DDL
ALTER TEXT SEARCH DICTIONARY	Y	Y	DDL
ALTER TEXT SEARCH PARSER	Y	Y	DDL
ALTER TEXT SEARCH TEMPLATE	Y	Y	DDL
ALTER TRIGGER	Y	Y	DDL
ALTER TYPE	Y	Y	DDL
ALTER USER MAPPING	Y	Y	DDL
ALTER VIEW	Y	Y	DDL
ANALYZE	Y	N	N
BEGIN	Y	N	N
CHECKPOINT	Y	N	N
CLOSE	Y	N	N
CLOSE CURSOR	Y	N	N
CLOSE CURSOR ALL	Y	N	N
CLUSTER	Y	N	N
COMMENT	Y	Details	DDL
COMMIT	Y	N	N
COMMIT PREPARED	Y	N	N
COPY	Y	N	N
COPY FROM	Y	N	N
CREATE ACCESS METHOD	Y	Y	DDL
CREATE AGGREGATE	Y	Y	DDL
CREATE CAST	Y	Y	DDL
CREATE COLLATION	Y	Y	DDL
CREATE CONSTRAINT	Y	Y	DDL
CREATE CONVERSION	Y	Y	DDL
CREATE DATABASE	Y	N	N
CREATE DATABASE LINK	Y	Y	DDL
CREATE DIRECTORY	Y	Y	DDL
CREATE DOMAIN	Y	Y	DDL
CREATE EVENT TRIGGER	Y	Y	DDL
CREATE EXTENSION	Y	Y	DDL
CREATE FOREIGN DATA WRAPPER	Y	Y	DDL
CREATE FOREIGN TABLE	Y	Y	DDL
CREATE FUNCTION	Y	Y	DDL
CREATE INDEX	Y	Y	DML
CREATE LANGUAGE	Y	Y	DDL
CREATE MATERIALIZED VIEW	Y	N	N
CREATE OPERATOR	Y	Y	DDL
CREATE OPERATOR CLASS	Y	Y	DDL
CREATE OPERATOR FAMILY	Y	Y	DDL
CREATE PACKAGE	Y	Y	DDL
CREATE PACKAGE BODY	Y	Y	DDL
CREATE POLICY	Y	Y	DML
CREATE PROCEDURE	Y	Y	DDL
CREATE PROFILE	Y	Y	Details

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Command	Allowed	Replicated	Lock
CREATE PUBLICATION	Y	Y	DDL
CREATE QUEUE	Y	Y	DDL
CREATE QUEUE TABLE	Y	Y	DDL
CREATE REDACTION POLICY	Y	Y	DDL
CREATE RESOURCE GROUP	Y	N	N
CREATE ROLE	Y	Y	DDL
CREATE ROUTINE	Y	Y	DDL
CREATE RULE	Y	Y	DDL
CREATE SCHEMA	Y	Y	DDL
CREATE SEQUENCE	Details	Y	DDL
CREATE SERVER	Y	Y	DDL
CREATE STATISTICS	Y	Y	DDL
CREATE SUBSCRIPTION	Y	Y	DDL
CREATE SYNONYM	Y	Y	DDL
CREATE TABLE	Y	Y	DDL
CREATE TABLE AS	Details	Y	DDL
CREATE TABLESPACE	Y	N	N
CREATE TEXT SEARCH CONFIGURATION	Y	Y	DDL
CREATE TEXT SEARCH DICTIONARY	Y	Y	DDL
CREATE TEXT SEARCH PARSER	Y	Y	DDL
CREATE TEXT SEARCH TEMPLATE	Y	Y	DDL
CREATE TRANSFORM	Y	Y	DDL
CREATE TRIGGER	Y	Y	DDL
CREATE TYPE	Y	Y	DDL
CREATE TYPE BODY	Y	Y	DDL
CREATE USER MAPPING	Y	Y	DDL
CREATE VIEW	Y	Y	DDL
DEALLOCATE	Y	N	N
DEALLOCATE ALL	Y	N	N
DECLARE CURSOR	Y	N	N
DISCARD	Y	N	N
DISCARD ALL	Y	N	N
DISCARD PLANS	Y	N	N
DISCARD SEQUENCES	Y	N	N
DISCARD TEMP	Y	N	N
DO	Y	N	N
DROP ACCESS METHOD	Y	Y	DDL
DROP AGGREGATE	Y	Y	DDL
DROP CAST	Y	Y	DDL
DROP COLLATION	Y	Y	DDL
DROP CONSTRAINT	Y	Y	DDL
DROP CONVERSION	Y	Y	DDL
DROP DATABASE	Y	N	N
DROP DATABASE LINK	Y	Y	DDL
DROP DIRECTORY	Y	Y	DDL
DROP DOMAIN	Y	Y	DDL
DROP EVENT TRIGGER	Y	Y	DDL
DROP EXTENSION	Y	Y	DDL
DROP FOREIGN DATA WRAPPER	Y	Y	DDL

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Command	Allowed	Replicated	Lock
DROP FOREIGN TABLE	Y	Y	DDL
DROP FUNCTION	Y	Y	DDL
DROP INDEX	Y	Y	DDL
DROP LANGUAGE	Y	Y	DDL
DROP MATERIALIZED VIEW	Y	N	N
DROP OPERATOR	Y	Y	DDL
DROP OPERATOR CLASS	Y	Y	DDL
DROP OPERATOR FAMILY	Y	Y	DDL
DROP OWNED	Y	Y	DDL
DROP PACKAGE	Y	Y	DDL
DROP PACKAGE BODY	Y	Y	DDL
DROP POLICY	Y	Y	DDL
DROP PROCEDURE	Y	Y	DDL
DROP PROFILE	Y	Y	DDL
DROP PUBLICATION	Y	Y	DDL
DROP QUEUE	Y	Y	DDL
DROP QUEUE TABLE	Y	Y	DDL
DROP REDACTION POLICY	Y	Y	DDL
DROP RESOURCE GROUP	Y	N	N
DROP ROLE	Y	Y	DDL
DROP ROUTINE	Y	Y	DDL
DROP RULE	Y	Y	DDL
DROP SCHEMA	Y	Y	DDL
DROP SEQUENCE	Y	Y	DDL
DROP SERVER	Y	Y	DDL
DROP STATISTICS	Y	Y	DDL
DROP SUBSCRIPTION	Y	Y	DDL
DROP SYNONYM	Y	Y	DDL
DROP TABLE	Y	Y	DML
DROP TABLESPACE	Y	N	N
DROP TEXT SEARCH CONFIGURATION	Y	Y	DDL
DROP TEXT SEARCH DICTIONARY	Y	Y	DDL
DROP TEXT SEARCH PARSER	Y	Y	DDL
DROP TEXT SEARCH TEMPLATE	Y	Y	DDL
DROP TRANSFORM	Y	Y	DDL
DROP TRIGGER	Y	Y	DDL
DROP TYPE	Y	Y	DDL
DROP TYPE BODY	Y	Y	DDL
DROP USER MAPPING	Y	Y	DDL
DROP VIEW	Y	Y	DDL
EXECUTE	Y	N	N
EXPLAIN	Y	Details	Details
FETCH	Y	N	N
GRANT	Y	Details	DDL
GRANT ROLE	Y	Y	DDL
IMPORT FOREIGN SCHEMA	Y	Y	DDL
LISTEN	Y	N	N
LOAD	Y	N	N
LOAD ROW DATA	Y	Y	DDL

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Command	Allowed	Replicated	Lock
LOCK TABLE	Y	N	Details
MOVE	Y	N	N
NOTIFY	Y	N	N
PREPARE	Y	N	N
PREPARE TRANSACTION	Y	N	N
REASSIGN OWNED	Y	Y	DDL
REFRESH MATERIALIZED VIEW	Y	N	N
REINDEX	Y	Y	DDL
RELEASE	Y	N	N
RESET	Y	N	N
REVOKE	Y	Details	DDL
REVOKE ROLE	Y	Y	DDL
ROLLBACK	Y	N	N
ROLLBACK PREPARED	Y	N	N
SAVEPOINT	Y	N	N
SECURITY LABEL	Y	Details	DDL
SELECT INTO	Details	Y	DDL
SET	Y	N	N
SET CONSTRAINTS	Y	N	N
SHOW	Y	N	N
START TRANSACTION	Y	N	N
TRUNCATE TABLE	Y	Details	Details
UNLISTEN	Y	N	N
VACUUM	Y	N	N

Command notes

ALTER SEQUENCE

Generally `ALTER SEQUENCE` is supported, but when using global sequences, some options have no effect.

`ALTER SEQUENCE ... RENAME` isn't supported on galloc sequences (only). `ALTER SEQUENCE ... SET SCHEMA` isn't supported on galloc sequences (only).

ALTER TABLE

Generally, `ALTER TABLE` commands are allowed. However, several subcommands aren't supported.

ALTER TABLE disallowed commands

Some variants of `ALTER TABLE` currently aren't allowed on a PGD node:

- `ADD COLUMN ... DEFAULT (non-immutable expression)` — This is not allowed because it currently results in different data on different nodes. See Adding a column for a suggested workaround. You can override this behavior using `bdr.permit_unsafe_commands` if you're sure the command is safe.
- `ALTER COLUMN ... SET STORAGE external` — Is rejected if the column is one of the columns of the replica identity for the table. You can override this behavior using `bdr.permit_unsafe_commands` if you're sure the command is safe.
- `RENAME` — Can't rename an Autopartitioned table.
- `SET SCHEMA` — Can't set the schema of an Autopartitioned table.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- `ALTER COLUMN ... TYPE` — Changing a column's type isn't supported if the command causes the whole table to be rewritten, which occurs when the change isn't binary coercible. Binary coercible changes might be allowed only one way. For example, the change from `VARCHAR(128)` to `VARCHAR(256)` is binary coercible and therefore allowed, whereas the change `VARCHAR(256)` to `VARCHAR(128)` isn't binary coercible and therefore normally disallowed. Nonreplicated `ALTER COLUMN ... TYPE`, can be allowed if the column is automatically castable to the new type (it doesn't contain the `USING` clause). An example follows. Table rewrites hold an AccessExclusiveLock for extended periods on larger tables, so such commands are likely to be infeasible on highly available databases in any case. See Changing a column's type for a suggested workaround. This can be overriden using `bdr.permit_unsafe_commands` if user is sure the command is safe.
- `ALTER TABLE ... ADD FOREIGN KEY` — Isn't supported if current user doesn't have permission to read the referenced table or if the referenced table has RLS restrictions enabled that the current user can't bypass.

The following example fails because it tries to add a constant value of type `timestamp` onto a column of type `timestamptz`. The cast between `timestamp` and `timestamptz` relies on the time zone of the session and so isn't immutable.

```
ALTER TABLE
foo
  ADD expiry_date timestamptz DEFAULT timestamp '2100-01-01 00:00:00' NOT
NULL;
```

Starting in PGD 3.7.4, you can add certain types of constraints, such as `CHECK` and `FOREIGN KEY` constraints, without taking a DML lock. But this requires a two-step process of first creating a `NOT VALID` constraint and then validating the constraint in a separate transaction with the `ALTER TABLE ... VALIDATE CONSTRAINT` command. See Adding a CONSTRAINT for more details.

ALTER TABLE locking

The following variants of `ALTER TABLE` take only DDL lock and not a DML lock:

- `ALTER TABLE ... ADD COLUMN ... (immutable) DEFAULT`
- `ALTER TABLE ... ALTER COLUMN ... SET DEFAULT expression`
- `ALTER TABLE ... ALTER COLUMN ... DROP DEFAULT`
- `ALTER TABLE ... ALTER COLUMN ... TYPE` if it doesn't require rewrite
- `ALTER TABLE ... ALTER COLUMN ... SET STATISTICS`
- `ALTER TABLE ... VALIDATE CONSTRAINT`
- `ALTER TABLE ... ATTACH PARTITION`
- `ALTER TABLE ... DETACH PARTITION`
- `ALTER TABLE ... ENABLE TRIGGER` (`ENABLE REPLICA TRIGGER` still takes a DML lock)
- `ALTER TABLE ... CLUSTER ON`
- `ALTER TABLE ... SET WITHOUT CLUSTER`
- `ALTER TABLE ... SET ( storage_parameter = value [, ... ] )`
- `ALTER TABLE ... RESET ( storage_parameter = [, ... ] )`
- `ALTER TABLE ... OWNER TO`

All other variants of `ALTER TABLE` take a DML lock on the table being modified. Some variants of `ALTER TABLE` have restrictions, noted below.

ALTER TABLE examples

This next example works because the type change is binary coercible and so doesn't cause a table rewrite. It executes as a catalog-only change.

```
CREATE TABLE foo (id BIGINT PRIMARY KEY, description
VARCHAR(20));
ALTER TABLE foo ALTER COLUMN description TYPE
VARCHAR(128);
```

However, making this change to reverse the command isn't possible because the change from `VARCHAR(128)` to `VARCHAR(20)` isn't binary coercible.

```
ALTER TABLE foo ALTER COLUMN description TYPE
VARCHAR(20);
```

For workarounds, see Restricted DDL workarounds.

It's useful to provide context for different types of `ALTER TABLE ... ALTER COLUMN TYPE` (ATCT) operations that are possible in general and in nonreplicated environments.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Some ATCT operations update only the metadata of the underlying column type and don't require a rewrite of the underlying table data. This is typically the case when the existing column type and the target type are binary coercible. For example:

```
CREATE TABLE sample (col1 BIGINT PRIMARY KEY, col2 VARCHAR(128), col3
INT);
ALTER TABLE sample ALTER COLUMN col2 TYPE VARCHAR(256);
```

You can also change the column type to `VARCHAR` or `TEXT` data types because of binary coercibility. Again, this is just a metadata update of the underlying column type.

```
ALTER TABLE sample ALTER COLUMN col2 TYPE VARCHAR;
ALTER TABLE sample ALTER COLUMN col2 TYPE TEXT;
```

However, if you want to reduce the size of col2, then that leads to a rewrite of the underlying table data. Rewrite of a table is normally restricted.

```
ALTER TABLE sample ALTER COLUMN col2 TYPE VARCHAR(64);
ERROR:  ALTER TABLE ... ALTER COLUMN TYPE that rewrites table data may not affect replicated tables on a PGD
node
```

To give an example with nontext types, consider col3 above with type INTEGER. An ATCT operation that tries to convert to SMALLINT or BIGINT fails in a similar manner as above.

```
ALTER TABLE sample ALTER COLUMN col3 TYPE bigint;
ERROR:  ALTER TABLE ... ALTER COLUMN TYPE that rewrites table data may not affect replicated tables on a PGD
node
```

In both of these failing cases, there's an automatic assignment cast from the current types to the target types. However, there's no binary coercibility, which ends up causing a rewrite of the underlying table data.

In such cases, in controlled DBA environments, you can change the type of a column to an automatically castable one by adopting a rolling upgrade for the type of this column in a nonreplicated environment on all the nodes, one by one. Suppose the DDL isn't replicated and the change of the column type is to an automatically castable one. You can then allow the rewrite locally on the node performing the alter, along with concurrent activity on other nodes on this same table. You can then repeat this nonreplicated ATCT operation on all the nodes one by one to bring about the desired change of the column type across the entire EDB Postgres Distributed cluster. Because this involves a rewrite, the activity still takes the DML lock for a brief period and thus requires that the whole cluster is available. With these specifics in place, you can carry out the rolling upgrade of the nonreplicated alter activity like this:

```
-- foreach node in EDB Postgres Distributed cluster
do:
SET bdr.ddl_replication TO
FALSE;
ALTER TABLE sample ALTER COLUMN col2 TYPE VARCHAR(64);
ALTER TABLE sample ALTER COLUMN col3 TYPE BIGINT;
RESET bdr.ddl_replication;
-- done
```

Due to automatic assignment casts being available for many data types, this local nonreplicated ATCT operation supports a wide variety of conversions. Also, ATCT operations that use a `USING` clause are likely to fail because of the lack of automatic assignment casts. This example shows a few common conversions with automatic assignment casts:

```
-- foreach node in EDB Postgres Distributed cluster
do:
SET bdr.ddl_replication TO
FALSE;
ATCT operations to-from {INTEGER, SMALLINT,
BIGINT}
ATCT operations to-from {CHAR(n), VARCHAR(n), VARCHAR,
TEXT}
ATCT operations from numeric types to text types
RESET bdr.ddl_replication;
-- done
```

This example isn't an exhaustive list of possibly allowable ATCT operations in a nonreplicated environment. Not all ATCT operations work. The cases where no automatic assignment is possible fail even if you disable DDL replication. So, while conversion from numeric types to text types works in a nonreplicated environment, conversion back from text type to numeric types fails.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
SET bdr.ddl_replication TO
FALSE;
-- conversion from BIGINT to TEXT
works
ALTER TABLE sample ALTER COLUMN col3 TYPE TEXT;
-- conversion from TEXT back to BIGINT
fails
ALTER TABLE sample ALTER COLUMN col3 TYPE BIGINT;
ERROR:  ALTER TABLE ... ALTER COLUMN TYPE which cannot be automatically cast to new type may not affect replicated
tables on a PGD node
RESET bdr.ddl_replication;
```

While the ATCT operations in nonreplicated environments support a variety of type conversions, the rewrite can still fail if the underlying table data contains values that you can't assign to the new data type. For example, suppose the current type for a column is `VARCHAR(256)` and you try a nonreplicated ATCT operation to convert it into `VARCHAR(128)`. If there's any existing data in the table that's wider than 128 bytes, then the rewrite operation fails locally.

```
INSERT INTO sample VALUES (1, repeat('a', 200),
10);
SET bdr.ddl_replication TO
FALSE;
ALTER TABLE sample ALTER COLUMN col2 TYPE VARCHAR(128);
INFO:  in rewrite
ERROR:  value too long for type character
varying(128)
```

If underlying table data meets the characteristics of the new type, then the rewrite succeeds. However, replication might fail if other nodes that haven't yet performed the nonreplicated rolling data type upgrade introduce new data that is wider than 128 bytes concurrently to this local ATCT operation. This brings replication to a halt in the cluster. So be aware of the data type restrictions and characteristics at the database and application levels while performing these nonreplicated rolling data type upgrade operations. We strongly recommend that you perform and test such ATCT operations in controlled and fully aware DBA environments. These ATCT operations are asymmetric, and backing out certain changes that fail can lead to table rewrites that take a long time.

Also, you can't perform the implicit castable ALTER activity in transaction blocks.

ALTER TYPE

`ALTER TYPE` is replicated, but a global DML lock isn't applied to all tables that use that data type, since PostgreSQL doesn't record those dependencies. See Restricted DDL workarounds.

COMMENT ON

All variants of `COMMENT ON` are allowed, but `COMMENT ON TABLESPACE/DATABASE/LARGE OBJECT` isn't replicated.

CREATE PROFILE or ALTER PROFILE

The `PASSWORD_VERIFY_FUNCTION` associated with the profile should be `IMMUTABLE` if the function is `SECURITY DEFINER`. Such a `CREATE PROFILE` or `ALTER PROFILE` command will be replicated but subsequent `CREATE USER` or `ALTER USER` commands using this profile will break the replication due to the `writer` worker throwing the error: `cannot change current role within security-restricted operation`.

> **Note**
>
> PGD doesn't execute `PASSWORD_VERIFY_FUNCTION` on witness servers, since database objects aren't replicated to these servers. The origin node already executed the function and verified the password, so a duplicate check on the witness is redundant.
>
> To run `PASSWORD_VERIFY_FUNCTION` on a witness server anyway, create the function manually there, then run `CREATE PROFILE` or `ALTER PROFILE` directly on the witness server.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

CREATE SEQUENCE

Generally `CREATE SEQUENCE` is supported, but when using global sequences, some options have no effect.

CREATE TABLE AS and SELECT INTO

`CREATE TABLE AS` and `SELECT INTO` are allowed only if all subcommands are also allowed.

EXPLAIN

Generally `EXPLAIN` is allowed, but because `EXPLAIN ANALYZE` can have side effects on the database, there are some restrictions on it.

EXPLAIN ANALYZE Replication

`EXPLAIN ANALYZE` follows replication rules of the analyzed statement.

EXPLAIN ANALYZE Locking

`EXPLAIN ANALYZE` follows locking rules of the analyzed statement.

GRANT and REVOKE

Generally `GRANT` and `REVOKE` statements are supported, however `GRANT/REVOKE ON TABLESPACE/LARGE OBJECT` aren't replicated.

LOCK TABLE

LOCK TABLE isn't replicated, but it might acquire the global DML lock when `bdr.lock_table_locking` is set `on`.

You can also use The `bdr.global_lock_table()` function to explicitly request a global DML lock.

MATERIALIZED VIEW

Materialized views are accepted but not replicated. Each node refreshes and creates them locally.

SECURITY LABEL

All variants of `SECURITY LABEL` are allowed, but `SECURITY LABEL ON TABLESPACE/DATABASE/LARGE OBJECT` isn't replicated.

TRUNCATE Replication

`TRUNCATE` command is replicated as DML, not as a DDL statement. Whether the `TRUNCATE` on table is replicated depends on replication settings for each affected table.

TRUNCATE Locking

Even though `TRUNCATE` isn't replicated the same way as other DDL, it can acquire the global DML lock when `bdr.truncate_locking` is set to `on`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.6 DDL and role manipulation statements

Users are global objects in a PostgreSQL instance, which means they span multiple databases while PGD operates on an individual database level. Because of this behavior, role manipulation statement handling needs extra thought.

PGD requires that any roles that are referenced by any replicated DDL must exist on all nodes. The roles don't have to have the same grants, password, and so on, but they must exist.

PGD replicates role manipulation statements if `bdr.role_replication` is enabled (default) and role manipulation statements are run in a PGD-enabled database.

The role manipulation statements include the following:

- `CREATE ROLE`
- `ALTER ROLE`
- `DROP ROLE`
- `GRANT ROLE`
- `CREATE USER`
- `ALTER USER`
- `DROP USER`
- `CREATE GROUP`
- `ALTER GROUP`
- `DROP GROUP`

In general, either:

- Configure the system so that exactly one PGD-enabled database on the Postgres instance has `bdr.role_replication = on`, and run all role management DDL on that database. We recommend this approach.
- Configure the system with `bdr.role_replication = off`, and deploy all role changes (user and group) by external orchestration tools like Ansible, Puppet, and Chef or explicitly replicated by `bdr.replicate_ddl_command()`. We recommend against this approach.

We recommend that you run all role management commands in one database, with `bdr.role_replication` set to `on`.

If role replication is turned off, then the administrator must ensure that any roles used by DDL on one node also exist on the other nodes. Otherwise PGD apply stalls with an error until the role is created on the other nodes.

> **Connection Manager authentication**
>
> For Connection Manager authentication to work correctly, set or change role passwords only while connected to a PGD-enabled database with `bdr.role_replication` set to `on`. A password set or changed while disconnected from the PGD-enabled database, or with `bdr.role_replication` set to `off`, doesn't replicate, and Connection Manager can then fail to authenticate that role.

> **PGD with non-PGD-enabled databases**
>
> PGD doesn't capture and replicate role management statements when they run on a non-PGD-enabled database in a PGD-enabled PostgreSQL instance. For example, suppose you have databases `bdrdb` (bdr group member) and `postgres` (bare db), and `bdr.role_replication = on`. A `CREATE USER` run in `bdrdb` is replicated, but a `CREATE USER` run in `postgres` isn't.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.7 Workarounds for DDL restrictions

You can work around some of the limitations of PGD DDL operation handling. Often splitting the operation into smaller changes can produce the desired result that either isn't allowed as a single statement or requires excessive locking.

Adding a CONSTRAINT

You can add `CHECK` and `FOREIGN KEY` constraints without requiring a DML lock. This involves a two-step process:

- `ALTER TABLE ... ADD CONSTRAINT ... NOT VALID`
- `ALTER TABLE ... VALIDATE CONSTRAINT`

Execute these steps in two different transactions. Both of these steps take DDL lock only on the table and hence can be run even when one or more nodes are down. But to validate a constraint, PGD must ensure that:

- All nodes in the cluster see the `ADD CONSTRAINT` command.
- The node validating the constraint applied replication changes from all other nodes prior to creating the NOT VALID constraint on those nodes.

So even though the new mechanism doesn't need all nodes to be up while validating the constraint, it still requires that all nodes applied the `ALTER TABLE .. ADD CONSTRAINT ... NOT VALID` command and made enough progress. PGD waits for a consistent state to be reached before validating the constraint.

The new facility requires the cluster to run with Raft protocol version 24 and later. If the Raft protocol isn't yet upgraded, the old mechanism is used, resulting in a DML lock request.

Adding a column

To add a column with a volatile default, run these commands in separate transactions:

```
    ALTER TABLE mytable ADD COLUMN newcolumn coltype; -- Note the lack of DEFAULT or NOT
NULL

    ALTER TABLE mytable ALTER COLUMN newcolumn DEFAULT
volatile-expression;

    BEGIN;
    SELECT bdr.global_lock_table('mytable');
    UPDATE mytable SET newcolumn = default-expression;
    COMMIT;
```

This approach splits schema changes and row changes into separate transactions that PGD can execute and results in consistent data across all nodes in a PGD group.

For best results, batch the update into chunks so that you don't update more than a few tens or hundreds of thousands of rows at once. You can do this using a `PROCEDURE` with embedded transactions.

The last batch of changes must run in a transaction that takes a global DML lock on the table. Otherwise you can miss rows that are inserted concurrently into the table on other nodes.

If required, you can run `ALTER TABLE mytable ALTER COLUMN newcolumn NOT NULL;` after the `UPDATE` has finished.

Changing a column's type

Changing a column's type can cause PostgreSQL to rewrite a table. In some cases, though, you can avoid this rewriting. For example:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE foo (id BIGINT PRIMARY KEY, description
VARCHAR(128));
ALTER TABLE foo ALTER COLUMN description TYPE
VARCHAR(20);
```

You can rewrite this statement to avoid a table rewrite by making the restriction a table constraint rather than a datatype change. The constraint can then be validated in a subsequent command to avoid long locks, if you want.

```
CREATE TABLE foo (id BIGINT PRIMARY KEY, description
VARCHAR(128));
ALTER TABLE
foo
  ALTER COLUMN description TYPE
varchar,
  ADD CONSTRAINT description_length_limit CHECK (length(description) <= 20) NOT
VALID;
ALTER TABLE foo VALIDATE CONSTRAINT
description_length_limit;
```

If the validation fails, then you can `UPDATE` just the failing rows. You can use this technique for `TEXT` and `VARCHAR` using `length()` or with `NUMERIC` datatype using `scale()`.

In the general case for changing column type, first add a column of the desired type:

```
ALTER TABLE mytable ADD COLUMN newcolumn newtype;
```

Create a trigger defined as `BEFORE INSERT OR UPDATE ON mytable FOR EACH ROW ..`. Creating ths trigger assigns `NEW.newcolumn` to `NEW.oldcolumn` so that new writes to the table update the new column.

`UPDATE` the table in batches to copy the value of `oldcolumn` to `newcolumn` using a `PROCEDURE` with embedded transactions. Batching the work helps reduce replication lag if it's a big table. Updating by range of IDs or whatever method you prefer is fine. Alternatively, you can update the whole table in one pass for smaller tables.

`CREATE INDEX ...` any required indexes on the new column. It's safe to use `CREATE INDEX ... CONCURRENTLY` individually without DDL replication on each node to reduce lock durations.

`ALTER` the column to add a `NOT NULL` and `CHECK` constraints, if required.

1. `BEGIN` a transaction.
2. `DROP` the trigger you added.
3. `ALTER TABLE` to add any `DEFAULT` required on the column.
4. `DROP` the old column.
5. `ALTER TABLE mytable RENAME COLUMN newcolumn TO oldcolumn`.
6. `COMMIT`.

> **Note**
>
> Because you're dropping a column, you might have to re-create views, procedures, and so on that depend on the table. Be careful if you `CASCADE` drop the column, as you must be sure to re-create everything that referred to it.

Changing other types

The `ALTER TYPE` statement is replicated, but affected tables aren't locked.

When you use this DDL, ensure that the statement has successfully executed on all nodes before using the new type. You can achieve this using the `bdr.wait_slot_confirm_lsn()` function.

This example ensures that the DDL is written to all nodes before using the new value in DML statements:

```
ALTER TYPE contact_method ADD VALUE 'email';
SELECT bdr.wait_slot_confirm_lsn(NULL, NULL);
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

11.8 PGD functions that behave like DDL

The following PGD management functions act like DDL. This means that, if DDL replication is active and DDL filter settings allow it, they attempt to take global locks, and their actions are replicated. For detailed information, see the documentation for the individual functions.

Replication set management:

- `bdr.create_replication_set`
- `bdr.alter_replication_set`
- `bdr.drop_replication_set`
- `bdr.replication_set_add_table`
- `bdr.replication_set_remove_table`
- `bdr.replication_set_add_ddl_filter`
- `bdr.replication_set_remove_ddl_filter`

Conflict management:

- `bdr.alter_table_conflict_detection`
- `bdr.column_timestamps_enable` (deprecated; use `bdr.alter_table_conflict_detection()`)
- `bdr.column_timestamps_disable` (deprecated; use `bdr.alter_table_conflict_detection()`)

Sequence management:

- `bdr.alter_sequence_set_kind`

Stream triggers:

- `bdr.create_conflict_trigger`
- `bdr.create_transform_trigger`
- `bdr.drop_trigger`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

12 Sequences

Many applications require that unique surrogate ids be assigned to database entries. Often the database `SEQUENCE` object is used to produce these. In PostgreSQL, these can be either:

- A manually created sequence using the `CREATE SEQUENCE` command and retrieved by calling the `nextval()` function
- `serial` and `bigserial` columns or, alternatively, `GENERATED BY DEFAULT AS IDENTITY` columns

However, standard sequences in PostgreSQL aren't multi-node aware and produce values that are unique only on the local node. This is important because unique ids generated by such sequences cause conflict and data loss by means of discarded `INSERT` actions in multi-master replication.

> **Permissions required**
>
> This means that any user who wants to use sequences must have at least the bdr_application role assigned to them.

PGD global sequences

For this reason, PGD provides an application-transparent way to generate unique ids using sequences on bigint or bigserial datatypes across the whole PGD group, called *global sequences*.

PGD global sequences provide an easy way for applications to use the database to generate unique synthetic keys in an asynchronous distributed system that works for most—but not necessarily all—cases.

Using PGD global sequences allows you to avoid the problems with insert conflicts. If you define a `PRIMARY KEY` or `UNIQUE` constraint on a column that's using a global sequence, no node can ever get the same value as any other node. When PGD synchronizes inserts between the nodes, they can never conflict.

PGD global sequences extend PostgreSQL sequences, so they are crash-safe. To use them, you must be granted the bdr_application role.

There are various possible algorithms for global sequences:

- SnowflakeId sequences
- Globally allocated range sequences

SnowflakeId sequences generate values using an algorithm that doesn't require inter-node communication at any point. It's faster and more robust and has the useful property of recording the timestamp when the values were created. Snowflake sequences are generally the preferred sequence option if the application can support it.

SnowflakeId sequences have the restriction that they work only for 64-bit BIGINT datatypes and produce values up to 19 digits long. This might be too long for use in some host language datatypes, such as JavaScript Number types. Globally allocated sequences allocate a local range of values that can be replenished as needed by inter-node consensus, making them suitable for either BIGINT or INTEGER sequences.

You can create a global sequence using the `bdr.alter_sequence_set_kind()` function. This function takes a standard PostgreSQL sequence and marks it as a PGD global sequence. It can also convert the sequence back to the standard PostgreSQL sequence.

PGD also provides the configuration variable `bdr.default_sequence_kind`. This variable determines the kind of sequence to create when the `CREATE SEQUENCE` command is executed or when a `serial`, `bigserial`, or `GENERATED BY DEFAULT AS IDENTITY` column is created. Valid settings are:

- `local` — Newly created sequences are the standard PostgreSQL (local) sequences.
- `galloc` — Always creates globally allocated range sequences.
- `snowflakeid` — Creates global sequences for BIGINT sequences that consist of time, nodeid, and counter components. You can't use it with INTEGER sequences (so you can use it for `bigserial` but not for `serial`).
- `timeshard` — The older version of SnowflakeId sequence. Provided for backward compatibility only. The SnowflakeId is preferred.
- `distributed` (default) — A special value that you can use only for `bdr.default_sequence_kind`. It selects `snowflakeid` for `int8` sequences (that is, `bigserial`) and `galloc` sequence for `int4` (that is, `serial`) and `int2` sequences.

The `bdr.sequences` view shows information about individual sequence kinds.

`currval()` and `lastval()` work correctly for all types of global sequence.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

SnowflakeId sequences

The ids generated by SnowflakeId sequences are loosely time ordered so you can use them to get the approximate order of data insertion, like standard PostgreSQL sequences. Values generated within the same millisecond might be out of order, even on one node. The property of loose time ordering means they're suitable for use as range-partition keys.

SnowflakeId sequences work on one or more nodes and don't require any inter-node communication after the node-join process completes. So you can continue to use them even if there's the risk of extended network partitions. They aren't affected by replication lag or inter-node latency.

SnowflakeId sequences generate unique ids in a different way from standard sequences. The algorithm uses three components for a sequence number. The first component of the sequence is a timestamp at the time of sequence number generation. The second component of the sequence number is the unique id assigned to each PGD node, which ensures that the ids from different nodes are always different. The third component is the number generated by the local sequence.

While adding a unique node id to the sequence number is enough to ensure there are no conflicts, you also want to keep another useful property of sequences. The ordering of the sequence numbers roughly corresponds to the order in which data was inserted into the table. Putting the timestamp first ensures this.

A few limitations and caveats apply to SnowflakeId sequences.

SnowflakeId sequences are 64 bits wide and need a `bigint` or `bigserial`. Values generated are up to 19 digits long. There's no practical 32-bit `integer` version, so you can't use it with `serial` sequences. Use globally allocated range sequences instead.

For SnowflakeId, there's a limit of 4096 sequence values generated per millisecond on any given node (about 4 million sequence values per second). In case the sequence value generation wraps around within a given millisecond, the SnowflakeId sequence waits until the next millisecond and gets a fresh value for that millisecond.

Since SnowflakeId sequences encode timestamps into the sequence value, you can generate new sequence values only within the given time frame (depending on the system clock). The oldest timestamp that you can use is 2016-10-07, which is the epoch time for the SnowflakeId. The values wrap to negative values in the year 2086 and completely run out of numbers by 2156.

Since timestamp is an important part of a SnowflakeId sequence, there's additional protection from generating sequences with a timestamp older than the latest one used in the lifetime of a Postgres process (but not between Postgres restarts).

The `INCREMENT` option on a sequence used as input for SnowflakeId sequences is effectively ignored. This might be relevant for applications that do sequence ID caching, like many object-relational mapper (ORM) tools, notably Hibernate. Because the sequence is time based, this has little practical effect since the sequence advances to a new noncolliding value by the time the application can do anything with the cached values.

Similarly, you might change the `START`, `MINVALUE`, `MAXVALUE`, and `CACHE` settings on the underlying sequence, but there's no benefit to doing so. The sequence's low 14 bits are used and the rest is discarded, so the value-range limits don't affect the function's result. For the same reason, `setval()` isn't useful for SnowflakeId sequences.

Timeshard sequences

Timeshard sequences are provided for backward compatibility with existing installations but aren't recommended for new application use. We recommend using the SnowflakeId sequence instead.

Timeshard is very similar to SnowflakeId but has different limits, fewer protections, and slower performance.

The differences between timeshard and SnowflakeId are as follows:

- Timeshard can generate up to 16384 per millisecond (about 16 million per second), which is more than SnowflakeId. However, there's no protection against wraparound within a given millisecond. Schemas using the timeshard sequence must protect the use of the `UNIQUE` constraint when using timeshard values for a given column.
- The timestamp component of timeshard sequence runs out of values in the year 2050 and, if used in combination with bigint, the values wrap to negative numbers in the year 2033. This means that sequences generated after 2033 have negative values. This is a considerably shorter time span than SnowflakeId and is the main reason why SnowflakeId is preferred.
- Timeshard sequences require occasional disk writes (similar to standard local sequences). SnowflakeIds are calculated in memory so the SnowflakeId sequences are in general a little faster than timeshard sequences.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Globally allocated range sequences

The globally allocated range (or `galloc`) sequences allocate ranges (chunks) of values to each node. When the local range is used up, a new range is allocated globally by consensus among the other nodes. This behavior uses the key space efficiently but requires that the local node be connected to a majority of the nodes in the cluster for the sequence generator to progress when the currently assigned local range is used up.

Unlike SnowflakeId sequences, `galloc` sequences support all sequence data types provided by PostgreSQL: `smallint`, `integer`, and `bigint`. This means that you can use `galloc` sequences in environments where 64-bit sequences are problematic. Examples include using integers in JavaScript, since that supports only 53-bit values, or when the sequence is displayed on output with limited space.

The range assigned by each voting node is currently predetermined based on the datatype the sequence is using:

- smallint — 1 000 numbers
- integer — 1 000 000 numbers
- bigint — 1 000 000 000 numbers

Each node allocates two chunks of seq_chunk_size—one for the current use plus a reserved chunk for future use—so the values generated from any one node increase monotonically. However, viewed globally, the values generated aren't ordered at all. This might cause a loss of performance due to the effects on b-tree indexes and typically means that generated values aren't useful as range-partition keys.

The main downside of the `galloc` sequences is that, once the assigned range is used up, the sequence generator has to ask for consensus about the next range for the local node that requires inter-node communication. This might lead to delays or operational issues if the majority of the PGD group isn't accessible. (This might be avoided in later releases.)

The `CACHE`, `START`, `MINVALUE`, and `MAXVALUE` options work correctly with `galloc` sequences. However, you need to set them before transforming the sequence to the `galloc` kind. The `INCREMENT BY` option also works correctly. However, you can't assign an increment value that's equal to or more than the above ranges assigned for each sequence datatype. `setval()` doesn't reset the global state for `galloc` sequences. Don't use it.

A few limitations apply to `galloc` sequences. PGD tracks `galloc` sequences in a special PGD catalog bdr.sequence_alloc. This catalog is required to track the currently allocated chunks for the `galloc` sequences. The sequence name and namespace is stored in this catalog. The sequence chunk allocation is managed by Raft, whereas any changes to the sequence name/namespace is managed by the replication stream. So PGD currently doesn't support renaming `galloc` sequences or moving them to another namespace or renaming the namespace that contains a `galloc` sequence. Be mindful of this limitation while designing application schema.

Additionally, after restoring a node from a backup, all galloc sequences must manually have their next value set to the maximum value of the related column. See "Set a new start value for the sequence".

Converting a local sequence to a galloc sequence

Before transforming a local sequence to galloc, you need to take care of several prerequisites.

1. Verify that sequence and column data type match

Check that the sequence's data type matches the datatype of the column with which it will be used. For example, you can create a `bigint` sequence and assign an `integer` column's default to the `nextval()` returned by that sequence. With galloc sequences, which for `bigint` are allocated in blocks of 1 000 000 000, this quickly results in the values returned by `nextval()` exceeding the `int4` range if more than two nodes are in use.

This example shows what can happen:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE SEQUENCE int8_seq;

SELECT sequencename, data_type FROM pg_sequences;
 sequencename |
data_type
--------------+-----------
 int8_seq     |
bigint
(1 row)

CREATE TABLE seqtest (id INT NOT NULL PRIMARY
KEY);

ALTER SEQUENCE int8_seq OWNED BY
seqtest.id;

SELECT bdr.alter_sequence_set_kind('public.int8_seq'::regclass, 'galloc', 1);
 alter_sequence_set_kind
-------------------------


(1 row)

ALTER TABLE seqtest ALTER COLUMN id SET DEFAULT
nextval('int8_seq'::regclass);
```

After executing `INSERT INTO seqtest VALUES(DEFAULT)` on two nodes, the table contains the following values:

```
SELECT * FROM
seqtest;
     id
------------
          2
 2000000002
(2 rows)
```

However, attempting the same operation on a third node fails with an `integer out of range` error, as the sequence generated the value `4000000002`.

> **Tip**
>
> You can retrieve the current data type of a sequence from the PostgreSQL`pg_sequences` view. You can modify the data type of a sequence with `ALTER SEQUENCE ... AS ...`, for example, `ALTER SEQUENCE public.sequence AS integer`, as long as its current value doesn't exceed the maximum value of the new data type.

2. Set a new start value for the sequence

When the sequence kind is altered to `galloc`, it's rewritten and restarts from the defined start value of the local sequence. If this happens on an existing sequence in a production database, you need to query the current value and then set the start value appropriately. To help with this use case, PGD lets you pass a starting value with the function `bdr.alter_sequence_set_kind()`. If you're already using offset and you have writes from multiple nodes, you need to check what's the greatest used value and restart the sequence to at least the next value:

```
-- determine highest sequence value across all
nodes
SELECT max((x->'response'->'command_tuples'->0->>'nextval')::bigint)
    FROM
jsonb_array_elements(

bdr.run_on_all_nodes(
            E'SELECT
nextval(\'public.sequence\');'
            )::jsonb) AS x;

-- turn into a galloc
sequence
SELECT bdr.alter_sequence_set_kind('public.sequence'::regclass, 'galloc', $MAX + $MARGIN);
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Since users can't lock a sequence, you must leave a `$MARGIN` value to allow operations to continue while the `max()` value is queried.

The `bdr.sequence_alloc` table gives information on the chunk size and the ranges allocated around the whole cluster.

In this example, the sequence starts at `333`, and the cluster has two nodes. The number of allocation is 4, which is 2 per node, and the chunk size is 1000000, which is related to an integer sequence.

```
SELECT * FROM bdr.sequence_alloc
    WHERE seqid = 'public.categories_category_seq'::regclass;
         seqid          | seq_chunk_size | seq_allocated_up_to | seq_nallocs |
seq_last_alloc
------------------------+----------------+---------------------+-------------+-------------------------------
 categories_category_seq |        1000000 |             4000333 |           4 | 2020-05-21
20:02:15.957835+00
(1 row)
```

To see the ranges currently assigned to a given sequence on each node, execute the function `bdr.galloc_chunk_info`.

- Node `Node1` is using range from `333` to `2000333`.

```
SELECT * FROM bdr.galloc_chunk_info('categories_category_seq');
 chunk_start |
chunk_end
-------------+-----------
         334 |
1000333
     1000334 |
2000333
(2 rows)
```

- Node `Node2` is using range from `2000334` to `4000333`.

```
SELECT * FROM bdr.galloc_chunk_info('categories_category_seq');
 chunk_start |
chunk_end
-------------+-----------
     2000334 |
3000333
     3000334 |
4000333
```

When a node finishes a chunk, it asks a consensus for a new one and gets the first available. In the example, it's from 4000334 to 5000333. This is the new reserved chunk and starts to consume the old reserved chunk.

UUIDs, KSUUIDs, and other approaches

You can generate globally unique ids in other ways without using the global sequences that can be used with PGD. For example:

- UUIDs and their PGD variant, KSUUIDs
- Local sequences with a different offset per node (i.e., manual)
- An externally coordinated natural key

PGD applications can't use other methods safely. Counter-table-based approaches relying on `SELECT ... FOR UPDATE`, `UPDATE ... RETURNING ...` or similar for sequence generation don't work correctly in PGD because PGD doesn't take row locks between nodes. The same values are generated on more than one node. For the same reason, the usual strategies for "gapless" sequence generation don't work with PGD. In most cases, the application coordinates generating sequences that must be gapless from some external source using two-phase commit. Or it generates them only on one node in the PGD group.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

UUIDs

`UUID` keys instead avoid sequences entirely and use 128-bit universal unique identifiers. These are random or pseudorandom values that are so large that it's nearly impossible for the same value to be generated twice. There's no need for nodes to have continuous communication when using `UUID` keys.

In the unlikely event of a collision, conflict detection chooses the newer of the two inserted records to retain. Conflict logging, if enabled, records such an event. However, it's exceptionally unlikely to ever occur, since collisions become practically likely only after about 2^64 keys are generated.

The main downside of `UUID` keys is that they're somewhat inefficient in terms of space and the network. They consume more space not only as a primary key but also where referenced in foreign keys and when transmitted on the wire. Also, not all applications cope well with `UUID` keys.

KSUUIDs

PGD provides functions for working with a K-sortable variant of `UUID` data. Known as KSUUID, it generates values that can be stored using the PostgreSQL standard `UUID` data type. A `KSUUID` value is similar to `UUIDv1` in that it stores both timestamp and random data, following the `UUID` standard. The difference is that `KSUUID` is K-sortable, meaning that it's weakly sortable by timestamp. This makes it more useful as a database key, as it produces more compact `btree` indexes. This behavior improves the effectiveness of search and allows natural time-sorting of result data. Unlike `UUIDv1`, `KSUUID` values don't include the MAC of the computer on which they were generated, so there are no security concerns from using them.

We now recommend `KSUUID` v2 in all cases. You can directly sort values generated with regular comparison operators.

There are two versions of `KSUUID` in PGD: v1 and v2. The legacy `KSUUID` v1 is deprecated but is kept to support existing installations. Don't use it for new installations. The internal contents of v1 and v2 aren't compatible. As such, the functions to manipulate them also aren't compatible. The v2 of `KSUUID` also no longer stores the `UUID` version number.

See KSUUID v2 functions and KSUUID v1 functions in the PGD reference.

Step and offset sequences

In offset-step sequences, a normal PostgreSQL sequence is used on each node. Each sequence increments by the same amount and starts at differing offsets. For example, with step 1000, node1's sequence generates 1001, 2001, 3001, and so on. node2's sequence generates 1002, 2002, 3002, and so on. This scheme works well even if the nodes can't communicate for extended periods. However, the designer must specify a maximum number of nodes when establishing the schema, and it requires per-node configuration. Mistakes can easily lead to overlapping sequences.

It's relatively simple to configure this approach with PGD by creating the desired sequence on one node, like this:

```
CREATE TABLE some_table (
    generated_value bigint primary key
);

CREATE SEQUENCE some_seq INCREMENT 1000 OWNED BY some_table.generated_value;

ALTER TABLE some_table ALTER COLUMN generated_value SET DEFAULT nextval('some_seq');
```

Then, on each node calling `setval()`, give each node a different offset starting value, for example:

```
-- On node 1
SELECT setval('some_seq', 1);

-- On node 2
SELECT setval('some_seq', 2);

 -- ... etc
```

Be sure to allow a large enough `INCREMENT` to leave room for all the nodes you might ever want to add, since changing it in the future is difficult and disruptive.

If you use `bigint` values, there's no practical concern about key exhaustion, even if you use offsets of 10000 or more. It would take hundreds of years, with hundreds of machines, doing millions of inserts per second, to have any chance of approaching exhaustion.

PGD doesn't currently offer any automation for configuring the per-node offsets on such step/offset sequences.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Composite keys

A variant on step/offset sequences is to use a composite key composed of `PRIMARY KEY (node_number, generated_value)`. The node number is usually obtained from a function that returns a different number on each node. You can create such a function by temporarily disabling DDL replication and creating a constant SQL function. Alternatively, you can use a one-row table that isn't part of a replication set to store a different value in each node.

See also

- Global Sequence management interfaces
- KSUUID v2 functions
- KSUUID v1 functions

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13 Node management

All data nodes in a PGD cluster are members of one or more groups. By default, all data nodes are members of the top-level group, which spans all data nodes in the PGD cluster. Nodes can also belong to subgroups that can be configured to reflect logical or geographical organization of the PGD cluster.

You can manage nodes and groups using the various options available with nodes and subgroups.

- Creating nodes covers the steps needed to create a new node in a PGD cluster.
- Groups and subgroups goes into more detail on how groups and subgroups work in PGD.
- Creating and joining groups looks at how new PGD groups can be created and how to join PGD nodes to them.
- Viewing topology details commands and SQL queries that can show the structure of a PGD cluster's nodes and groups.
- Removing nodes and groups shows the process to follow to safely remove a node from a group or a group from a cluster.
- Heterogeneous clusters looks at how your PGD cluster can interoperate with PGD nodes from earlier editions of PGD.
- Connection DSNs introduces the DSNs or connection strings needed to connect directly to a node in a PGD cluster. It also covers how to use SSL/TLS certificates to provide authentication and encryption between servers and between clients.
- Replication slots examines how the Postgres replication slots are consumed when PGD is operating.
- Node recovery details the steps needed to bring a node back into service after a failure or scheduled downtime and the impact it has on the cluster as it returns.
- Maintenance commands through proxies shows how to send maintenance commands to nodes that you can't directly access, such as those behind a proxy.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.1 Creating PGD nodes

Depending on your selected deployment method, you may or may not have to create PGD nodes manually. For example, if you are using TPA or the EDB Postgres Distributed for Kubernetes, the nodes are created automatically. But if you are manually deploying PGD or creating your own deployment method, you need to know how to create and configure a PGD node.

It's just Postgres

A PGD node is just a Postgres instance with the BDR extension installed. The BDR extension enables bidirectional replication between nodes and is the foundation of PGD.

That means, in the most general terms, you can create a PGD node by installing Postgres and the BDR extension, and then configuring the node to connect to the other nodes in the PGD group. But there are some specifics to consider.

Which Postgres version?

PGD is built on top of Postgres, so the distribution and version of Postgres you use for your PGD nodes is important. The version of Postgres you use must be compatible with the version of PGD you are using. You can find the compatibility matrix in the release notes. Features and functionality in PGD may depend on the distribution of Postgres you are using. The EDB Postgres Advanced Server is the recommended distribution for PGD. PGD also supports EDB Postgres Extended Server and Community Postgres. You can find out what features are available in each distribution in the Planning section's Choosing a server page.

Installing Postgres

You must install your selected Postgres distribution on each node you are configuring. You can find installation instructions for each distribution in the EDB Postgres Advanced Server documentation, EDB Postgres Extended Server documentation, and the Postgres installation documentation. You can also refer to the PGD manual installation guide which covers the installation of Postgres.

Installing the BDR extension

The BDR extension is the key to PGD's distributed architecture. You need to install the BDR extension on each node in your PGD cluster. The BDR extension is available from the EDB Postgres Distributed repository. You need to add the `postgres_distributed` repository to your package management system on Linux and then install the `edb-bdr` package. You can find the repository configuration instructions in the PGD manual installation guide.

Once the repository is configured, you can install the BDR package with your package manager. The package name is `edb-bdr5-<postgresversion>` where `<postgresversion>` is the version of Postgres you are using. For example, if you are using Postgres 13, the package name is `edb-bdr5-13`.

Configuring the database for PGD

This process is specific to PGD and involves configuring the Postgres instance to work with the BDR extension and adjusting various settings to work with the PGD cluster. This process is also detailed in the PGD manual installation guide The steps are as follows:

- Add the BDR extension `$libdir/bdr` at the start of the `shared_preload_libraries` setting in `postgresql.conf`.
- Set the `wal_level` GUC variable to `logical` in `postgresql.conf`.
- Turn on commit timestamp tracking by setting `track_commit_timestamp` to `'on'` in `postgresql.conf`.
- Increase the maximum worker processes to 16 or higher by setting `max_worker_processes` to `'16'` in `postgresql.conf`.

> **The `max_worker_processes` value**
>
> The `max_worker_processes` value is derived from the topology of the cluster, the number of peers, number of databases, and other factors. To calculate the needed value, see Postgres configuration/settings. The value of 16 was calculated for the size of cluster being deployed in this example. It must be increased for larger clusters.

- Set a password on the EnterprisedDB/Postgres user.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- Add rules to `pg_hba.conf` to allow nodes to connect to each other.
  - Ensure that these lines are present in `pg_hba.conf`:

```
host all all all md5
host replication all all md5
```

- Add a `.pgpass` file to allow nodes to authenticate each other.
  - Configure a user with sufficient privileges to log in to the other nodes.
  - See The Password File in the Postgres documentation for more on the `.pgpass` file.

Once these steps are complete, restart the Postgres instance to apply the changes.

Setting up the replicated database

Create a database within Postgres to use as PGD's replicated database. You can do this with the `CREATE DATABASE` command. The created database should be the name of the database that other nodes in the PGD cluster replicate. The convention is to name the database `bdrdb`.

Log into that specific database instance you have configured and set up the BDR extension. You can do this by running the `CREATE EXTENSION bdr;` command as superuser. This command creates the BDR extension within that database.

Next steps

The node is now configured and ready to be join a group, or start a group, in the PGD cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.2 Groups and subgroups

Groups

A PGD cluster's nodes are gathered in groups. A "top level" group always exists and is the group to which all data nodes belong to automatically. The "top level" group can also be the direct parent of sub-groups.

Sub-groups

A group can also contain zero or more subgroups. Subgroups can be used to represent data centers or locations allowing commit scopes to refer to nodes in a particular region as a whole. PGD Proxy can also make use of subgroups to delineate nodes available to be write leader.

The `node_group_type` value specifies the type when the subgroup is created. Some sub-group types change the behavior of the nodes within the group. For example, a subscriber-only sub-group will make all the nodes within the group into subscriber-only nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.3 Creating and joining PGD groups

Creating and joining PGD groups

For PGD, every node must connect to every other node. To make configuration easy, when a new node joins, it configures all existing nodes to connect to it. For this reason, every node, including the first PGD node created, must know the PostgreSQL connection string that other nodes can use to connect to it. This connection string is sometimes referred to as a data source name (DSN).

Both formats of connection string are supported. So you can use either key-value format, like `host=myhost port=5432 dbname=mydb`, or URI format, like `postgresql://myhost:5432/mydb`.

The SQL function `bdr.create_node_group()` creates the PGD group from the local node. Doing so activates PGD on that node and allows other nodes to join the PGD group, which consists of only one node at that point. At the time of creation, you must specify the connection string for other nodes to use to connect to this node.

Once the node group is created, every further node can join the PGD group using the `bdr.join_node_group()` function.

Alternatively, use the command line utility bdr_init_physical to create a new node, using `pg_basebackup`. If using `pg_basebackup`, the bdr_init_physical utility can optionally specify the base backup of only the target database. The earlier behavior was to back up the entire database cluster. With this utility, the activity completes faster and also uses less space because it excludes unwanted databases. If you specify only the target database, then the excluded databases get cleaned up and removed on the new node.

When a new PGD node is joined to an existing PGD group or a node subscribes to an upstream peer, before replication can begin the system must copy the existing data from the peer nodes to the local node. This copy must be carefully coordinated so that the local and remote data starts out identical. It's not enough to use pg_dump yourself. The BDR extension provides built-in facilities for making this initial copy.

During the join process, the BDR extension synchronizes existing data using the provided source node as the basis and creates all metadata information needed for establishing itself in the mesh topology in the PGD group. If the connection between the source and the new node disconnects during this initial copy, restart the join process from the beginning.

The node that's joining the cluster must not contain any schema or data that already exists on databases in the PGD group. We recommend that the newly joining database be empty except for the BDR extension. However, it's important that all required database users and roles are created. Also, if a non-superuser is performing the joining operation, extensions that require superuser permission must be created manually. For more details, see Connections and roles.

Optionally, you can skip the schema synchronization using the `synchronize_structure` parameter of the `bdr.join_node_group` function. In this case, the schema must already exist on the newly joining node.

We recommend that you select the source node that has the best connection (logically close, ideally with low latency and high bandwidth) as the source node for joining. Doing so lowers the time needed for the join to finish.

Coordinate the join procedure using the Raft consensus algorithm, which requires most existing nodes to be online and reachable.

The logical join procedure (which uses the `bdr.join_node_group` function) performs data sync doing `COPY` operations and uses multiple writers (parallel apply) if those are enabled.

Node join can execute concurrently with other node joins for the majority of the time taken to join. However, only one regular node at a time can be in either of the states PROMOTE or PROMOTING. These states are typically fairly short if all other nodes are up and running. Otherwise the join is serialized at this stage. The subscriber-only nodes are an exception to this rule, and they can be concurrently in PROMOTE and PROMOTING states as well, so their join process is fully concurrent.

The join process uses only one node as the source, so it can be executed when nodes are down if a majority of nodes are available. This approach can cause a complexity when running logical join. During logical join, the commit timestamp of rows copied from the source node is set to the latest commit timestamp on the source node. Committed changes on nodes that have a commit timestamp earlier than this (because nodes are down or have significant lag) can conflict with changes from other nodes. In this case, the newly joined node can be resolved differently to other nodes, causing a divergence. As a result, we recommend not running a node join when significant replication lag exists between nodes. If this is necessary, run LiveCompare on the newly joined node to correct any data divergence once all nodes are available and caught up.

`pg_dump` can fail when there's concurrent DDL activity on the source node because of cache-lookup failures. Since `bdr.join_node_group` uses pg_dump internally, it might fail if there's concurrent DDL activity on the source node. Retrying the join works in that case.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.4 Viewing PGD topology

Listing PGD groups

Using pgd-cli

Use the pgd-cli `groups list` command to list all groups in the PGD cluster:

```
pgd groups list
```

```
  Group Name  Parent Group Name Group Type     Nodes
  ----------- ----------------- --------------- -----
  bdrgroup    bdrgroup          global          0
  group_a     bdrgroup          data            4
  group_b     bdrgroup          data            4
  group_c     bdrgroup          data            1
  group_so    bdrgroup          subscriber-only 1
```

Using SQL

The following simple query lists all the PGD node groups of which the current node is a member. It currently returns only one row from `bdr.local_node_summary`.

```
SELECT node_group_name
FROM bdr.local_node_summary;
```

You can display the configuration of each node group using a more complex query:

```
SELECT g.node_group_name
,
ns.pub_repsets
,
ns.sub_repsets
, g.node_group_default_repset     AS
default_repset
, node_group_check_constraints    AS check_constraints
FROM bdr.local_node_summary ns
JOIN bdr.node_group g USING
(node_group_name);
```

Listing nodes in a PGD group

Using pgd-cli

Use the `nodes list` command to list all nodes in the PGD cluster:

```
pgd nodes list
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
  Node Name           Group Name Node Kind       Join State Node Status
  ------------------- ---------- --------------- ---------- -----------
  bdr-a1              group_a    data            ACTIVE     Up
  bdr-a2              group_a    data            ACTIVE     Up
  logical-standby-a1  group_a    standby         ACTIVE     Up
  witness-a           group_a    witness         ACTIVE     Up
  bdr-b1              group_b    data            ACTIVE     Up
  bdr-b2              group_b    data            ACTIVE     Up
  logical-standby-b1  group_b    standby         ACTIVE     Up
  witness-b           group_b    witness         ACTIVE     Up
  witness-c           group_c    witness         ACTIVE     Up
  subscriber-only-c1  group_so   subscriber-only ACTIVE     Up
```

Use `grep` with the group name to filter the list to a specific group:

```
pgd nodes list | grep group_b
```

```
  bdr-b1             group_b  data      ACTIVE     Up
  bdr-b2             group_b  data      ACTIVE     Up
  logical-standby-b1 group_b  standby   ACTIVE     Up
  witness-b          group_b  witness   ACTIVE     Up
```

Using SQL

You can extract the list of all nodes in a given node group (such as `mygroup`) from the `bdr.node_summary` view. For example:

```
SELECT node_name          AS name
, node_seq_id             AS
ord
, peer_state_name         AS current_state
, peer_target_state_name AS target_state
, interface_connstr       AS
dsn
FROM
bdr.node_summary
WHERE node_group_name = 'mygroup';
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.5 Removing nodes and groups

Removing a node from a PGD group

Since PGD is designed to recover from extended node outages, you must explicitly tell the system if you're removing a node permanently. If you permanently shut down a node and don't tell the other nodes, then performance suffers and eventually the whole system stops working.

Node removal, also called *parting*, is done using the `bdr.part_node()` function. You must specify the node name (as passed during node creation) to remove a node. You can call the `bdr.part_node()` function from any active node in the PGD group, including the node that you're removing.

Just like the join procedure, parting is done using Raft consensus and requires a majority of nodes to be online to work.

The parting process affects all nodes. The Raft leader manages a vote between nodes to see which node has the most recent data from the parting node. Then all remaining nodes make a secondary, temporary connection to the most recent node to allow them to catch up any missing data.

A parted node still is known to PGD but doesn't consume resources. A node might be added again under the same name as a parted node. In rare cases, you might want to clear all metadata of a parted node by using the function `bdr.drop_node()`.

Removing a whole PGD group

PGD groups usually map to locations. When a location is no longer being deployed, it's likely that the PGD group for the location also needs to be removed.

The PGD group that's being removed must be empty. Before you can remove the group, you must part all the nodes in the group.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.6 Joining a heterogeneous cluster

A PGD 4.0 node can join an EDB Postgres Distributed cluster running 3.7.x at a specific minimum maintenance release (such as 3.7.6) or a mix of 3.7 and 4.0 nodes. This procedure is useful when you want to upgrade not just the PGD major version but also the underlying PostgreSQL major version. You can achieve this by joining a 3.7 node running on PostgreSQL 12 or 13 to an EDB Postgres Distributed cluster running 3.6.x on PostgreSQL 11. The new node can also run on the same PostgreSQL major release as all of the nodes in the existing cluster.

PGD ensures that the replication works correctly in all directions even when some nodes are running 3.6 on one PostgreSQL major release and other nodes are running 3.7 on another PostgreSQL major release. However, we recommend that you quickly bring the cluster into a homogenous state by parting the older nodes once enough new nodes join the cluster. Don't run any DDLs that might not be available on the older versions and vice versa.

A node joining with a different major PostgreSQL release can't use physical backup taken with `bdr_init_physical`, and the node must join using the logical join method. Using this method is necessary because the major PostgreSQL releases aren't on-disk compatible with each other.

When a 3.7 node joins the cluster using a 3.6 node as a source, certain configurations, such as conflict resolution, aren't copied from the source node. The node must be configured after it joins the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.7 Connection DSNs and SSL (TLS)

Because nodes connect using `libpq`, the DSN of a node is a `libpq` connection string. As such, the connection string can contain any permitted `libpq` connection parameter, including those for SSL. The DSN must work as the connection string from the client connecting to the node in which it's specified. An example of such a set of parameters using a client certificate is:

```
sslmode=verify-full sslcert=bdr_client.crt
sslkey=bdr_client.key
sslrootcert=root.crt
```

With this setup, the files `bdr_client.crt`, `bdr_client.key`, and `root.crt` must be present in the data directory on each node, with the appropriate permissions. For `verify-full` mode, the server's SSL certificate is checked to ensure that it's directly or indirectly signed with the `root.crt` certificate authority and that the host name or address used in the connection matches the contents of the certificate. In the case of a name, this can match a subject's alternative name or, if there are no such names in the certificate, the subject's common name (CN) field. Postgres doesn't currently support subject alternative names for IP addresses, so if the connection is made by address rather than name, it must match the CN field.

The CN of the client certificate must be the name of the user making the PGD connection, which is usually the user postgres. Each node requires matching lines permitting the connection in the `pg_hba.conf` file. For example:

```
hostssl all         postgres 10.1.2.3/24
cert
hostssl replication postgres 10.1.2.3/24
cert
```

Another setup might be to use `SCRAM-SHA-256` passwords instead of client certificates and not verify the server identity as long as the certificate is properly signed. Here the DSN parameters might be:

```
sslmode=verify-ca sslrootcert=root.crt
```

The corresponding `pg_hba.conf` lines are:

```
hostssl all         postgres 10.1.2.3/24 scram-sha-
256
hostssl replication postgres 10.1.2.3/24 scram-sha-
256
```

In such a scenario, the postgres user needs a `.pgpass` file containing the correct password.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.8 Replication slots created by PGD

On a PGD master node, the following replication slots are created by PGD:

- One *group slot*, named `bdr_<database name>_<group name>`
- N-1 *node slots*, named `bdr_<database name>_<group name>_<node name>`, where N is the total number of PGD nodes in the cluster, including direct logical standbys, if any

> **Warning**
>
> Don't drop those slots. PGD creates and manages them and drops them when or if necessary.

On the other hand, you can create or drop replication slots required by software like Barman or logical replication using the appropriate commands for the software without any effect on PGD. Don't start slot names used by other software with the prefix `bdr_`.

For example, in a cluster composed of the three nodes `alpha`, `beta`, and `gamma`, where PGD is used to replicate the `mydb` database and the PGD group is called `mygroup`:

- Node `alpha` has three slots:
  - One group slot named `bdr_mydb_mygroup`
  - Two node slots named `bdr_mydb_mygroup_beta` and `bdr_mydb_mygroup_gamma`
- Node `beta` has three slots:
  - One group slot named `bdr_mydb_mygroup`
  - Two node slots named `bdr_mydb_mygroup_alpha` and `bdr_mydb_mygroup_gamma`
- Node `gamma` has three slots:
  - One group slot named `bdr_mydb_mygroup`
  - Two node slots named `bdr_mydb_mygroup_alpha` and `bdr_mydb_mygroup_beta`

Group replication slot

The group slot is an internal slot used by PGD primarily to track the oldest safe position that any node in the PGD group (including all logical standbys) has caught up to, for any outbound replication from this node.

The group slot name is given by the function `bdr.local_group_slot_name()`.

The group slot can:

- Join new nodes to the PGD group without having all existing nodes up and running (although the majority of nodes should be up). This process doesn't incur data loss in case the node that was down during join starts replicating again.
- Part nodes from the cluster consistently, even if some nodes haven't caught up fully with the parted node.
- Hold back the freeze point to avoid missing some conflicts.
- Keep the historical snapshot for timestamp-based snapshots.

The group slot is usually inactive and is fast forwarded only periodically in response to Raft progress messages from other nodes.

> **Warning**
>
> Don't drop the group slot. Although usually inactive, it's still vital to the proper operation of the EDB Postgres Distributed cluster. If you drop it, then some or all of the features can stop working or have incorrect outcomes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Hashing long identifiers

The name of a replication slot, like any other PostgreSQL identifier, can't be longer than 63 bytes. PGD handles this by shortening the database name, the PGD group name, and the name of the node in case the resulting slot name is too long for that limit. Shortening an identifier is carried out by replacing the final section of the string with a hash of the string itself.

For example, consider a cluster that replicates a database named `db20xxxxxxxxxxxxxxx` (20 bytes long) using a PGD group named `group20xxxxxxxxxxxxx` (20 bytes long). The logical replication slot associated to node `a30xxxxxxxxxxxxxxxxxxxxxxxxxxxx` (30 bytes long) is called since `3597186`, `be9cbd0`, and `7f304a2` are respectively the hashes of `db20xxxxxxxxxxxxxxx`, `group20xxxxxxxxxxxxx`, and `a30xxxxxxxxxxxxxxxxxxxxxxxxxxxx`.

```
bdr_db20xxxx3597186_group20xbe9cbd0_a30xxxxxxxxxxxxx7f304a2
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.9 Node restart and down node recovery

PGD is designed to recover from node restart or node disconnection. The disconnected node rejoins the group by reconnecting to each peer node and then replicating any missing data from that node.

When a node starts up, each connection begins showing up in `bdr.node_slots` with `bdr.node_slots.state = catchup` and begins replicating missing data. Catching up continues for a period of time that depends on the amount of missing data from each peer node and will likely increase over time, depending on the server workload.

If the amount of write activity on each node isn't uniform, the catchup period from nodes with more data can take significantly longer than other nodes. Eventually, the slot state changes to `bdr.node_slots.state = streaming`.

Nodes that are offline for longer periods, such as hours or days, can begin to cause resource issues for various reasons. Don't plan on extended outages without understanding the following issues.

Each node retains change information (using one replication slot for each peer node) so it can later replay changes to a temporarily unreachable node. If a peer node remains offline indefinitely, this accumulated change information eventually causes the node to run out of storage space for PostgreSQL transaction logs (*WAL* in `pg_wal`), and likely causes the database server to shut down with an error similar to this:

```
PANIC: could not write to file "pg_wal/xlogtemp.559": No space left on device
```

Or, it might report other out-of-disk related symptoms.

In addition, slots for offline nodes also hold back the catalog xmin, preventing vacuuming of catalog tables.

On EDB Postgres Extended Server and EDB Postgres Advanced Server, offline nodes also hold back freezing of data to prevent losing conflict-resolution data (see Origin conflict detection).

Administrators must monitor for node outages (see Monitoring) and make sure nodes have enough free disk space. If the workload is predictable, you might be able to calculate how much space is used over time, allowing a prediction of the maximum time a node can be down before critical issues arise.

Don't manually remove replication slots created by PGD. If you do, the cluster becomes damaged and the node that was using the slot must be parted from the cluster, as described in Replication slots created by PGD.

While a node is offline, the other nodes might not yet have received the same set of data from the offline node, so this might appear as a slight divergence across nodes. The parting process corrects this imbalance across nodes. (Later versions might do this earlier.)

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

13.10 Maintenance commands through proxies

Maintenance and performance

As a general rule, you should aim to avoid performing long running or CPU/IO intensive maintenance operations on a cluster's write leader. Maintenance operations such as `VACUUM` can potentially be disruptive to the smooth running of a busy server and detrimental to workload performance.

Ideally, it's best to execute long running maintenance commands on any node in a group that isn't the write leader. Where you are confident that the maintenance command won't cause problems, you can run it on the write leader. For example, standard `VACUUM` can run alongside normal operations without causing problems, so you can run it on the write leader. But `VACUUM FULL` is a more disruptive operation that requires an exclusive lock on the table, so you should avoid running it on the write leader. Routine vacuumingthat has been tuned to your workload is a good way to keep your database healthy and performing well.

If you do wish to avoid the performance issue and only maintain non-write-leader nodes, you will need to connect directly and issue the maintenance commands on those non-write-leader nodes. But in some situations, for example where the server is managed behind proxies, this isn't possible.

Maintenance and proxies

Proxies for PGD tend, by design, to always connect to and send commands to the current write leader. This usually means that you must not connect by way of a proxy to perform maintenance. PGD clusters nodes can present a direct connection for psql and PGD CLI clients that you can use to issue maintenance commands to the server on those nodes. But there are environment in which the PGD cluster is deployed where a proxy is the only way to access the cluster.

For example, in a DBaaS environment, PGD clusters may be locked down such that the only access to the database is through an instance of PGD Proxy. This configuration reduces the footprint of the cluster and makes it more secure. However, it requires that you use a different way of sending maintenance requests to the cluster's nodes.

The technique outlined here is generally useful for despatching commands to specific nodes without being directly connected to that node's server.

Maintenance commands

The term *maintenance commands* refers to:

- `VACUUM`
- Non-replicated DDL commands (which you might want to manually replicate)

A note on node names

The servers in the cluster are referred to by their PGD cluster node names. To get a list of node names in your cluster, use:

```
select node_name from bdr.node;
```

> **Tip**
>
> For more details, see the `bdr.node` table.

This command lists just the node names. If you need to know the group they are a member of, use:

```
select node_name, node_group_name from bdr.node_summary;
```

> **Tip**
>
> For more details, see the `bdr.node_summary` table.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Finding the write leader

If you're connected through the proxy, then you're connected to the write leader. Run `select node_name from bdr.local_node_summary` to see the name of the node:

```
select node_name from bdr.local_node_summary;
```

```
                                                output
    node_name
------------------
node-two
(1 row)
```

This is the node you do **not** want to run your maintenance tasks on.

```
select * from bdr.node_group_routing_summary;
```

```
                                                output
 node_group_name |    write_lead    | previous_write_lead |       read_nodes
-----------------+------------------+---------------------+-------------------------
 dc1             | node-two         | node-one            | {node-one,node-three}
```

Where the `write_lead` is the node determined earlier (node-two), you can also see the two `read_nodes` (node-one and node-three). It's on these nodes that you can safely perform maintenance.

> **Tip**
>
> You can perform that operation with a single query:
>
> ```
> select read_nodes from bdr.node_group_routing_summary where write_lead = (select node_name from
> bdr.local_node_summary);
> ```

Using `bdr.run_on_nodes()`

PGD has the ability to run specific commands on specific nodes using the `bdr.run_on_nodes()` function. This function takes two parameters: an array of node names and the command you want to run on those nodes. For example:

```
SELECT bdr.run_on_nodes(ARRAY['node-one','node-three'],'vacuum full foo');
```

```
                                                output

                                                run_on_nodes
-----------------------------------------------------------------------------------------------------------------------
-----------------------------------------------------------------------------------------------------------------------
-----------------------------------------------------------------------------------------------------------------------
-----------------------------------------------------------------------------------------------------------------------
-----------------------------------------------------------------------------------------------------------------------
 [{"dsn": "host=host-one port=5444 dbname=bdrdb", "node_id": "807899305", "response": {"command_status": "VACUUM"},
"node_name": "node-one", "query_send_time": "2024-01-16 16:24:35.418323+00"}, {"dsn": "host=host-three port=5432
dbname=bdrdb", "node_id": "199017004", "response": {"command_status": "VACUUM"}, "node_name": "node",
"query_send_time": "2024-01-16 16:24:35.4542+00"}]
```

This command runs the `vacuum full foo` command on the node-one and node-three nodes. The node names are passed to the function in an array.

The `bdr.run_on_nodes` function reports its results as JSONB. The results include the name of the node and the response (or error message) resulting from running the command. Other fields included might be include and might not be relevant.

The results also appear as a single string that's hard to read. By applying some formatting to this string, it can become more readable.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Formatting `bdr.run_on_nodes()` output

Using Postgres's JSON expressions, you can reduce the output to just the columns you're interested in. The following command is functionally equivalent to the previous example but lists only the node and response as its results:

```
select q->>'node_name' as node, q->>'response' as response FROM jsonb_array_elements(bdr.run_on_nodes(ARRAY['node-one','node-three'], 'VACUUM FULL foo')) q;
```

```
                                                output
        node     |         response
-----------------+--------------------------
 node-one        | {"command_status": "VACUUM"}
 node-three      | {"command_status": "VACUUM"}
```

If an error occurs, the `command_status` field is set to error. An additional `error_message` value is included in the response. For example:

```
select q->>'node_name' as node, q->>'response' as response FROM jsonb_array_elements(bdr.run_on_nodes(ARRAY['node-one','node-three'], 'VACUUM FULL fool')) q;
```

```
                                                output
    node          |                                        response
------------------+-----------------------------------------------------------------------------------------
 node-one         | {"error_message": "ERROR:  relation \"fool\" does not exist\n", "command_status": "ERROR"}
 node-three       | {"error_message": "ERROR:  relation \"fool\" does not exist\n", "command_status": "ERROR"}
(2 rows)
```

Defining a function for maintenance

If you find yourself regularly issuing maintenance commands to one node at a time, you can define a function to simplify things:

```
create or replace function runmaint(nodename varchar, command varchar) returns TABLE(node text,response jsonb) as
$$
begin
return query
select (q->>'node_name')::text, (q->'response') from jsonb_array_elements(bdr.run_on_nodes(ARRAY [nodename], command)) as q;
end;
$$ language
'plpgsql';
```

This function takes a node name and a command and runs the command on that node, returning the results as shown in this interaction:

```
select runmaint('node-one','VACUUM FULL foo');
```

```
                                                output
                    runmaint
-------------------------------------------------------
 (node-one,"{""command_status"": ""VACUUM""}")
```

You can break up the response by using `select * from`:

```
select * from runmaint('node-one','VACUUM FULL foo');
```

```
                                                output
    node          |         response
------------------+--------------------------
 node-one         | {"command_status": "VACUUM"}
(1 row)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

14 Connection Manager

PGD 5.9 includes a back-ported version of Connection Manager as an optional feature that is disabled by default. Starting in PGD 6.0, Connection Manager replaces PGD proxy.

Connection Manager in 5.9 allows for seamless upgrades to PGD 6 by having the necessary infrastructure in place. It also gives you the opportunity to test the Connection Manager in non-production environments before a full production upgrade.

- Overview covers the new features and benefits of the Connection Manager.
- Authentication covers how authentication works with the Connection Manager.
- Configuration details the configuration options available and how to set them.
- Load Balancing how to use load balancing with the Connection Manager.
- Monitoring covers the tables and HTTP endpoints available for monitoring.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

14.1 Connection Manager overview

About Connection Manager

Connection Manager is a new background worker for EDB Postgres Distributed (PGD) 6.0 that simplifies the process of connection to PGD clusters by providing a single point of entry for client applications. It replaces the PGD 5.x proxy solution with a tightly integrated approach that exposes read-write, read-only, and HTTP status network interfaces in PGD.

PGD 5.9 includes a back-ported version of Connection Manager as an optional feature that is disabled by default in order to allow for seamless upgrades to PGD 6 by having the necessary infrastructure in place.

Connection Manager is fully integrated into PGD and is designed to work seamlessly with the existing PGD architecture. Every PGD data node has a Connection Manager instance that listens for incoming connections and routes them to the appropriate node in the cluster, specifically the current write leader in the cluster. It also provides a read-only interface for applications that only need to read data from the cluster.

Using Connection Manager

Connection Manager follows the Postgres server's configuration by default. There are three ports, the read-write port, the read-only port, and the HTTP port. The read-write port is used for write operations, while the read-only port is used for read operations. The HTTP port is used for monitoring and management purposes.

The read-write port is, by default, set to the Postgres port + 1000 (usually 6432). The read-only port is set to the Postgres port + 1001 (usually 6433). The HTTP port is set to the Postgres port + 1002 (usually 6434).

To use Connection Manager, you need to configure your client applications to connect to the read-write or read-only port of the Connection Manager instance running on the data node. The Connection Manager will then route the connection to the appropriate node in the cluster.

Note that the Connection Manager is not a replacement for a load balancer. It is designed to work in conjunction with a load balancer to provide a complete solution for managing connections to PGD clusters. The Connection Manager provides a simple and efficient way to manage connections to PGD clusters, while the load balancer provides additional features such as load balancing and failover. See Load Balancing for more information.

Enabling Connection Manager

Connection Manager is an optional feature for PGD 5.9 and is disabled by default. To enable it, choose the section below that corresponds to your current configuration: whether or not you have an active PGD Proxy setup.

Enabling Connection Manager for PGD 5.9 with an active PGD Proxy configuration

Use the following steps to move from PGD Proxy to Connection Manager:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

1. From one of the PGD 5.9 nodes, run the following query to ensure that SCRAM hashes of all user passwords are the same across all nodes:

```
DO $$
DECLARE
    rec
RECORD;
    command TEXT;    password TEXT;
BEGIN
    FOR rec IN SELECT rolname,rolpassword FROM pg_authid WHERE rolcanlogin = true AND rolpassword like 'SCRAM-
SHA%'
    LOOP
        password :=
rec.rolpassword;
        command := 'ALTER ROLE ' || quote_ident(rec.rolname) || ' WITH ENCRYPTED PASSWORD ' ||
quote_literal(password);
        EXECUTE
command;
    END LOOP;
END;
$$;
SELECT bdr.wait_slot_confirm_lsn(NULL,
NULL);
```

> **Note**
>
> No new users should be added to 5.9 after executing this. If they are added, run the query again. The above block does not change the passwords, it just ensure SCRAM hashes are same across the cluster on all nodes.

2. Fence a node in this cluster with `pgd node <node-name> set-option route_fence true` so that it does not become the write leader.

3. Set the configuration parameter `bdr.enable_builtin_connection_manager` to `true`:

```
SET bdr.enable_builtin_connection_manager to
'TRUE';
```

4. Restart the server.

5. Stop PGD Proxy running on the server.

6. Restart the server. It will start with the Connection Manager running on the default port. If the proxy read and write ports were different, the Connection Manager port read and write ports can be changed to be the same as proxy by `bdr.alter_node_group_option()`.

7. Unfence the node. This node can now accept connections from the user and route to the write leader via Connection Manager.

8. Repeat this for each node in the cluster. This will ensure all nodes are now routing via Connection Manager.

Enabling Connection Manager for PGD 5.9 with no active PGD Proxy configuration

To enable Connection Manager in an environment with no active PGD Proxy configuration, log in to any node in the cluster using `psql` to connect to the `bdrdb` database (use the `enterprisedb` user for EPAS), and run:

```
SELECT bdr.alter_node_group_option('dc1', 'enable_raft', 'true');
SELECT bdr.alter_node_group_option('dc1', 'enable_proxy_routing', 'true');
```

Set the configuration parameter `bdr.enable_builtin_connection_manager` to `true` and restart the server:

```
SET bdr.enable_builtin_connection_manager to
'TRUE';
```

You must run the commands for all the subgroups in the cluster where you want Connection Manager enabled.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Read-Only connections

Connecting a client to the read-only port provided by connection manager restricts that connection to read-only operations in a similar way to using `SET TRANSACTION READ ONLY` would, except that it's not possible to change it to read-write. The `transaction_read_only` GUC correctly reports `on` in these connections.

TLS and Authentication

The Connection Manager performs TLS termination and pre-authentication. The configuration for these is taken directly from Postgres `pg_hba.conf` file, and server key configuration are used transparently. See authentication for more information.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

14.2 Connection Manager Authentication

Connection Manager's authentication is configured through Postgres's own `pg_hba.conf` file. Connection Manager uses the same authentication methods as Postgres.

> **Note**
>
> For Connection Manager authentication to work correctly, set or change role passwords only while connected to a PGD-enabled database with `bdr.role_replication` set to `on`. A password set or changed while disconnected from the PGD-enabled database, or with `bdr.role_replication` set to `off`, doesn't replicate, and Connection Manager can then fail to authenticate that role.

Connection Manager connection types

Connection Manager supports the following connection types in `pg_hba.conf`:

- `host` - TCP/IP connections
- `hostssl` - TCP/IP connections with SSL
- `hostnossl` - TCP/IP connections without SSL

Connection Manager authentication methods

Connection Manager supports the following authentication methods in `pg_hba.conf`:

- `trust` - No authentication
- `reject` - Reject the connection
- `md5` - MD5 password authentication
- `scram-sha-256` - SCRAM-SHA-256 password authentication
- `cert` - SSL certificate authentication
- `ldap` - Authenticate using an LDAP server

> **Note**
>
> Connection Manager needs to be able to authenticate to the PGD nodes as the client user. Configure the `pg_hba.conf` file on each PGD node to accept connections originating from other PGD nodes for replication and internal communications.
>
> When using a certificate authentication method, the Connection Manager presents its server key. You must configure the PGD node to accept this certificate from the Connection Manager address.

Connection Manager authentication options

Connection Manager also supports regular expression matching for the `user` and `database` fields in `pg_hba.conf`. This allows you to specify a pattern for matching user and database names, making it easier to manage authentication for multiple users and databases.

Group membership checks are also supported. This allows you to specify a group of users that can connect to the database, rather than specifying each user individually.

Connection Manager supports `pg_ident.conf` for user identity mapping when using the `cert` authentication method.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

TLS and client certificates

Connection Manager offers TLS to clients only when `ssl` is `on` in `postgresql.conf`, as Postgres does. With `ssl` on, both `ssl_cert_file` and `ssl_key_file` must be set. If clients connect to Connection Manager over TLS, set `ssl = on` before upgrading to PGD 5.10.0. Earlier releases offered TLS whenever the certificate and key files existed, whatever `ssl` was set to. The HTTPS status port (`use_https`) isn't affected and keeps using `ssl_cert_file` and `ssl_key_file` whatever `ssl` is set to.

When you use `cert` authentication, Connection Manager verifies client certificates the way Postgres does:

- It checks each client certificate against `ssl_ca_file`, `ssl_crl_file`, and `ssl_crl_dir`, and applies the `clientcert` option of the `pg_hba.conf` rule. If `ssl_ca_file` isn't set, `cert` authentication fails, as it does in Postgres.
- If Connection Manager can't parse a certificate revocation list (CRL), for example a version 1 CRL, it refuses client certificates and logs a `WARNING`. Other authentication methods keep working.
- The HTTPS status port doesn't ask clients for a certificate.

Unsupported pg_hba.conf rules

Where a rule is not supported by Connection Manager, it will be logged as a warning and ignored.

LDAP authentication notes and constraints

Connection Manager supports the same LDAP authentication features as PostgreSQL, with the following key constraints:

- Connection Manager does not use the OpenLDAP library for communication with the LDAP server. As a result, standard OpenLDAP configuration files (such as `ldap.conf` or `.ldaprc`) and environment variables are ignored.
- Connection Manager validates LDAP server certificates by default when using LDAPS or LDAP StartTLS. The necessary CA certificate for the LDAP server's SSL certificate must be in the system trust-store.
- Suppress validation of the LDAP server's SSL certificate by setting `LDAPTLS_REQCERT=never` environment variable. Other values for this variable are ignored.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

14.3 Configuring Connection Manager

Configuring Connection Manager

Connection Manager takes its configuration from the PGD Group options for the group the node is a member of.

These can be configured using the `bdr.alter_node_group_option` command, or using the `pgd group set-option` command.

The following options are available for configuring Connection Manager:

Option	Default	Description
listen_address	Postgres's listen address	which local addresses it should listen on for client connections
read_write_port	Postgres's port + 1000 (usually 6432)	which port to listen on for read-write connections
read_only_port	read_write_port + 1 (usually 6433)	which port to listen on for read-only connections
http_port	read_write_port + 2 (usually 6434)	which http port to listen for REST API calls (for integration purposes)
use_https	false	whether http listener should use HTTPS, if enabled, the server certificate is used to TLS
read_write_max_client_connections	max_connection	maximum read-write client connections allowed, defaults to max_connections
read_write_max_server_connections	max_connections	maximum read-write connections that will be opened to server
read_only_max_client_connections	max_connections	maximum read-only client connections allowed
read_only_max_server_connections	max_connections	maximum read-only connections that will be opened to server
read_write_consensus_timeout	0 (immediate action)	how long to wait on loss of consensus before read-write connections are no longer accepted
read_only_consensus_timeout	0 (immediate action)	how long to wait on loss of consensus before read-only connections are no longer accepted.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

14.4 Load Balancing with Connection Manager

You can use an external load balancer to distribute traffic across multiple Connection Manager instances. Treat the Connection Manager ports as you would with any other Postgres port, but use the read-write ports for write traffic and the read-only ports for read traffic.

Depending on your load balancer, you have a number of options for how to configure it.

Connection Manager routing

If you want the Connection Manager to route traffic to the write leader, connect to the Connection Manager's read-write port. The Connection Manager routes the traffic to the write leader of the node group the node is a member of.

HAProxy example: Connection Manager routing

With HAProxy, you can use a configuration similar to the following example to load balance between three Connection Manager instances, each running on different hosts and ports. Read-write traffic to haproxy port 5010 is directed to Connection Manager's read-write port (default 6432) on any one of the nodes. Read-only traffic to haproxy port 5011 is directed to Connection Manager's read-only port (default 6433). Port 5011 is used for read-only traffic, which is distributed across the nodes in a round-robin fashion.

```
global
    maxconn 100

defaults
    log     global
    mode    tcp
    retries 2
    timeout client 30m
    timeout connect 4s
    timeout server 30m
    timeout check 5s

listen stats
    mode http
    bind 127.0.0.1:7000
    stats enable
    stats uri /

listen read-write
    bind *:5010
    option pgsql-check user checkuser postgres
    default-server inter 3s fall 3 rise 2 on-marked-down shutdown-sessions
    server node1 host1:6432 maxconn 100 check port 6432
    server node2 host2:6432 maxconn 100 check port 6432
    server node3 host3:6432 maxconn 100 check port 6432

listen read-only
    balance roundrobin
    bind *:5011
    option pgsql-check user checkuser postgres
    default-server inter 3s fall 3 rise 2 on-marked-down shutdown-sessions
    server node1 host1:6433 maxconn 100 check port 6433
    server node2 host2:6433 maxconn 100 check port 6433
    server node3 host3:6433 maxconn 100 check port 6433
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Direct routing

You may want to connect directly to the nodes in your cluster, bypassing Connection Manager. To leverage Connection Manager in this scenario, consult its HTTP endpoints for information about the nodes in your cluster, such as which node is the write leader. Then connect directly to that node. You can use the `/node/is-read-write` endpoint to check if a node is the write leader and the `/node/is-read-only` endpoint to get information about the read-only pool.

The main reason to configure the load balancer like this is if you want a layer 4 tcp proxy that looks more like a traditional Postgres connection, where TLS termination and authentication happen on the server. Connection Manager provides a layer 7 proxy, which handles TLS termination and authentication at the proxy level, that is, within Connection Manager.

The drawback to this approach is that you won't benefit from Connection Manager's features, especially its ability to enforce read-only connections to the read-only pool. Connections will be directed to the non-write-leader nodes rather than the write leader.

See Monitoring Connection Manager for more information on the available endpoints.

HAProxy example: Direct routing

This example shows a configuration that uses HAProxy to route traffic directly to the nodes based on their health status. The configuration checks the health of the nodes by querying the `/node/is-read-write` and `/node/is-read-only` endpoints and routes traffic accordingly. As in the previous example, this example routes read-write traffic on port 5010 to the node that's the write leader and read-only traffic on port 5011 to the nodes that are read-only.

```
global
    maxconn 100

defaults
    log     global
    mode    tcp
    retries 2
    timeout client 30m
    timeout connect 4s
    timeout server 30m
    timeout check 5s

listen stats
    mode http
    bind 127.0.0.1:7000
    stats enable
    stats uri /

listen read-write
    bind *:5010
    option httpchk GET /node/is-read-write
    http-check expect string true
    default-server inter 3s fall 3 rise 2 on-marked-down shutdown-sessions
    server node1 host1:5432 maxconn 100 check port 6434
    server node2 host2:5432 maxconn 100 check port 6434
    server node3 host3:5432 maxconn 100 check port 6434

listen read-only
    balance roundrobin
    bind *:5011
    option httpchk GET /node/is-read-only
    http-check expect string true
    default-server inter 3s fall 3 rise 2 on-marked-down shutdown-sessions
    server node1 host1:5432 maxconn 100 check port 6434
    server node2 host2:5432 maxconn 100 check port 6434
    server node3 host3:5432 maxconn 100 check port 6434
```

This configuration checks the health of the nodes by querying the `/node/is-read-write` and `/node/is-read-only` endpoints. It routes traffic only to nodes that are healthy and available for read-write or read-only operations, respectively.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

14.5 Monitoring the Connection Manager

You can view the status of the Connection Manager and its connections through SQL queries and HTTP endpoints.

Available SQL tables and views

The Connection Manager provides a number of tables and views that can be used to monitor the status of the Connection Manager and its connections. These include:

- `bdr.stat_activity` — which is information from `pg_stat_activity` enhanced with addition columns regarding the `connection_manager_client_addr` and `connection_manager_client_port` is the connection has come through the connection manager, and `session_read_only` if it has connected through the read-only port.
- `bdr.stat_connection_manager` — which is a view that provides statistics about the Connection Manager's status.
- `bdr.stat_connection_manager_connections` — which is a view that provides statistics about the Connection Manager's connections.
- `bdr.stat_connection_manager_node_stats` — which is a view that provides statistics about the Connection Manager on each of the data nodes.
- `bdr.stat_connection_manager_hba_file_rules` — which is a view that shows which HBA file rules for the connection manager are being used on this node.

Available HTTP/HTTPS endpoints

The Connection Manager can be monitored through the HTTP API.

Endpoints returning true/false will also return a 200 status code for true and a 503 status code for false.

The following endpoints are available:

Endpoint	Description
/connection/is-live	Is the connection manager live (listening), always returns “true”, if the manager is not running, the client will simply fail to open the connection/url
/connection/is-ready	Is the connection manager is ready, returns true(200)/false(503)
/node/is-read-write	Is this PGD node, not the connection manager but the PGD node itself, a read-write node (is it write leader), returns true(200)/false(503)
/node/is-read-only	Is this PGD node, not the connection manager but the PGD node itself, a read-only node (not the write leader), returns true(200)/false(503)node
/group/read-write-info	Returns information about the read-write pool on this instance of connection manager - a list of nodes in the pool in JSON format with node id, node name, node host, node port and node dbname. For the read-write pool, the pool only contains one entry.
/group/read-only-info	Returns information about the read-only pool on this instance of connection manager - a list of nodes in the pool in JSON format with node id, node name, node host, node port and node dbname.

Below is an example of a response body from the `/group/read-write-info` endpoint:

```
[
  {
    "id": 683485707,
    "name": "node-1",
    "host": "host-1",
    "port": 5432,
    "dbname": "pgddb"
  }
]
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Logging

All Connection Manager log messages are written to the PostgreSQL log.

The behavior of `%r` and `%h` escape sequences in log_line_prefix has been altered to log "proxy_address/client_address" and "proxy_port/client_port" respectively.

This is achieved by the proxy setting a GUC for the server connections it uses. As users can override this GUC, any security context derived from the client_address will need to be verified by referring to the full session logs.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

15 Postgres configuration

Several Postgres configuration parameters affect PGD nodes. You can set these parameters differently on each node, although we don't generally recommend it.

For PGD's own settings, see the PGD settings reference.

Postgres settings

To run correctly, PGD requires these Postgres settings:

- `wal_level` — Must be set to `logical`, since PGD relies on logical decoding.
- `shared_preload_libraries` — Must include `bdr` to enable the extension. Most other extensions can appear before or after the `bdr` entry in the comma-separated list. Don't include `pglogical` in this list.
- `track_commit_timestamp` — Must be set to `on` for conflict resolution to retrieve the timestamp for each conflicting row.

PGD requires these PostgreSQL settings to be set to appropriate values, which vary according to the size and scale of the cluster:

- `logical_decoding_work_mem` — Memory buffer size used by logical decoding. Transactions larger than this size overflow the buffer and are stored temporarily on local disk. Default is 64MB, but you can set it much higher.
- `max_worker_processes` — PGD uses background workers for replication and maintenance tasks, so you need enough worker slots for it to work correctly. The formula for the correct minimal number of workers for each database is to add together these values:
  - One per PostgreSQL instance
  - One per database on that instance
  - Four per PGD-enabled database
  - One per peer node in the PGD group
  - The number of peer nodes times the (number of writers (bdr.num_writers) plus one) You might need more worker processes temporarily when a node is being removed from a PGD group.

- `max_wal_senders` — Two needed for every peer node.
- `max_replication_slots` — Two needed for every peer node.
- `wal_sender_timeout` and `wal_receiver_timeout` — Determines how quickly a node considers its CAMO partner as disconnected or reconnected. See CAMO failure scenarios for details.

In normal running for a group with N peer nodes, PGD requires N slots and WAL senders. During synchronization, PGD temporarily uses another N-1 slots and WAL senders, so be careful to set the parameters high enough for this occasional peak demand.

With Parallel Apply turned on, the number of slots must be increased to N slots from the formula * writers. This is because `max_replication_slots` also sets the maximum number of replication origins, and some of the functionality of Parallel Apply uses an extra origin per writer.

When the decoding worker is enabled, this process requires one extra replication slot per PGD group.

Changing the `max_worker_processes`, `max_wal_senders`, and `max_replication_slots` parameters requires restarting the local node.

A legacy synchronous replication mode is supported using the following parameters. See Commit scopes for details and limitations.

- `synchronous_commit` and `synchronous_standby_names` — Affects the durability and performance of PGD replication. in a similar way to physical replication.

Time-based snapshots

`snapshot_timestamp`

Turns on the use of timestamp-based snapshots and sets the timestamp to use.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Max prepared transactions

`max_prepared_transactions`

Needs to be set high enough to cope with the maximum number of concurrent prepared transactions across the cluster due to explicit two-phase commits, CAMO, or Eager transactions. Exceeding the limit prevents a node from running a local two-phase commit or CAMO transaction and prevents all Eager transactions on the cluster. This parameter can be set only at Postgres server start.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16 PGD Proxy

Managing application connections is an important part of high availability. PGD Proxy offers a way to manage connections to the EDB Postgres Distributed cluster. It acts as a proxy layer between the client application and the Postgres database.

- PGD Proxy overview provides an overview of the PGD Proxy, its processes, and how it interacts with the EDB Postgres Distributed cluster.
- Installing the PGD Proxy service covers installation of the PGD Proxy service on a host.
- Configuring PGD Proxy details the three levels (group, node, and proxy) of configuration on a cluster that control how the PGD Proxy service behaves.
- Administering PGD Proxy shows how to switch the write leader and manage the PGD Proxy.
- Monitoring PGD Proxy looks at how to monitor PGD Proxy through the cluster and at a service level.
- Read-only routing explains how the read-only routing feature in PGD Proxy enables read scalability.
- Raft provides an overview of the Raft consensus mechanism used to coordinate PGD Proxy.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.1 EDB Postgres Distributed Proxy overview

Especially with asynchronous replication, having a consistent write leader node is important to avoid conflicts and guarantee availability for the application.

The two parts to EDB Postgres Distributed's proxy layer are:

- Proxy configuration and routing information, which is maintained by the PGD consensus mechanism.
- The PGD Proxy service, which is installed on a host. It connects to the PGD cluster, where it reads its configuration and listens for changes to the routing information.

This layer is normally installed in a highly available configuration (at least two instances of the proxy service per PGD group).

Once configured, the PGD Proxy service monitors routing changes as decided by the EDB Postgres Distributed cluster. It acts on these changes to ensure that connections are consistently routed to the correct nodes.

Configuration changes to the PGD Proxy service are made through the PGD cluster. The PGD Proxy service reads its configuration from the PGD cluster, but the proxy service must be restarted to apply those changes.

The information about currently selected write and read nodes is visible in `bdr.node_group_routing_summary`. This is a node-local view: the proxy always reads from Raft leader to get a current and consistent view.

Leader selection

The write leader is selected by the current Raft leader for the group the proxy is part of. This could be the Raft leader for a subgroup or leader for the entire cluster. The leader is selected from candidate nodes that are reachable and meet the criteria based on the configuration as described in PGD Proxy cluster configuration. To be a viable candidate, the node must have `route_writes` enabled and `route_fence` disabled and be within `route_writer_max_lag` (if enabled) from the previous leader. The candidates are ordered by their `route_priority` in descending order and by the lag from the previous leader in ascending order.

The new leader selection process is started either when there's no existing leader currently or when connectivity is lost to the existing leader. (If there's no existing write leader, it could be because there were no valid candidates or because Raft was down.)

A node is considered connected if the last Raft protocol message received from the leader isn't older than Raft election timeout (see Internal settings - Raft timeouts).

Since the Raft leader is sending heartbeat 3 times every election timeout limit, the leader node needs to miss the reply to 3 heartbeats before it's considered disconnected.

PGD Proxy cluster configuration

The PGD cluster always has at least one top-level group and one data group. PGD elects the write leader for each data group that has the `enable_proxy_routing` and `enable_raft` options set to true.

The cluster also maintains proxy configurations for each group. Each configuration has a name and is associated with a group. You can attach a proxy to a top-level group or data group. You can attach multiple proxies to each group. When a PGD Proxy service starts running on a host, it has a name in its local configuration file and it connects to a node in a group. From there, it uses the name to look up its complete configuration as stored on the group.

PGD Proxy service

The EDB Postgres Distributed Proxy (PGD Proxy) service is a process that acts as an abstraction layer between the client application and Postgres. It interfaces with the PGD consensus mechanism to get the identity of the current write leader node and redirects traffic to that node. It also optionally supports a read-only mode where it can route read-only queries to nodes that aren't the write leader, improving the overall performance of the cluster.

PGD Proxy is a TCP layer 4 proxy.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

How they work together

Upon starting, PGD Proxy connects to one of the endpoints given in the local config file. It fetches:

- DB connection information for all nodes.
- Proxy options like listen address, listen port.
- Routing details including the current write leader in default mode, read nodes in read-only mode, or both in any mode.

The endpoints given in the config file are used only at startup. After that, actual endpoints are taken from the PGD catalog's `route_dsn` field in `bdr.node_routing_config_summary`.

PGD manages write leader election. PGD Proxy interacts with PGD to get write leader change events notifications on Postgres notify/listen channels and routes client traffic to the current write leader. PGD Proxy disconnects all existing client connections on write leader change or when write leader is unavailable. Write leader election is a Raft-backed activity and is subject to Raft leader availability. PGD Proxy closes the new client connections if the write leader is unavailable.

PGD Proxy responds to write leader change events that can be categorized into two modes of operation: *failover* and *switchover*.

Automatic transfer of write leadership from the current write leader node to a new node in the event of Postgres or operating system crash is called *failover*. PGD elects a new write leader when the current write leader goes down or becomes unresponsive. Once the new write leader is elected by PGD, PGD Proxy closes existing client connections to the old write leader and redirects new client connections to the newly elected write leader.

User-controlled, manual transfer of write leadership from the current write leader to a new target leader is called *switchover*. Switchover is triggered through the PGD CLI group set-leader command. The command is submitted to PGD, which attempts to elect the given target node as the new write leader. Similar to failover, PGD Proxy closes existing client connections and redirects new client connections to the newly elected write leader. This is useful during server maintenance, for example, if the current write leader node needs to be stopped for maintenance like a server update or OS patch update.

If the proxy is configured to support read-only routing, it can route read-only queries to a pool of nodes that aren't the write leader. The pool of nodes is maintained by the PGD cluster and proxies listen for changes to the pool. When the pool changes, the proxy updates its routing configuration and starts routing read-only queries to the new pool of nodes and disconnecting existing client connections to nodes that have left the pool.

Consensus grace period

PGD Proxy provides the `consensus_grace_period` proxy option that can be used to configure the routing behavior upon loss of a Raft leader. PGD Proxy continues to route to the current write leader (if it's available) for this duration. If the new Raft leader isn't elected during this period, the proxy stops routing. If set to `0s`, PGD Proxy stops routing immediately.

The main purpose of this option is to allow users to configure the write behavior when the Raft leader is lost. When the Raft leader isn't present in the cluster, it's not always guaranteed that the current write leader seen by the proxy is the correct one. In some cases, like network partition in the following example, it's possible that the two write leaders may be seen by two different proxies attached to the same group, increasing the chances of write conflicts. If this isn't the behavior you want, then you can set the previously mentioned `consensus_grace_period` to 0s. This setting configures the proxy to stop routing and closes existing open connections immediately when it detects the Raft leader is lost.

Network partition example

Consider a 3-data-node group with a proxy on each data node. In this case, if the current write leader gets network partitioned or isolated, then the data nodes present in the majority partition elect a new write leader. If `consensus_grace_period` is set to a non-zero value, for example, `10s`, then the proxy present on the previous write leader continues to route writes for this duration.

In this case, if the grace period is kept too high, then writes continue to happen on the two write leaders. This condition increases the chances of write conflicts.

Having said that, most of the time, upon loss of the current Raft leader, the new Raft leader gets elected by BDR within a few seconds if more than half of the nodes (quorum) are still up. Hence, if the Raft leader is down but the write leader is still up, then proxy can be configured to allow routing by keeping `consensus_grace_period` to a non-zero, positive value. The proxy waits for the Raft leader to get elected during this period before stopping routing. This might be helpful in some cases where availability is more important.

Read consensus grace period

Similar to the `consensus_grace_period`, a `read_consensus_grace_period` option is available for read-only routing. This option can be used to configure the routing behavior upon loss of a Raft leader for read-only queries. PGD Proxy continues to route to the current read nodes for this duration. If the new Raft leader isn't elected during this period, the proxy stops routing read-only queries. If set to `0s`, PGD Proxy stops routing read-only queries immediately.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Multi-host connection strings

The PostgreSQL C client library (libpq) allows you to specify multiple host names in a single connection string for simple failover. This ability is also supported by client libraries (drivers) in some other programming languages. It works well for failing over across PGD Proxy instances that are down or inaccessible.

If an application connects to a proxy instance that doesn't have access to a write leader, the connection will simply fail. No other hosts in the multi-host connection string will be tried. This behavior is consistent with the behavior of PostgreSQL client libraries with other proxies like HAProxy or pgbouncer. Access to a write leader requires the group the instance is part of has been able to select a write leader for the group.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.2 Installing PGD Proxy

Installing PGD Proxy

You can use two methods to install and configure PGD Proxy to manage an EDB Postgres Distributed cluster. The recommended way to install and configure PGD Proxy is to use the EDB Trusted Postgres Architect (TPA) utility for cluster deployment and management.

Installing through TPA

If the PGD cluster is being deployed through TPA, then TPA installs and configures PGD Proxy automatically as per the recommended architecture. If you want to install PGD Proxy on any other node in a PGD cluster, then you need to attach the pgd-proxy role to that instance in the TPA configuration file. Also set the `bdr_child_group` parameter before deploying, as this example shows. See Trusted Postgres Architect for more information.

```
- Name: proxy-
a1
  location:
a
  node: 4
  role:
  - pgd-proxy
  vars:
    bdr_child_group: group_a
  volumes:
  - device_name:
/dev/sdf
    volume_type: none
```

Configuration

PGD Proxy connects to the PGD database for its internal operations, like getting proxy options and getting write leader details. Therefore, it needs a list of endpoints/dsn to connect to PGD nodes. PGD Proxy expects these configurations in a local config file `pgd-proxy-config.yml`. Following is a working example of the `pgd-proxy-config.yml` file:

```
log-level: debug
cluster:
  name: cluster-
name
  endpoints:
    - "host=bdr-a1 port=5432 dbname=bdrdb
user=pgdproxy"
    - "host=bdr-a3 port=5432 dbname=bdrdb
user=pgdproxy"
    - "host=bdr-a2 port=5432 dbname=bdrdb
user=pgdproxy"
  proxy:
    name: "proxy-a1"
```

By default, in the cluster created through TPA, `pgd-proxy-config.yml` is located in the `/etc/edb/pgd-proxy` directory. PGD Proxy searches for `pgd-proxy-config.yml` in the following locations. Precedence order is high to low.

1. `/etc/edb/pgd-proxy` (default)
2. `$HOME/.edb/pgd-proxy`

If you rename the file or move it to another location, specify the new name and location using the optional `-f` or `--config-file` flag when starting a service. See the sample service file.

You can set the log level for the PGD Proxy service using the top-level config parameter `log-level`, as shown in the sample config. The valid values for `log-level` are `debug`, `info`, `warn`, and `error`.

`cluster.endpoints` and `cluster.proxy.name` are mandatory fields in the config file. PGD Proxy always tries to connect to the first endpoint in the list. If it fails, it tries the next endpoint, and so on.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

PGD Proxy uses endpoints given in the local config file only at proxy startup. After that, PGD Proxy retrieves the list of actual endpoints (route_dsn) from the PGD Proxy catalog. Therefore, the node option `route_dsn` must be set for each PGD Proxy node. See route_dsn for more information.

Configuring health check

PGD Proxy provides HTTP(S) health check APIs. If the health checks are required, you can enable them by adding the following configuration parameters to the pgd-proxy configuration file. By default, it's disabled.

```
cluster:
  name: cluster-
name
  endpoints:
    - "host=bdr-a1 port=5432 dbname=bdrdb user=pgdproxy
"
    - "host=bdr-a3 port=5432 dbname=bdrdb user=pgdproxy
"
    - "host=bdr-a2 port=5432 dbname=bdrdb user=pgdproxy
"
  proxy:
    name: "proxy-a1"
    endpoint: "host=proxy-a1 port=6432 dbname=bdrdb user=pgdproxy
"
    http:
      enable: true
      host: "0.0.0.0"
      port: 8080
      secure: false
      cert_file: ""
      key_file: ""
      probes:
        timeout:
10s
```

You can enable the API by adding the config `cluster.proxy.http.enable: true`. When enabled, an HTTP server listens on the default port, `8080`, with a 10-second `timeout` and no HTTPS support.

To enable HTTPS, set the config parameter `cluster.proxy.http.secure: true`. If it's set to `true`, you must also set the `cert_file` and `key_file`.

The `cluster.proxy.endpoint` is an endpoint used by the proxy to connect to the current write leader as part of its checks. When `cluster.proxy.http.enable` is `true`, `cluster.proxy.endpoint` must also be set. It can be the same as BDR noderouting_dsn, where host is `listen_address` and port is `listen_port` proxy options. If required, you can add connection string parameters in this endpoint, like `sslmode`, `sslrootcert`, `user`, and so on.

PGD Proxy user

The database user specified in the endpoint doesn't need to be a superuser. Typically, in the TPA environment, pgdproxy is an OS user as well as a database user with the bdr_superuser role.

PGD Proxy service

We recommend running PGD Proxy as a systemd service. The `pgd-proxy` service unit file is located at `/etc/systemd/system/pgd-proxy.service` by default. Following is the sample service file created by TPA:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
[Unit]
Description=PGD Proxy

[Service]
Type=simple
User=pgdproxy
Group=pgdproxy
Restart=on-failure
RestartSec=1s
ExecStart=/usr/bin/pgd-proxy -f /etc/edb/pgd-proxy/pgd-proxy-config.yml
StandardOutput=syslog
StandardError=syslog
SyslogIdentifier=pgd-proxy

[Install]
WantedBy=multi-user.target
```

Use these commands to manage the `pgd-proxy` service:

```
systemctl status pgd-
proxy
systemctl stop pgd-proxy
systemctl restart pgd-proxy
```

Installing manually

You can manually install PGD Proxy on any Linux machine using `.deb` and `.rpm` packages available from the PGD repository. The package name is `edb-pgd5-proxy`. For example:

```
# for
Debian
sudo apt-get install edb-pgd5-proxy
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.3 PGD Proxy configuration

Group-level configuration

Configuring the routing is done either through SQL interfaces or through PGD CLI.

You can enable routing decisions by calling the `bdr.alter_node_group_option()` function. For example:

```
SELECT bdr.alter_node_group_option('region1-group', 'enable_proxy_routing', 'true')
```

You can disable it by setting the same option to `false`.

Additional group-level options affect the routing decisions:

- `route_writer_max_lag` — Maximum lag in bytes of the new write candidate to be selected as write leader. If no candidate passes this, no writer is selected automatically.
- `route_reader_max_lag` — Maximum lag in bytes for a node to be considered a viable read-only node (PGD 5.5.0 and later).

Node-level configuration

Set per-node configuration of routing using `bdr.alter_node_option()`. The available options that affect routing are:

- `route_dsn` — The dsn used by proxy to connect to this node.
- `route_priority` — Relative routing priority of the node against other nodes in the same node group. Used only when electing a write leader.
- `route_fence` — Determines whether the node is fenced from routing. When fenced, the node can't receive connections from PGD Proxy. It therefore can't become the write leader or be available in the read-only node pool. Replication is not impacted.
- `route_writes` — Determines whether writes can be routed to this node, that is, whether the node can become write leader.
- `route_reads` — Determines whether read-only connections can be routed to this node (PGD 5.5.0 and later).

Proxy-level configuration

You can configure the proxies using SQL interfaces.

Creating and dropping proxy configurations

You can add a proxy configuration using `bdr.create_proxy`. For example, `SELECT bdr.create_proxy('region1-proxy1', 'region1-group');` creates the default configuration for a proxy named `region1-proxy1` in the PGD group `region1-group`.

The name of the proxy given here must be same as the name given in the proxy configuration file.

You can remove a proxy configuration using `SELECT bdr.drop_proxy('region1-proxy1')`. Dropping a proxy deactivates it.

Altering proxy configurations

You can configure options for each proxy using the `bdr.alter_proxy_option()` function.

The available options are:

- `listen_address` — Address for the proxy to listen on.
- `listen_port` — Port for the proxy to listen on.
- `max_client_conn` — Maximum number of connections for the proxy to accept.
- `max_server_conn` — Maximum number of connections the proxy can make to the Postgres node.
- `server_conn_timeout` — Connection timeout for server connections.
- `server_conn_keepalive` — Keepalive interval for server connections.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- `consensus_grace_period` — Duration for which proxy continues to route even upon loss of a Raft leader. If set to `0s`, proxy stops routing immediately.
- `read_listen_address` — Address for the read-only proxy to listen on.
- `read_listen_port` — Port for the read-only proxy to listen on.
- `read_max_client_conn` — Maximum number of connections for the read-only proxy to accept.
- `read_max_server_conn` — Maximum number of connections the read-only proxy can make to the Postgres node.
- `read_server_conn_keepalive` — Keepalive interval for read-only server connections.
- `read_server_conn_timeout` — Connection timeout for read-only server connections.
- `read_consensus_grace_period` — Duration for which read-only proxy continues to route even upon loss of a Raft leader.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.4 Administering PGD Proxy

Switching the write leader

Switching the write leader is a manual operation that you can perform to change the node that's the write leader. It can be useful when you want to perform maintenance on the current write leader node or when you want to change the write leader for any other reason. When changing write leader, there are two modes: `strict` and `fast`. In `strict` mode, the lag is checked before switching the write leader. It waits until the lag is less than `route_writer_max_lag` before starting the switchover. This is the default. In `fast` mode, the write leader is switched immediately. You can also set a timeout parameter to specify the time when the method is strict. (Defaults to 30s)

> **Note**
>
> The set-leader operation is not a guaranteed operation. If, due to a timeout or for other reasons, the switch to the given target node fails, PGD may elect another node as write leader in its place. This other node can include the current write leader node. PGD always tries to elect a new write leader if the set-leader operation fails.

Using SQL

You can perform a switchover operation that explicitly changes the node that's the write leader to another node.

Use the `bdr.routing_leadership_transfer()` function.

For example, to switch the write leader to node `node1` in group `group1`, use the following SQL command:

```
SELECT bdr.routing_leadership_transfer('group1', 'node1','strict','10s');
```

This command switches the write leader using `strict` mode and waits for up to 10 seconds for the switchover to complete. Those are default settings, so you can omit them, as follows:

```
SELECT bdr.routing_leadership_transfer('group1', 'node1');
```

Using PGD CLI

You can use the `group set-leader` command to perform a switchover operation.

For example, to switch the write leader from node `node1` to node `node2` in group `group1`, use the following command:

```
pgd group group1 set-leader node1 --strict --timeout
10s
```

This command switches the write leader using `strict` mode and waits for up to 10 seconds for the switchover to complete in strict mode. Those are default settings, so you can omit them, as follows:

```
pgd group group1 set-leader
node1
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.5 Monitoring PGD Proxy

You cam monitor proxies at the cluster and group level or at the process level.

Monitoring through the cluster

Using SQL

The current configuration of every group is visible in the `bdr.node_group_routing_config_summary` view.

The `bdr.node_routing_config_summary` view shows current per-node routing configuration.

`bdr.proxy_config_summary` shows per-proxy configuration.

Monitoring at the process level

Proxy health check

PGD Proxy provides the following HTTP(S) health check API endpoints. The API endpoints respond to `GET` requests. You need to enable and configure the endpoints before using them. See Configuration.

Endpoint	Description
`/health/is-ready`	Checks if the proxy can successfully route connections to the current write leader.
`/health/is-live`	Checks if the proxy is running.
`/health/is-write-ready`	Checks if the proxy can successfully route connections to the current write leader (PGD 5.5.0 and later).
`/health/is-read-only-ready`	Checks if the proxy can successfully route read-only connections (PGD 5.5.0 and later).

Readiness

On receiving a valid `GET` request:

- When in default (write) mode, the proxy checks if it can successfully route connections to the current write leader.
- When in read-only mode, the proxy checks if it can successfully route read-only connections.
- When in any mode, the proxy first checks if it can successfully route connections to the current write leader. If it can, the check is successful. If not, it checks if it can route a read-only connection. If it can, the check is successful. If not, the check fails.

If the check returns successfully, the API responds with a body containing `true` and an HTTP status code `200 (OK)`. Otherwise, it returns a body containing `false` with the HTTP status code `500 (Internal Server Error)`.

Liveness

Liveness checks return either `true` with HTTP status code `200 (OK)` or an error. They never return `false` because the HTTP server listening for the request is stopped if the PGD Proxy service fails to start or exits.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Proxy log location

Proxies also write logs to system logging where they can be monitored with other system services.

syslog

- Debian based - `/var/log/syslog`
- Red Hat based - `/var/log/messages`

Use the `journalctl` command to filter and view logs for troubleshooting PGD Proxy. The following are sample commands for quick reference:

```
journalctl -u pgd-proxy -n100 -f
journalctl -u pgd-proxy --since today
journalctl -u pgd-proxy --since "10 min
ago"
journalctl -u pgd-proxy --since "2022-10-20 16:21:50" --until "2022-10-20 16:21:55"
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.6 Read-only routing with PGD Proxy

Background

By default, PGD Proxy routes connections to the currently selected write leader in the cluster. This allows the write traffic conflicts to be rapidly and consistently resolved. Just routing everything to a single node, the write leader, is a natural fit for traditional high-availability deployments where system throughput is typically limited to the throughput of what a single node can handle.

But for some use cases, this behavior also means that clients that are only querying the data are also placing a load on the current write leader. It's possible this read-only workload could be equally well served by one of the non-write-leader nodes in the cluster.

If you could move traffic that has read-only queries to the non-write leader nodes, you could, at least in theory, handle a throughput which could be a multiple of a single nodes capability. An approach like this, though, usually requires changes to applications so that they are aware of details of cluster topology and the current node status to detect the write leader.

Read-only routing in PGD Proxy

From PGD 5.5.0, PGD Proxy addresses this requirement to utilize read capacity while minimizing application exposure to the cluster status. It does this by offering a new `read_listen_port` on proxies that complement the existing listen port. Proxies can be configured with either or both of these ports.

When a proxy is configured with a `read_listen_port`, connections to that particular port are routed to available data nodes that aren't the current write leader. If an application only queries and reads from the database, using a `read_listen_port` ensures that your queries aren't answered by the write leader.

Because PGD Proxy is a TCP Layer 4 proxy, it doesn't interfere with traffic passing through it. That means that it can't detect attempts to write passing through the `read_listen_port` connections. As it can't distinguish between a SELECT or an INSERT, it's possible to write through a read-only port.

The active-active nature of PGD means that any write operation will be performed and replicated, and conflict resolution may or may not have to take place. It's up to the application to avoid this and make sure that it uses only `read_listen_ports` for read-only traffic.

Where available, the problem can be mitigated on the client side by passing `default_transaction_read_only=on` in the connection string or equivalent for the driver in use.

Valid read-only nodes

Only data nodes that aren't the write leader are valid as read-only nodes. For reference, the following node types aren't eligible to be a read-only node:

- Witness nodes, because they don't contain data
- Logical standbys, because they're standbys and prioritize replicating
- Subscriber-only nodes

Creating a proxy configuration

SQL proxy creation functions in PGD take an optional `proxy_mode` parameter. You can set this parameter to one of the following values:

- `default` — This is the default value. It creates a proxy that can handle traffic that follows the write leader on port 6432.
- `read-only` — This option creates a read-only proxy that routes traffic to nodes that aren't the write leader. It handles this read-only traffic only on port 6433.
- `any` — This option creates create a proxy that can handle both read-only and write-leader-following traffic on separate ports: 6432 for write-leader-following traffic and 6433 for read-only traffic.

PGD CLI proxy creation passes the `proxy_mode` value using the `--proxy-mode` flag.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Creating a read-only proxy

Using SQL

To create a new read-only proxy, use the `bdr.create_proxy` function:

```
SELECT bdr.create_proxy('proxy-ro1','group-a','read-only');
```

This command creates a read-only proxy named `proxy-ro1` in group `group-a`. By default, it listens on port 6433 for read-only traffic.

Using PGD CLI

To create a new read-only proxy, use the `pgd create-proxy` command with the optional `--proxy-mode` flag set to `read-only`:

```
pgd create-proxy --proxy-name proxy-ro1 --node-group group-a --proxy-mode read-
only
```

Configuring running proxies

> **Note**
>
> After changing a proxy's configuration, restart the proxy to make the changes take effect.

You activate read-only routing on a proxy by setting the `read_listen_port` option to a port number. This port number is the port on which the proxy will listen for read-only traffic. If the proxy already has a `listen_port` set, then the proxy will listen on both ports, routing read/write and read-only traffic respectively on each port. This is equivalent to creating a proxy with `proxy-mode` set to `any`.

If you set a `read_listen_port` on a proxy and then set the `listen_port` to 0, the proxy listens only on the `read_listen_port` and routes only read-only traffic. This is equivalent to creating a proxy with `proxy-mode` set to `read-only`. The configuration elements related to the read/write port are cleared (set to null).

If you set a `listen_port` on a proxy and then set the `read_listen_port` to 0, the proxy listens only on the `listen_port` and routes only read/write traffic. This is equivalent to creating a proxy with `proxy-mode` set to `default`. The configuration elements related to the read-only port are cleared (set to null).

Configuring using SQL

To configure a read-only proxy port on a proxy, use the `bdr.alter_proxy_options` function:

```
SELECT bdr.alter_proxy_options('proxy-
a1','read_listen_port','6433');
```

This command configures a read-only proxy port on port 6433 in the proxy-a1 configuration.

To remove the read-only proxy, set the port to 0:

```
SELECT bdr.alter_proxy_options('proxy-
a1','read_listen_port','0');
```

Configuring using PGD CLI

To configure a read-only proxy port on a proxy, use the `pgd alter-proxy` command:

```
pgd set-proxy-options --proxy-name proxy-a1 --option
read_listen_port=6433
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

This command configures a read-only proxy port on port 6433 in the proxy-a1 configuration.

To remove the read-only proxy, set the port to 0:

```
pgd set-proxy-options --proxy-name proxy-a1 --option
read_listen_port=0
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.7 Proxies, Raft, and Raft subgroups

PGD manages its metadata using a Raft model where a top-level group spans all the data nodes in the PGD installation. A Raft leader is elected by the top-level group and propagates the state of the top-level group to all the other nodes in the group.

> **What is Raft?**
>
> Raft is an industry-accepted algorithm for making decisions though achieving *consensus* from a group of separate nodes in a distributed system.

For certain operations in the top-level group, it's essential that a Raft leader must be both established and connected. Examples of these operations include adding and removing nodes and allocating ranges for galloc sequences.

It also means that an absolute majority of nodes in the top-level group (one half of them plus one) must be able to reach each other. So, in a top-level group with five nodes, at least three of the nodes must be reachable by each other to establish a Raft leader.

Proxy routing

One function that also uses Raft is proxy routing. Proxy routing requires that the proxies can coordinate writing to a data node within their group of nodes. This data node is the write leader. If the write leader goes offline, the proxies need to be able to switch to a new write leader, selected by the data nodes, to maintain continuity for connected applications.

You can configure proxy routing on a per-node group basis in PGD 5, but the recommended configurations are *global* and *local* routing.

Global routing

Global routing uses the top-level group to manage the proxy routing. All writable data nodes (not witness or subscribe-only nodes) in the group are eligible to become write leader for all proxies. Connections to proxies within the top-level group will be routed to data nodes within the top-level group.

With global routing, there's only one write leader for the entire top-level group.

Local routing

Local routing uses subgroups, often mapped to locations, to manage the proxy routing within the subgroup. Local routing is often used for geographical separation of writes. It's important for them to continue routing even when the top-level consensus is lost.

That's because PGD allows queries and asynchronous data manipulation (DMLs) to work even when the top-level consensus is lost. But using the top-level consensus, as is the case with global routing, means that new write leaders can't be elected when that consensus is lost. Local groups can't rely on the top-level consensus without adding an independent consensus mechanism and its added complexity.

PGD 5 introduced subgroup Raft support to elegantly address this issue. Subgroup Raft support allows the subgroups in a PGD top-level group to elect the leaders they need independently. They do this by forming devolved Raft groups that can elect write leaders independent of other subgroups or the top-level Raft consensus. Connections to proxies in the subgroup then route to data nodes within the subgroup.

With local routing, there's a write leader for each subgroup.

More information

- Raft subgroups and TPA shows how Raft subgroups can be enabled in PGD when deploying with Trusted Postgres Architect.
- Raft subgroups and PGD CLI shows how the PGD CLI reports on the presence and status of Raft subgroups.
- Migrating to Raft subgroups is a guide to migrating existing installations and enabling Raft subgroups without TPA.
- Raft elections in depth looks in detail at how the write leader is elected using Raft.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.7.1 Creating Raft subgroups using TPA

The `TPAexec configure` command enables Raft subgroups if the `--enable_proxy_routing local` option is set. TPA uses the term *locations* to reflect the common use case of subgroups that map to physical/regional domains. When the configuration is generated, the location name given is stored under the generated group name, which is based on the location name.


Creating Raft subgroups using TPA

This example creates a two-location cluster with three data nodes in each location. The nodes in each location are part of a PGD Raft subgroup for the location.

The top-level group's name is `pgdgroup`.

The top-level group has two locations: `us_east` and `us_west`. These locations are mapped to two subgroups: `us_east_subgroup` and `us_west_subgroup`.

Each location has four nodes: three data nodes and a barman backup node. The three data nodes also cohost PGD Proxy. The configuration can be visualized like this:



The barman nodes don't participate in the subgroup and, by extension, the Raft group. They're therefore not shown. This diagram is a snapshot of a potential state of the cluster with the West Raft group having selected west_1 as write leader and west_2 as its own Raft leader. On the East, east_1 is write leader while east_3 is Raft leader. The entire cluster is contained within the top-level Raft group. There, west_3 is currently Raft leader.

To create this configuration, you run:

```
tpaexec configure pgdgroup --architecture PGD-Always-ON --location-names us_east us_west --data-nodes-per-location 3
--epas 16 --no-redwood --enable_proxy_routing local --hostnames-from hostnames.txt
```

Where `hostnames.txt` contains:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
east1
east2
east3
eastbarman
west1
west2
west3
westbarman
```

The configuration file

The generated `config.yml` file has a `bdr_node_groups` section that contains the top-level group `pgdgroup` and the two subgroups `us_east_subgroup` and `us_west_subgroup`. Each of those subgroups has a location set (`us_east` and `us_west`) and two other options that are set to true:

- `enable_raft`, which activates the subgroup Raft in the subgroup
- `enable_proxy_routing`, which enables the pgd_proxy routers to route traffic to the subgroup's write leader

Here's an example generated by the sample tpaexec command:

```
cluster_vars:
  apt_repository_list: []
  bdr_database: bdrdb
  bdr_node_group: pgdgroup
  bdr_node_groups:
  - name: pgdgroup
  - name: us_east_subgroup
    options:
      enable_proxy_routing: true
      enable_raft: true
      location: us_east
    parent_group_name: pgdgroup
  - name: us_west_subgroup
    options:
      enable_proxy_routing: true
      enable_raft: true
      location: us_west
    parent_group_name: pgdgroup
  bdr_version: '5'
```

Every node instance has an entry in the instances list. In that entry, `bdr_child_group` appears in the variables section, set to the subgroup the node belongs to. Here's an example generated by the sample tpaexec command:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
instances:
- Name: east1
  backup: eastbarman
  location: us_east
  node: 1
  role:
  - bdr
  - pgd-proxy
  vars:
    bdr_child_group: us_east_subgroup
    bdr_node_options:
      route_priority: 100
- Name: east2
  location: us_east
  node: 2
  role:
  - bdr
  - pgd-proxy
  vars:
    bdr_child_group: us_east_subgroup
    bdr_node_options:
      route_priority: 100
- Name: east3
  location: us_east
  node: 3
  role:
  - bdr
  - pgd-proxy
  vars:
    bdr_child_group: us_east_subgroup
    bdr_node_options:
      route_priority: 100
- Name: eastbarman
  location: us_east
  node: 4
  role:
  - barman
```

The one node in this location that doesn't have a `bdr_child_group` setting is the barman node because it doesn't participate in the Raft decision-making process.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.7.2 Working with Raft subgroups and PGD CLI

You can view the status of your nodes and subgroups with the pgd CLI command. The examples here assume a cluster as configured in Creating Raft subgroups with TPA.

Viewing nodes with pgd

The pgd command is `show-nodes`.

```
pgd nodes list
```

output

```
Node Name Group Name Node Kind Join State Node Status
--------- ---------- --------- ---------- ------------
east1     us_east    data       ACTIVE    Up
east2     us_east    data       ACTIVE    Up
east3     us_east    data       ACTIVE    Up
west1     us_west    data       ACTIVE    Up
west2     us_west    data       ACTIVE    Up
west3     us_west    data       ACTIVE    Up
```

Viewing groups (and subgroups) with pgd

To show the groups in a PGD deployment, along with their names and some attributes, use the PGD CLI command `groups list.`

```
pgd groups list
```

output

```
Group Name Parent Group Name Group Type Nodes
---------- ----------------- ---------- -----
pgdgroup                     global     0
us_east    pgdgroup          data       3
us_west    pgdgroup          data       3
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.7.3 Migrating to Raft subgroups

You can introduce Raft subgroups in a running PGD installation.

Migrating to Raft subgroups (using SQL only)

To enable Raft subgroups to an existing cluster, these configuration steps are needed:

- Identify the top-level group for all nodes in the PGD cluster. An existing cluster already has a top-level group that all nodes belong to.
- Create a subgroup for each location. Use `bdr.create_node_group` with a `parent_group_name` argument that gives the top-level group as its value.
- Add each node at each location to their location's subgroup using `bdr.switch_node_group()`.
- Alter each of the location's subgroups to enable Raft for the group. Use `bdr.alter_node_group_option()`, setting the `enable_raft` option to `true`.

Enabling subgroup Raft node group (using SQL only)

```
SELECT bdr.alter_node_group_option('$group_name', 'enable_raft', 'true');
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

16.7.4 Raft elections in depth

The selection of a write leader in PGD relies on PGD's Raft mechanism. The Raft mechanism is completely internal to PGD's BDR Postgres extension and operates transparently. The nodes within a group begin by establishing a Raft leader within the nodes of the group.

Node interaction

With the Raft leader established, the leader then queries the catalog to see if a write leader for proxy routing was designated.

If no write leader is designated, the Raft leader takes steps to designate a new write leader. The process starts by querying all the nodes in the group to establish their state. The resulting list of nodes is then filtered for ineligible nodes (for example, witness nodes) and prioritized. The first/top entry on the list is then set as the new write leader in the Raft log.

Raft leader elections and PreVote

A node that is cut off from its group, for example by a flapping network link, keeps raising its Raft term while it's isolated. When it reconnects, its higher term forces the healthy leader to step down and starts an unnecessary election. Until the election ends, the group has no Raft leader and no write leader.

With PreVote, a node first asks the other voting nodes whether they would vote for it, without raising its own term. It starts a real election only if a majority would. An isolated node never gets that majority, so its term stays low and it rejoins the group without disturbing the leader. Granting a PreVote doesn't change which node the voter treats as the Raft leader.

PreVote needs no configuration and you can't turn it off. It's active once every node in the group runs PGD 5.10 or later, because the group then negotiates Raft protocol version 5011. Until the last node is upgraded, the group uses ordinary elections. To check, look at the `Protocol Version` column of `pgd raft show` or the `protocol_version` column of `bdr.group_raft_details`.

> **Note**
>
> In PGD 5.10.0, PreVote applies to the Raft instance of the top-level group. Raft subgroups still use ordinary elections.


Proxy interaction

All proxies initially connect any data node in their group. This behavior allows them to query the catalog for the current write leader and begin routing connections to that node.

They connect to the Raft leader and listen for changes to the catalog entry for write leader. When notified of a change in write leader, they reconfigure routing and send connections to the new write leader.

Both the node and proxy interaction are shown on the following sequence diagram. Two nodes and one proxy are involved, coordinating which node will be write leader and the proxy waiting to learn which node is write leader.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.



Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

17 Backup and recovery

PGD is designed to be a distributed, highly available system. If one or more nodes of a cluster are lost, the best way to replace them is to clone new nodes directly from the remaining nodes.

The role of backup and recovery in PGD is to provide for disaster recovery (DR), such as in the following situations:

- Loss of all nodes in the cluster
- Significant, uncorrectable data corruption across multiple nodes as a result of data corruption, application error, or security breach

Logical backup and restore

You can use pg_dump, sometimes referred to as *logical backup*, normally with PGD.

Temporary postgresql.conf settings

First, temporarily set the following settings in `postgresql.conf`:

```
# Increase from the default of `1GB` to something large, but still a
# fraction of your disk space since the non-WAL data must also fit.
# This decreases the frequency of checkpoints.
max_wal_size = 100GB

# Increase the amount of memory for building indexes. Default is
# 64MB. For example, 1GB assuming 128GB total RAM.
maintenance_work_mem = 1GB

# Increase the receiver and sender timeout from 1 minute to 1hr to
# allow large transactions through.
wal_receiver_timeout = 1h
wal_sender_timeout = 1h

# Increase the number of writers to make better use of parallel
# apply. Default is 2. Make sure this isn't overriden lower by the
# node group config num_writers setting.
bdr.writers_per_subscription = 5

# Increase Raft-related election timeouts with default values of 6s
# and 3s.
bdr.raft_global_election_timeout = 20s
bdr.raft_group_election_timeout = 10s

# Increase the size of the shared memory queue used by the receiver to
# send data to the writer process from the default 1MB.
bdr.writer_input_queue_size = 32MB
```

Additionally:

- Make sure the default bdr.streaming_mode = 'auto' is not overridden so that transactions are streamed.
- Make sure any session or postgresql.conf settings listed above are not overriden by node group-level settings in general.

Now continue with pg_dump and pg_restore.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

pg_dump / pg_restore

In order to reduce the risk of global lock timeouts, we recommend dumping pre-data, data, and post-data separately. For example:

```
pg_dump -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB -v --exclude-schema='"bdr"' --exclude-extension='"bdr"' --
section=pre-data -Fc -f pgd-pre-data.dump
pg_dump -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB -v --exclude-schema='"bdr"' --exclude-extension='"bdr"' --
section=data -Fc -f pgd-data.dump
pg_dump -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB -v --exclude-schema='"bdr"' --exclude-extension='"bdr"' --
section=post-data -Fc -f pgd-post-data.dump
```

And restore by directly executing these SQL files on a node (do not run these on the connection manager port):

```
PGOPTIONS="-cbdr.commit_scope=local" pg_restore -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB --section=pre-data -f
pgd-pre-data.dump
PGOPTIONS="-cbdr.commit_scope=local" pg_restore -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB --section=data -f pgd-
data.dump
psql -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB -c 'SELECT bdr.wait_slot_confirm_lsn(NULL, NULL)'
PGOPTIONS="-cbdr.commit_scope=local" pg_restore -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB --section=post-data -f
pgd-post-data.dump
psql -h $PG_HOST -p $PG_PORT -U $PG_USER -d $PGD_DB -c 'SELECT bdr.wait_slot_confirm_lsn(NULL, NULL)'
```

After which point the dump will be restored on all nodes in the cluster.

In contrast if you do not split sections out with a naive pg_dump and pg_restore, the restore will likely fail with a global lock timeout.

If you still get global lock timeouts with pg_restore, add `-cbdr.ddl_locking=off` to `PGOPTIONS`.

If you choose to run pg_restore with `-j` / `--jobs` you will need to increase `max_worker_processes` and `max_parallel_maintenance_workers` by the same amount.

Prefer restoring to a single node cluster

Especially when initially setting up a cluster from a Postgres dump, we recommend you restore to a cluster with a single PGD node. Then run `pgd node setup` for each node you want in the cluster which will do a physical join that uses `bdr_init_physical` under the hood.

Sequences

pg_dump dumps both local and global sequences as if they were local sequences. This behavior is intentional, to allow a PGD schema to be dumped and ported to other PostgreSQL databases. This means that sequence-kind metadata is lost at the time of dump, so a restore effectively resets all sequence kinds to the value of `bdr.default_sequence_kind` at time of restore.

To create a post-restore script to reset the precise sequence kind for each sequence, you might want to use a SQL script like this:

```
SELECT 'SELECT bdr.alter_sequence_set_kind(''''||
       nspname||'.'||relname||''','''||seqkind||''');'
FROM bdr.sequences
WHERE seqkind != 'local';
```

If you run pg_dump using `bdr.crdt_raw_value = on`, then you can reload the dump only with `bdr.crdt_raw_value = on`.

Technical Support recommends the use of physical backup techniques for backup and recovery of PGD.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Physical backup and restore

You can take physical backups of a node in an EDB Postgres Distributed cluster using standard PostgreSQL software, such as Barman.

You can perform a physical backup of a PGD node using the same procedure that applies to any PostgreSQL node. A PGD node is just a PostgreSQL node running the BDR extension.

Consider these specific points when applying PostgreSQL backup techniques to PGD:

- PGD operates at the level of a single database, while a physical backup includes all the databases in the instance. Plan your databases to allow them to be easily backed up and restored.
- Backups make a copy of just one node. In the simplest case, every node has a copy of all data, so you need to back up only one node to capture all data. However, the goal of PGD isn't met if the site containing that single copy goes down, so the minimum is at least one node backup per site (with many copies, and so on).
- However, each node might have unreplicated local data, or the definition of replication sets might be complex so that all nodes don't subscribe to all replication sets. In these cases, backup planning must also include plans for how to back up any unreplicated local data and a backup of at least one node that subscribes to each replication set.

Restore

While you can take a physical backup with the same procedure as a standard PostgreSQL node, it's slightly more complex to restore the physical backup of a PGD node.

EDB Postgres Distributed cluster failure or seeding a new cluster from a backup

The most common use case for restoring a physical backup involves the failure or replacement of all the PGD nodes in a cluster, for instance in the event of a data center failure.

You might also want to perform this procedure to clone the current contents of a EDB Postgres Distributed cluster to seed a QA or development instance.

In that case, you can restore PGD capabilities based on a physical backup of a single PGD node, optionally plus WAL archives:

- If you still have some PGD nodes live and running, fence off the host you restored the PGD node to, so it can't connect to any surviving PGD nodes. This practice ensures that the new node doesn't confuse the existing cluster.
- Restore a single PostgreSQL node from a physical backup of one of the PGD nodes.
- If you have WAL archives associated with the backup, create a suitable `postgresql.conf`, and start PostgreSQL in recovery to replay up to the latest state. You can specify an alternative `recovery_target` here if needed.
- Start the restored node, or promote it to read/write if it was in standby recovery. Keep it fenced from any surviving nodes!
- Clean up any leftover PGD metadata that was included in the physical backup.
- Fully stop and restart the PostgreSQL instance.
- Add further PGD nodes with the standard procedure based on the `bdr.join_node_group()` function call.

Cleanup of PGD metadata

To clean up leftover PGD metadata:

1. Drop the PGD node using `bdr.drop_node`.
2. Fully stop and restart PostgreSQL (important!).

Cleanup of replication origins

You must explicitly remove replication origins with a separate step because they're recorded persistently in a system catalog. They're therefore included in the backup and in the restored instance. They aren't removed automatically when dropping the BDR extension because they aren't explicitly recorded as its dependencies.

To track progress of incoming replication in a crash-safe way, PGD creates one replication origin for each remote master node. Therefore, for each node in the previous cluster run this once:

```
SELECT pg_replication_origin_drop('bdr_dbname_grpname_nodename');
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

You can list replication origins as follows:

```
SELECT * FROM pg_replication_origin;
```

Those created by PGD are easily recognized by their name.

Cleanup of replication slots

If a physical backup was created with `pg_basebackup`, replication slots are omitted from the backup.

Some other backup methods might preserve replications slots, likely in outdated or invalid states. Once you restore the backup, use these commands to drop all replication slots:

```
SELECT pg_drop_replication_slot(slot_name)
FROM pg_replication_slots;
```

If you have a reason to preserve some slots, you can add a `WHERE slot_name LIKE 'bdr%'` clause, but this is rarely useful.

> **Warning**
>
> Never use these commands to drop replication slots on a live PGD node

Eventual consistency

The nodes in an EDB Postgres Distributed cluster are *eventually consistent* but not *entirely consistent*. A physical backup of a given node provides point-in-time recovery capabilities limited to the states actually assumed by that node.

The following example shows how two nodes in the same EDB Postgres Distributed cluster might not (and usually don't) go through the same sequence of states.

Consider a cluster with two nodes, `N1` and `N2`, that's initially in state `S`. If transaction `W1` is applied to node `N1`, and at the same time a non-conflicting transaction `W2` is applied to node `N2`, then node `N1` goes through the following states:

```
(N1)   S  -->  S + W1  -->  S + W1 + W2
```

Node `N2` goes through the following states:

```
(N2)   S  -->  S + W2  -->  S + W1 + W2
```

That is, node `N1` *never* assumes state `S + W2`, and node `N2` likewise never assumes state `S + W1`. However, both nodes end up in the same state `S + W1 + W2`. Considering this situation might affect how you decide on your backup strategy.

Point-in-time recovery (PITR)

The previous example showed that the changes are also inconsistent in time. `W1` and `W2` both occur at time `T1`, but the change `W1` isn't applied to `N2` until `T2`.

PostgreSQL PITR is designed around the assumption of changes arriving from a single master in COMMIT order. Thus, PITR is possible by scanning through changes until one particular point in time (PIT) is reached. With this scheme, you can restore one node to a single PIT from its viewpoint, for example, `T1`. However, that state doesn't include other data from other nodes that committed near that time but had not yet arrived on the node. As a result, the recovery might be considered to be partially inconsistent, or at least consistent for only one replication origin.

With PostgreSQL PITR, you can use the standard syntax:

```
recovery_target_time = T1
```

PGD allows for changes from multiple masters, all recorded in the WAL log for one node, separately identified using replication origin identifiers.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

PGD allows PITR of all or some replication origins to a specific point in time, providing a fully consistent viewpoint across all subsets of nodes.

Thus for multi-origins, you can view the WAL stream as containing multiple streams all mixed up into one larger stream. There's still just one PIT, but that's reached as different points for each origin separately.

The WAL stream is read until requested origins have found their PIT. All changes are applied up until that point, except that any transaction records aren't marked as committed for an origin after the PIT on that origin is reached.

You end up with one LSN "stopping point" in WAL, but you also have one single timestamp applied consistently, just as you do with single-origin PITR.

Once you reach the defined PIT, a later one might also be set to allow the recovery to continue, as needed.

After the desired stopping point is reached, if the recovered server will be promoted, shut it down first. Move the LSN forward to an LSN value higher than used on any timeline on this server using `pg_resetwal`. This approach ensures that there are no duplicate LSNs produced by logical decoding.

In the specific example shown, `N1` is restored to `T1`. It also includes changes from other nodes that were committed by `T1`, even though they weren't applied on `N1` until later.

To request multi-origin PITR, use the standard syntax in the `postgresql.conf` file:

```
recovery_target_time = T1
```

You need to specify the list of replication origins that are restored to `T1` in one of two ways. You can use a separate `multi_recovery.conf` file by way of a new parameter, `recovery_target_origins`:

```
recovery_target_origins = '*'
```

Or you can specify the origin subset as a list in `recovery_target_origins`:

```
recovery_target_origins = '1,3'
```

The local WAL activity recovery to the specified `recovery_target_time` is always performed implicitly. For origins that aren't specified in `recovery_target_origins`, recovery can stop at any point, depending on when the target for the list mentioned in `recovery_target_origins` is achieved.

In the absence of the `multi_recovery.conf` file, the recovery defaults to the original PostgreSQL PITR behavior that's designed around the assumption of changes arriving from a single master in COMMIT order.

> **Note**
>
> This feature is available only with EDB Postgres Extended. Barman doesn't create a `multi_recovery.conf` file.

Monitoring

Use the following queries to check on the progress of the restore process.

```
SELECT pg_size_pretty(pg_database_size('bdrdb'));
```

The above query shows the database size on the restoring node. The size should grow as the restore makes progress and approaches the size of the original node. However, due to bloat, logical restores are always a little smaller than the original.

```
SELECT * FROM bdr.node_replication_rates;
```

The above query shows the rate of replication. However, the progress info can be misleading for big transactions; lag and progress will appear to stair-step.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
SELECT
  application_name,

state,

wait_event_type,

wait_event,
  now() - state_change AS
state_change_ago
FROM

pg_stat_activity
WHERE
  application_name LIKE
'%pg_restore%';
```

The above query shows information on what pg_restore is doing, if it's blocked/waiting (on what is waiting) or working, and changing its status continuously.

Check the following views to see issues with replication slots, accumulated lag, broken replication, etc.

- pg_catalog.pg_stat_replication_slots
- pg_catalog.pg_replication_slots
- bdr.node_slots

And use `bdr.stat_subscription` to see statistics for each subscription, for example to check on parallel apply or transaction stream.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

18 Security and roles

EDB Postgres Distributed allows a PGD cluster to be administered without giving access to the stored data by design. It achieves this through the use of roles and controlled access to system objects.

- Roles introduces the roles that PGD predefines for controlling access to PGD functionality.
- Role management discusses how roles are managed on multi-database nodes and new nodes.
- PGD predefined roles details the specific privileges of the PGD roles.
- Roles and replication explains how PGD replication interacts with roles and privileges.
- Access control explains how tables, functions, catalog objects and triggers interact with PGD roles and Postgres attributes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

18.1 Roles

Configuring and managing PGD doesn't require superuser access and we recommend that you don't use superuser access. Instead, the privileges required to administer PGD are split across the following predefined roles.

Role	Description
bdr_superuser	The highest-privileged role, having access to all PGD tables and functions.
bdr_read_all_stats	The role having read-only access to the tables, views, and functions, sufficient to understand the state of PGD.
bdr_monitor	Includes the privileges of bdr_read_all_stats, with some extra privileges for monitoring.
bdr_application	The minimal privileges required by applications running PGD.
bdr_read_all_conflicts	Can view all conflicts in `bdr.conflict_history`.

These roles are named to be analogous to PostgreSQL's `pg_` predefined roles.

The PGD `bdr_` roles are created when the BDR extension is installed. See PGD predefined roles for more details of the privileges each role has.

Managing PGD doesn't require that administrators have access to user data.

Arrangements for securing information about conflicts are discussed in Logging conflicts to a table.

You can monitor conflicts using the `bdr.conflict_history_summary` view.

> **The BDR extension and superuser access**
>
> The one exception to the rule of not needing superuser access is in the management of PGD's underlying BDR extension. Only superusers can create the BDR extension. However, if you want, you can set up the `pgextwlist` extension and configure it to allow a non-superuser to create a BDR extension.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

18.2 Role management

Users are global objects in a PostgreSQL instance. A `CREATE ROLE` command or its alias `CREATE USER` is replicated automatically if it's executed in a PGD replicated database. If a role or user is created in a non-PGD, unreplicated database, the role exists only for that PostgreSQL instance. `GRANT ROLE` and `DROP ROLE` work the same way, replicating only if applied to a PGD-replicated database.

> **Note**
>
> Remember that a user in Postgres terms is simply a role with login privileges.

Role rule - No un-replicated roles

If you do create a role or user in a non-PGD, unreplicated database, it's especially important that you do not make an object in the PGD-replicated database rely on that role. It will break the replication process, as PGD cannot replicate a role that is not in the PGD-replicated database.

You can disable this automatic replication behavior by turning off the `bdr.role_replication` setting, but we don't recommend that.

> **Note**
>
> For Connection Manager authentication to work correctly, set or change role passwords only while connected to a PGD-enabled database with `bdr.role_replication` set to `on`. A password set or changed while disconnected from the PGD-enabled database, or with `bdr.role_replication` set to `off`, doesn't replicate, and Connection Manager can then fail to authenticate that role.

Roles for new nodes

New PGD nodes that are added using `bdr_init_physical` will automatically replicate the roles from other nodes of the PGD cluster.

Starting with PGD 5.9.0, when a PGD node is manually joined to a PGD group without using bdr_init_physical, existing roles are automatically copied to the newly joined node. This means that you no longer need to create roles manually on the new node before joining it to the group.

When roles are copied to a new node, if there are existing roles (or tablespaces) with the same name, the new node's existing roles (or tablespaces) will be updated to share the same settings (including passwords) as the roles (or tablespaces) on the source node in the join operation.

Connections and roles

When allocating a new PGD node, the user supplied in the DSN for the `local_dsn` argument of `bdr.create_node` and the `join_target_dsn` of `bdr.join_node_group` are used frequently to refer to, create, and manage database objects.

PGD is carefully written to prevent privilege escalation attacks even when using a role with `SUPERUSER` rights in these DSNs.

To further reduce the attack surface, you can specify a more restricted user in these DSNs. At a minimum, such a user must be granted permissions on all nodes, such that following stipulations are satisfied:

- The user has the `REPLICATION` attribute.
- It's granted the `CREATE` permission on the database.
- It inherits the bdr_superuser role.
- It owns all database objects to replicate, either directly or from permissions from the owner roles.

Also, if any non-default extensions (excluding the BDR extension) are present on the source node, and any of these can be installed only by a superuser, a superuser must create these extensions manually on the join target node. Otherwise the join process will fail.

In PostgreSQL 13 and later, you can identify the extensions requiring superuser permission and that must be manually installed. On the source node, execute:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
    SELECT name, (trusted IS FALSE AND superuser) AS
superuser_only
      FROM
pg_available_extension_versions
     WHERE installed AND name != 'bdr';
```

Once all nodes are joined, to continue to allow DML and DDL replication, you can further reduce the permissions to the following:

- The user has the `REPLICATION` attribute.
- It inherits the bdr_superuser role.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

18.3 PGD predefined roles

PGD predefined roles are created when the BDR extension is installed. After BDR extension is dropped from a database, the roles continue to exist. You need to drop them manually if dropping is required.

bdr_superuser

This is a role for an admin user that can manage anything PGD related. It allows you to separate management of the database and table access. Using it allows you to have a user that can manage the PGD cluster without giving them PostgreSQL superuser privileges.

Privileges

- ALL PRIVILEGES ON ALL TABLES IN SCHEMA BDR
- ALL PRIVILEGES ON ALL ROUTINES IN SCHEMA BDR

bdr_read_all_stats

This role provides read access to most of the tables, views, and functions that users or applications may need to observe the statistics and state of the PGD cluster.

Privileges

`SELECT` privilege on:

- `bdr.autopartition_partitions`
- `bdr.autopartition_rules`
- `bdr.ddl_epoch`
- `bdr.ddl_replication`
- `bdr.global_consensus_journal_details`
- `bdr.global_lock`
- `bdr.global_locks`
- `bdr.group_camo_details`
- `bdr.local_consensus_state`
- `bdr.local_node_summary`
- `bdr.node`
- `bdr.node_catchup_info`
- `bdr.node_catchup_info_details`
- `bdr.node_conflict_resolvers`
- `bdr.node_group`
- `bdr.node_local_info`
- `bdr.node_peer_progress`
- `bdr.node_replication_rates`
- `bdr.node_slots`
- `bdr.node_summary`
- `bdr.replication_sets`
- `bdr.replication_status`
- `bdr.sequences`
- `bdr.stat_activity`
- `bdr.stat_relation`
- `bdr.stat_subscription` *deprecated*
- `bdr.state_journal_details`
- `bdr.subscription`
- `bdr.subscription_summary`
- `bdr.tables`
- `bdr.taskmgr_local_work_queue`
- `bdr.taskmgr_work_queue`
- `bdr.worker_errors` *deprecated*
- `bdr.workers`
- `bdr.writers`
- `bdr.xid_peer_progress`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

EXECUTE privilege on:

- `bdr.bdr_edition` *deprecated*
- `bdr.bdr_version`
- `bdr.bdr_version_num`
- `bdr.decode_message_payload`
- `bdr.get_consensus_status`
- `bdr.get_decoding_worker_stat`
- `bdr.get_global_locks`
- `bdr.get_min_required_replication_slots`
- `bdr.get_min_required_worker_processes`
- `bdr.get_raft_status`
- `bdr.get_relation_stats`
- `bdr.get_slot_flush_timestamp`
- `bdr.get_sub_progress_timestamp`
- `bdr.get_subscription_stats`
- `bdr.lag_control`
- `bdr.lag_history`
- `bdr.node_catchup_state_name`
- `bdr.node_kind_name`
- `bdr.peer_state_name`
- `bdr.pglogical_proto_version_ranges`
- `bdr.show_subscription_status`
- `bdr.show_workers`
- `bdr.show_writers`
- `bdr.stat_get_activity`
- `bdr.wal_sender_stats`
- `bdr.worker_role_id_name`

bdr_monitor

This role provides read access to any tables, views, and functions that users or applications may need to monitor the PGD cluster. It includes all the privileges of the `bdr_read_all_stats` role.

Privileges

All privileges from `bdr_read_all_stats` plus the following additional privileges:

`SELECT` privilege on:

- `bdr.group_raft_details`
- `bdr.group_replslots_details`
- `bdr.group_subscription_summary`
- `bdr.group_versions_details`
- `bdr.raft_instances`

`EXECUTE` privilege on:

- `bdr.get_raft_instance_by_nodegroup`
- `bdr.monitor_camo_on_all_nodes`
- `bdr.monitor_group_raft`
- `bdr.monitor_group_versions`
- `bdr.monitor_local_replslots`
- `bdr.monitor_raft_details_on_all_nodes`
- `bdr.monitor_replslots_details_on_all_nodes`
- `bdr.monitor_subscription_details_on_all_nodes`
- `bdr.monitor_version_details_on_all_nodes`
- `bdr.node_group_member_info`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

bdr_application

This role is designed for applications that require access to PGD features, objects, and functions such as sequences, CRDT datatypes, CAMO status functions, or trigger management functions.

Privileges

`EXECUTE` privilege on:

- All functions for column_timestamps datatypes
- All functions for CRDT datatypes
- `bdr.alter_sequence_set_kind`
- `bdr.create_conflict_trigger`
- `bdr.create_transform_trigger`
- `bdr.drop_trigger`
- `bdr.get_configured_camo_partner`
- `bdr.global_lock_table`
- `bdr.is_camo_partner_connected`
- `bdr.is_camo_partner_ready`
- `bdr.logical_transaction_status`
- `bdr.ri_fkey_trigger`
- `bdr.seq_nextval`
- `bdr.seq_currval`
- `bdr.seq_lastval`
- `bdr.trigger_get_committs`
- `bdr.trigger_get_conflict_type`
- `bdr.trigger_get_origin_node_id`
- `bdr.trigger_get_row`
- `bdr.trigger_get_type`
- `bdr.trigger_get_xid`
- `bdr.wait_for_camo_partner_queue`
- `bdr.wait_slot_confirm_lsn`
- `bdr.wait_node_confirm_lsn`

Many of these functions require additional privileges before you can use them. For example, you must be the table owner to successfully execute `bdr.alter_sequence_set_kind`. These additional rules are described with each specific function.

bdr_read_all_conflicts

PGD logs conflicts into the `bdr.conflict_history` table. Conflicts are visible only to table owners, so no extra privileges are required for the owners to read the conflict history.

If, though, it's useful to have a user that can see conflicts for all tables, you can optionally grant the role `bdr_read_all_conflicts` to that user.

Privileges

An explicit policy is set on `bdr.conflict_history` that allows this role to read the `bdr.conflict_history` table.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

18.4 Roles and replication

DDL and DML replication and users

DDL changes executed by a user are applied as that same user on each node.

DML changes to tables are replicated as the table-owning user on the target node.

By default, PGD replicates new tables with the same owner across nodes.

Differing table ownership

We recommend for the same user to own the table on each node. That's the default behavior, but you can override it. If you do, there are some things to take into account.

Consider a situation where table A is owned by user X on node1 and owned by user Y on node2. If user Y has higher privileges than user X, this might be viewed as a privilege escalation.

Since nodes can have different use cases, we do allow this scenario. But we also warn against it. If tables have different owners on different nodes, we recommend that a security administrator help to plan and audit this configuration.

Replication and row-level security

On tables with row-level security policies enabled, changes are replicated without reenforcing policies on apply. This behavior is equivalent to the changes being applied as `NO FORCE ROW LEVEL SECURITY`, even if `FORCE ROW LEVEL SECURITY` is specified. If this isn't what you want, specify a row_filter that avoids replicating all rows. We recommend that the row security policies on all nodes be identical or at least compatible, but we don't enforce this.

bdr_superuser role and replication

The user bdr_superuser controls replication for PGD and can add or remove any table from any replication set. bdr_superuser doesn't need any privileges over individual tables, nor do we recommend it. If you need to restrict access to replication set functions, you can implement restricted versions of these functions as `SECURITY DEFINER` functions and grant them to the appropriate users.

Privilege restrictions

PGD enforces additional restrictions, effectively preventing the use of DDL that relies solely on TRIGGER or REFERENCES privileges.

`GRANT ALL` still grants both TRIGGER and REFERENCES privileges, so we recommend that you state privileges explicitly. For example, use `GRANT SELECT, INSERT, UPDATE, DELETE, TRUNCATE` instead of `ALL`.

Foreign key privileges

`ALTER TABLE ... ADD FOREIGN KEY` is supported only if the user has SELECT privilege on the referenced table or if the referenced table has RLS restrictions enabled that the current user can't bypass.

This means that the REFERENCES privilege alone isn't sufficient to allow creating a foreign key with PGD. Relying solely on the REFERENCES privilege isn't typically useful since it makes the validation check execute using triggers rather than a table scan. It's typically too expensive to use successfully.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

18.5 Access control

Catalog tables

System catalog and information schema tables are always excluded from replication by PGD.

In addition, tables owned by extensions are excluded from replication.

PGD functions and operators

All PGD functions are exposed in the `bdr` schema. Any calls to these functions must be schema qualified, rather than putting `bdr` in the search_path.

All PGD operators are available by way of the `pg_catalog` schema to allow users to exclude the `public` schema from the search_path without problems.

Granting privileges on catalog objects

Administrators must not grant explicit privileges on catalog objects such as tables, views, and functions. Manage access to those objects by granting one of the roles described in PGD default roles.

This requirement is a consequence of the flexibility that allows joining a node group even if the nodes on either side of the join don't have the exact same version of PGD and therefore of the PGD catalog.

More precisely, if privileges on individual catalog objects were explicitly granted, then the `bdr.join_node_group()` procedure might fail because the corresponding GRANT statements extracted from the node being joined might not apply to the node that's joining.

Triggers

In PostgreSQL, both the owner of a table and anyone who was granted the TRIGGER privilege can create triggers. Triggers granted by the non-table owner execute as the table owner in PGD, which might cause a security issue. The TRIGGER privilege is seldom used, and PostgreSQL Core Team has said, "The separate TRIGGER permission is something we consider obsolescent."

PGD mitigates this problem by using stricter rules on who can create a trigger on a table:

- superuser: Can create trigggers.
- bdr_superuser: Can create triggers.
- Owner of the table: Can create triggers according to same rules as in PostgreSQL (must have EXECUTE privilege on the function used by the trigger).
- Users who have TRIGGER privilege on the table: Can create a trigger only if they use a function that's owned by the same owner as the table and they satisfy standard PostgreSQL rules. Specifically, they must have EXECUTE privilege on the function.

  If both table and function have the same owner, and the owner decides to give a user both TRIGGER privilege on the table and EXECUTE privilege on thae function. It's assumed that it's okay for that user to create a trigger on that table using this function.
- Users who have TRIGGER privilege on the table: Can also create triggers using functions that are defined with theSECURITY DEFINER clause if they have EXECUTE privilege on them.

  The SECURITY DEFINER clause makes the function always execute as the owner of the function both in standard PostgreSQL and PGD.

This logic is built on the fact that, in PostgreSQL, the owner of the trigger isn't the user who created it but the owner of the function used by that trigger.

The same rules apply to existing tables, and if the existing table has triggers that aren't owned by the owner of the table and don't use SECURITY DEFINER functions, you can't add it to a replication set.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

When PGD replication applies changes it uses the system-level default search_path only. Replica triggers, stream triggers, and index expression functions that assume other search_path settings will then fail when they execute on apply. To ensure this doesn't occur, resolve object references clearly using either the default search_path only, or set the search path for a function using `ALTER FUNCTION ... SET search_path = ...` for the functions affected. When using the default search_path, always use fully qualified references to objects, for example, schema.objectname.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

19 Monitoring

Monitoring replication setups is important to ensure that your system:

- Performs optimally
- Doesn't run out of disk space
- Doesn't encounter other faults that might halt operations

It's important to have automated monitoring in place to ensure that the administrator is alerted and can take proactive action when issues occur. For example, the administrator can be alerted if replication slots start falling badly behind.

EDB provides Postgres Enterprise Manager (PEM), which supports PGD starting with version 8.1. See Monitoring EDB Postgres Distributed for more information.

Alternatively, tools or users can make their own calls into information views and functions provided by the BDR extension. See Monitoring through SQL for details.

EDB Postgres Distributed also integrates with OpenTelemetry, allowing you to use an existing reporting setup to follow the state of the EDB Postgres Distributed cluster. See OpenTelemetry integration for details.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

19.1 OpenTelemetry integration

You can configure EDB Postgres Distributed to report monitoring information as well as traces to theOpenTelemetry collector.

EDB Postgres Distributed OTEL collector fills several resource attributes. These are attached to all metrics and traces:

- The `service.name` is configurable with the `bdr.otel_service_name` configuration setting.
- The `service.namespace` is always set to `edb_postgres_distributed`.
- The `service.instance.id` is always set to the system identifier of the Postgres instance.
- The `service.version` is set to the current version of the BDR extension loaded in the Postgresql instance.

OTEL and OLTP compatibility

For OTEL connections, the integration supports OLTP/HTTP version 1.0.0 only, over HTTP or HTTPS. It doesn't support OLTP/gRPC.

Metrics collection

Setting the configuration option `bdr.metrics_otel_http_url` to a non-empty URL enables the metric collection.

Different kinds of metrics are collected, as shown in the tables that follow.

Generic metrics

Metric name	Type	Labels	Description
pg_backends_by_state	gauge	conn_state - idle, active, idle in transaction, fastpath functioncall, idle in transaction (aborted), disabled, undefined	Number of backends in a given state
pg_oldest_xact_start	gauge		Oldest transaction start time
pg_oldest_activity_start	gauge		Oldest query start time
pg_waiting_backends	gauge	wait_type - LWLock, Lock, BufferPin, Activity, Client, Extension, IPC, Timeout, IO, ??? (for unknown)	Number of currently waiting backends by wait type
pg_start_time	gauge		Timestamp at which the server has started
pg_reload_time	gauge		Timestamp at which the server has last reloaded configuration

Replication metrics

Metric name	Type	Labels	Description
bdr_slot_sent_lag	gauge	slot_name - name of a slot	Current sent lag in bytes for each replication slot
bdr_slot_write_lag	gauge	slot_name - name of a slot	Current write lag in bytes for each replication slot
bdr_slot_flush_lag	gauge	slot_name - name of a slot	Current flush lag in bytes for each replication slot
bdr_slot_apply_lag	gauge	slot_name - name of a slot	Current apply lag in bytes for each replication slot
bdr_subscription_receive_lsn	gauge	sub_name - name of subscription	Current received LSN for each subscription
bdr_subscription_flush_lsn	gauge	sub_name - name of subscription	Current flushed LSN for each subscription
bdr_subscription_apply_lsn	gauge	sub_name - name of subscription	Current applied LSN for each subscription
bdr_subscription_receiver	gauge	sub_name - name of subscription	Whether subscription receiver is currently running (1) or not (0)

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Consensus metric

See also Monitoring Raft consensus

Metric name	Type	Labels	Description
bdr_raft_state	gauge	state_str - RAFT_FOLLOWER, RAFT_CANDIDATE, RAFT_LEADER, RAFT_STOPPED	Raft state of the consensus on this node
bdr_raft_protocol_version	gauge		Consensus protocol version used by this node
bdr_raft_leader_node	gauge		Id of a node that this node considers to be current leader
bdr_raft_nodes	gauge		Total number of nodes that participate in consensus (includes learner/non-voting nodes)
bdr_raft_voting_nodes	gauge		Number of actual voting nodes in consensus
bdr_raft_term	gauge		Current raft term this node is on
bdr_raft_commit_index	gauge		Raft commit index committed by this node
bdr_raft_apply_index	gauge		Raft commit index applied by this node

Tracing

Tracing collection to OpenTelemetry requires configuring `bdr.trace_otel_http_url` and enabling tracing using `bdr.trace_enable`.

The tracing is currently limited to only some subsystems, primarily to the cluster management functionality. The following spans can be seen in traces.

Span name	Description
create_node_group	Group creation
alter_node_group_config	Change of group config options
alter_node_config	Change of node config option
join_node_group	Node joining a group
join_send_remote_request	Join source sending the join request on behalf of the joining node
add_camo_pair	Add CAMO pair
alter_camo_pair	Change CAMO pair
remove_camo_pair	Delete CAMO pair
alter_commit_scope	Change commit scope definition (either create new or update existing)
alter_proxy_config	Change config for PGD-Proxy instance (either create new or update existing)
walmsg_global_lock_send	Send global locking WAL message
walmsg_global_lock_recv	Received global locking WAL message
ddl_epoch_apply	Global locking epoch apply (ensure cluster is synchronized enough for new epoch to start)
walmsg_catchup	Catchup during node removal WAL message
raft_send_appendentries	Internal Raft book keeping message
raft_recv_appendentries	Internal Raft book keeping message
raft_request	Raft request execution
raft_query	Raft query execution
msgb_send	Consensus messaging layer message
msgb_recv_receive	Consensus messaging layer message
msgb_recv_deliver	Consensus messaging layer message delivery
preprocess_ddl	DDL command preprocessing

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

TLS support

The metrics and tracing endpoints can be HTTP or HTTPS. You can configure paths to the CA bundle, client key, and client certificate using `bdr.otel_https_ca_path`, `bdr.otel_https_key_path`, and `bdr.otel_https_cert_path` configuration options.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

19.2 Monitoring through SQL

EDB Postgres Distributed provides several monitoring and statistics views that are specific to its distributed nature. The standard Postgres monitoring is also useful for monitoring EDB Postgres Distributed.

Monitoring overview

A PGD group consists of multiple servers, often referred to as nodes. Monitor all of the nodes to ensure the health of the whole group.

The bdr_monitor role can execute the `bdr.monitor` functions to provide an assessment of PGD health using one of three levels:

- `OK` — Often shown as green.
- `WARNING` — Often shown as yellow.
- `CRITICAL` — Often shown as red.
- `UNKNOWN` — For unrecognized situations, often shown as red.

PGD also provides dynamic catalog views that show the instantaneous state of various internal metrics. It also provides metadata catalogs that store the configuration defaults and configuration changes the user requests. Some of those views and tables are accessible by bdr_monitor or bdr_read_all_stats, but some contain user or internal information that has higher security requirements.

PGD allows you to monitor each of the nodes individually or to monitor the whole group by access to a single node. If you want to monitor each node individually, connect to each node and issue monitoring requests. If you want to monitor the group from a single node, then use the views starting with `bdr.group` since these requests make calls to other nodes to assemble a group-level information set.

If you were granted access to the `bdr.run_on_all_nodes()` function by bdr_superuser, then you can make your own calls to all nodes.

Monitoring node join and removal

By default, the node management functions wait for the join or part operation to complete. You can turn waiting off using the respective `wait_for_completion` function argument. If waiting is turned off, then to see when a join or part operation finishes, check the node state indirectly using `bdr.node_summary` and `bdr.event_summary`.

When called, the helper function `bdr.wait_for_join_completion()` causes a PostgreSQL session to pause until all outstanding node join operations area complete.

This example shows the output of a `SELECT` query from `bdr.node_summary`. It indicates that two nodes are active and another one is joining.

```
# SELECT node_name, interface_connstr, peer_state_name,
#     node_seq_id, node_local_dbname
# FROM bdr.node_summary;
-[ RECORD 1 ]-----+----------------------------------------
node_name         | node1
interface_connstr | host=localhost dbname=postgres port=7432
peer_state_name   | ACTIVE
node_seq_id       | 1
node_local_dbname | postgres
-[ RECORD 2 ]-----+----------------------------------------
node_name         | node2
interface_connstr | host=localhost dbname=postgres port=7433
peer_state_name   | ACTIVE
node_seq_id       | 2
node_local_dbname | postgres
-[ RECORD 3 ]-----+----------------------------------------
node_name         | node3
interface_connstr | host=localhost dbname=postgres port=7434
peer_state_name   | JOINING
node_seq_id       | 3
node_local_dbname | postgres
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Also, the table `bdr.node_catchup_info` gives information on the catch-up state, which can be relevant to joining nodes or parting nodes.

When a node is parted, some nodes in the cluster might not receive all the data from that parting node. So parting a node creates a temporary slot from a node that already received that data and can forward it.

The `catchup_state` can be one of the following:

```
10 = setup
20 = start
30 = catchup
40 = done
```

Monitoring the manager worker

The manager worker is responsible for many background tasks, including the managing of all the other workers. As such it is important to know what it's doing, especially in cases where it might seem stuck.

Accordingly, the `bdr.stat_worker` view provides per worker statistics for PGD workers, including manager workers. With respect to ensuring manager workers do not get stuck, the current task they are executing would be reported in their `query` field prefixed by "pgd manager:".

The `worker_backend_state` field for manager workers also reports whether the manager is idle or busy.

Monitoring Routing

Routing is a critical part of PGD for ensuring a seemless application experience and conflict avoidance. Routing changes should happen quickly, including the detections of failures. At the same time we want to have as few disruptions as possible. We also want to ensure good load balancing for use-cases where it's supported.

Monitoring all of these is important for noticing issues, debugging issues, as well as informing more optimal configurations. Accoringly, there are two main views for monitoring statistics to do with routing:

- `bdr.stat_routing_state` for monitoring the state of the connection routing with PGD Proxy uses to route the connections.
- `bdr.stat_routing_candidate_state` for information about routing candidate nodes from the point of view of the Raft leader (the view is empty on other nodes).

Monitoring Replication Peers

You use two main views for monitoring of replication activity:

- `bdr.node_slots` for monitoring outgoing replication
- `bdr.subscription_summary` for monitoring incoming replication

You can also obtain most of the information provided by `bdr.node_slots` by querying the standard PostgreSQL replication monitoring views `pg_catalog.pg_stat_replication` and `pg_catalog.pg_replication_slots`.

Each node has one PGD group slot that must never have a connection to it and is very rarely be marked as active. This is normal and doesn't imply something is down or disconnected. See Replication slots in Node Management.

Monitoring outgoing replication

You can use another view for monitoring of outgoing replication activity:

- `bdr.node_replication_rates` for monitoring outgoing replication

The `bdr.node_replication_rates` view gives an overall picture of the outgoing replication activity along with the catchup estimates for peer nodes, specifically.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
# SELECT * FROM bdr.node_replication_rates;
-[ RECORD 1 ]----+-----------
peer_node_id     | 112898766
target_name      | node1
sent_lsn         | 0/28AF99C8
replay_lsn       | 0/28AF99C8
replay_lag       | 00:00:00
replay_lag_bytes | 0
replay_lag_size  | 0 bytes
apply_rate       | 822
catchup_interval | 00:00:00
-[ RECORD 2 ]----+-----------
peer_node_id     | 312494765
target_name      | node3
sent_lsn         | 0/28AF99C8
replay_lsn       | 0/28AF99C8
replay_lag       | 00:00:00
replay_lag_bytes | 0
replay_lag_size  | 0 bytes
apply_rate       | 853
catchup_interval | 00:00:00
```

The `apply_rate` refers to the rate in bytes per second. It's the rate at which the peer is consuming data from the local node. While a peer node is reconnecting and catching up, and replication isn't yet in the `streaming` state, `replay_lag` reports an estimate: the time elapsed since the slot's last confirmed flush. Once the state becomes `streaming`, `replay_lag` reports the measured lag. To estimate how long the peer needs to catch up to the local node, use the `catchup_interval` column, which gives the approximate time required to replay the changes still pending. The other fields are also available from the `bdr.node_slots` view.

Administrators can query `bdr.node_slots` for outgoing replication from the local node. It shows information about replication status of all other nodes in the group that are known to the current node as well as any additional replication slots created by PGD on the current node.

```
# SELECT node_group_name, target_dbname, target_name, slot_name, active_pid,
#     catalog_xmin, client_addr, sent_lsn, replay_lsn, replay_lag,
#     replay_lag_bytes, replay_lag_size
# FROM bdr.node_slots;
-[ RECORD 1 ]---+----------------------------
node_group_name | bdrgroup
target_dbname   | postgres
target_name     | node3
slot_name       | bdr_postgres_bdrgroup_node3
active_pid      | 15089
catalog_xmin    | 691
client_addr     | 127.0.0.1
sent_lsn        | 0/23F7B70
replay_lsn      | 0/23F7B70
replay_lag      | [NULL]
replay_lag_bytes| 120
replay_lag_size | 120 bytes
-[ RECORD 2 ]---+----------------------------
node_group_name | bdrgroup
target_dbname   | postgres
target_name     | node2
slot_name       | bdr_postgres_bdrgroup_node2
active_pid      | 15031
catalog_xmin    | 691
client_addr     | 127.0.0.1
sent_lsn        | 0/23F7B70
replay_lsn      | 0/23F7B70
replay_lag      | [NULL]
replay_lag_bytes| 84211
replay_lag_size | 82 kB
```

Because PGD is a mesh network, to get the full view of lag in the cluster, you must execute this query on all nodes participating.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`replay_lag_bytes` reports the difference in WAL positions between the local server's current WAL write position and `replay_lsn`, the last position confirmed replayed by the peer node. `replay_lag_size` is a human-readable form of the same. It's important to understand that WAL usually contains a lot of writes that aren't replicated but still count in `replay_lag_bytes`, including, for example:

- `VACUUM` activity
- Index changes
- Writes associated with other databases on the same node
- Writes for tables that are not part of a replication set

So the lag in bytes reported here isn't the amount of data that must be replicated on the wire to bring the peer node up to date, only the amount of server-side WAL that must be processed.

Similarly, `replay_lag` isn't a measure of how long the peer node takes to catch up or how long it takes to replay from its current position to the write position at the time `bdr.node_slots` was queried. It measures the delay between when the peer confirmed the most recent commit and the current wall-clock time. We suggest that you also monitor `replay_lag_bytes` and `replay_lag_size`, or `catchup_interval` in `bdr.node_replication_rates`, for an estimate of how far behind a peer is and how long it needs to catch up.

The lag in both bytes and time doesn't advance while logical replication is streaming a transaction. It changes only when a commit is replicated. So the lag tends to "sawtooth," rising as a transaction is streamed and then falling again as the peer node commits it, flushes it, and sends confirmation. The reported LSN positions "stair-step" instead of advancing smoothly, for similar reasons.

When replication is disconnected (`active` = `'f'`), the `active_pid` column is `NULL`, as is `client_addr` and the other fields that make sense only with an active connection. The `state` field is `'disconnected'`. The `_lsn` fields are the same as the `confirmed_flush_lsn`, since that's the last position that the client is known for certain to have replayed to and saved. The `_lag` fields show the elapsed time between the most recent confirmed flush on the client and the current time. The `_lag_size` and `_lag_bytes` fields report the distance between `confirmed_flush_lsn` and the local server's current WAL insert position.

> **Note**
>
> It's normal for `restart_lsn` to be behind the other `lsn` columns. This doesn't indicate a problem with replication or a peer node lagging. The `restart_lsn` is the position that PostgreSQL's internal logical decoding must be reading WAL at if interrupted. It generally reflects the position of the oldest transaction that's not yet replicated and flushed. A very old `restart_lsn` can make replication slow to restart after disconnection and force retention of more WAL than is desirable, but it's otherwise harmless. If you're concerned, look for very long-running transactions and forgotten prepared transactions.

Monitoring incoming replication

You can monitor incoming replication (also called subscriptions) at a high level by querying the `bdr.subscription_summary` view. This query shows the list of known subscriptions to other nodes in the EDB Postgres Distributed cluster and the state of the replication worker:

```
# SELECT node_group_name, origin_name, sub_enabled, sub_slot_name,
#     subscription_status
# FROM bdr.subscription_summary;
-[ RECORD 1 ]-------+---------------------------
node_group_name     | bdrgroup
origin_name         | node2
sub_enabled         | t
sub_slot_name       | bdr_postgres_bdrgroup_node1
subscription_status | replicating
-[ RECORD 2 ]-------+---------------------------
node_group_name     | bdrgroup
origin_name         | node3
sub_enabled         | t
sub_slot_name       | bdr_postgres_bdrgroup_node1
subscription_status | replicating
```

You can further monitor subscriptions by monitoring subscription summary statistics through `bdr.stat_subscription`, and by monitoring the subscription replication receivers and subscription replication writers, using `bdr.stat_receiver` and `bdr.stat_writer`, respectively.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Monitoring WAL senders using LCR

If the decoding worker is enabled, you can monitor information about the current logical change record (LCR) file for each WAL sender using the function `bdr.wal_sender_stats()`. For example:

```
postgres=# SELECT * FROM bdr.wal_sender_stats();
   pid   | is_using_lcr |       decoder_slot_name       |              lcr_file_name
---------+--------------+-------------------------------+-------------------------------------------
 2059904 | f            |                               |
 2059909 | t            | bdr_postgres_bdrgroup_decoder | 000000000000000000000014000000000000000000
 2059916 | t            | bdr_postgres_bdrgroup_decoder | 000000000000000000000014000000000000000000
(3 rows)
```

If `is_using_lcr` is `FALSE`, `decoder_slot_name` / `lcr_file_name` is `NULL`. This is the case if the decoding worker isn't enabled or the WAL sender is serving a logical standby.

Also, you can monitor information about the decoding worker using the function `bdr.get_decoding_worker_stat()`. For example:

```
postgres=# SELECT * FROM bdr.get_decoding_worker_stat();
   pid   | decoded_upto_lsn | waiting | waiting_for_lsn
---------+------------------+---------+-----------------
 1153091 | 0/1E5EEE8        | t       | 0/1E5EF00
(1 row)
```

Monitoring PGD replication workers

All PGD workers show up in the system view `bdr.stat_activity`, which has the same columns and information content as pg_stat_activity. So this view offers these insights into the state of a PGD system:

- The wait_event column has enhanced information, if the reason for waiting is related to PGD.
- The `query` column is blank in PGD workers, except when a writer process is executing DDL, or for when a manager worker is active (in which case the entry in the `query` column will be prefixed with "`pgd manager:`").

The `bdr.workers` view shows PGD worker-specific details that aren't available from `bdr.stat_activity`.

The view `bdr.event_summary` shows the last error (if any) reported by any worker that has a problem continuing the work. This information is persistent, so it's important to note the time of the error and not just its existence. Most errors are transient, and PGD workers will retry the failed operation.

Monitoring PGD writers

Another system view, `bdr.writers`, monitors writer activities. This view shows only the current status of writer workers. It includes:

- `sub_name` to identify the subscription that the writer belongs to
- `pid` of the writer process
- `streaming_allowed` to know if the writer supports applying in-progress streaming transactions
- `is_streaming` to know if the writer is currently applying a streaming transaction
- `commit_queue_position` to check the position of the writer in the commit queue

PGD honors commit ordering by following the same commit order as happened on the origin. In case of parallel writers, multiple writers might apply different transactions at the same time. The `commit_queue_position` shows the order in which they will commit. Value `0` means that the writer is the first one to commit. Value `-1` means that the commit position isn't yet known, which can happen for a streaming transaction or when the writer isn't currently applying any transaction.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Monitoring commit scopes

Commit scopes are our durability and consistency configuration framework. As such, they affect the performance of transactions, so it is important to get statistics on them. Moreover, because in failure scenarios transactions might appear to be stuck due to the commit scope configuration, we need insight into what commit scope is being used, what it's waiting on, and so on.

Accordingly, these two views show relevant statistics about commit scopes:

- bdr.stat_commit_scope for cumulative statistics for each commit scope.
- bdr.stat_commit_scope_state for information about the current use of commit scopes by backend processes.

Monitoring global locks

The global lock, which is currently used only for DDL replication, is a heavyweight lock that exists across the whole PGD group.

There are currently two types of global locks:

- DDL lock, used for serializing all DDL operations on permanent (not temporary) objects (that is, tables) in the database
- DML relation lock, used for locking out writes to relations during DDL operations that change the relation definition

You can create either or both entry types for the same transaction, depending on the type of DDL operation and the value of the `bdr.ddl_locking` setting.

Global locks held on the local node are visible in the `bdr.global_locks` view. This view shows the type of the lock. For relation locks, it shows the relation that's being locked, the PID holding the lock (if local), and whether the lock was globally granted. In case of global advisory locks, `lock_type` column shows `GLOBAL_LOCK_ADVISORY`, and `relation` column shows the advisory keys on which the lock is acquired.

This example shows the output of `bdr.global_locks` while running an `ALTER TABLE` statement with `bdr.ddl_locking = 'all'`:

```
# SELECT lock_type, relation, pid FROM bdr.global_locks;
-[ RECORD 1 ]--------------
lock_type | GLOBAL_LOCK_DDL
relation  | [NULL]
pid       | 15534
-[ RECORD 2 ]--------------
lock_type | GLOBAL_LOCK_DML
relation  | someschema.sometable
pid       | 15534
```

See Catalogs for details on all fields, including lock timing information.

Monitoring conflicts

Replication conflicts can arise when multiple nodes make changes that affect the same rows in ways that can interact with each other. Monitor the PGD system to identify conflicts and, where possible, make application changes to eliminate the conflicts or make them less frequent.

By default, all conflicts are logged to `bdr.conflict_history`. Since this log contains full details of conflicting data, the rows are protected by row-level security to ensure they're visible only by owners of replicated tables. Owners should expect conflicts and analyze them to see which, if any, might be considered as problems to resolve.

For monitoring purposes, use `bdr.conflict_history_summary`, which doesn't contain user data. This example shows a query to count the number of conflicts seen in the current day using an efficient query plan:

```
SELECT count(*)
FROM bdr.conflict_history_summary
WHERE local_time > date_trunc('day',
current_timestamp)
  AND local_time < date_trunc('day', current_timestamp + '1
day');
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Apply statistics

PGD collects statistics about replication apply, both for each subscription and for each table.

Two monitoring views exist: `bdr.stat_subscription` for subscription statistics and `bdr.stat_relation` for relation statistics. These views both provide:

- Number of INSERTs/UPDATEs/DELETEs/TRUNCATEs replicated
- Block accesses and cache hit ratio
- Total I/O time for read/write
- Number of in-progress transactions streamed to file
- Number of in-progress transactions streamed to writers
- Number of in-progress streamed transactions committed/aborted

For relations only, `bdr.stat_relation` also includes:

- Total time spent processing replication for the relation
- Total lock wait time to acquire lock (if any) for the relation (only)

For subscriptions only, `bdr.stat_subscription` includes:

- Number of COMMITs/DDL replicated for the subscription
- Number of times this subscription has connected upstream

Tracking of these statistics is controlled by the PGD GUCs `bdr.track_subscription_apply` and `bdr.track_relation_apply`, respectively.

The following shows the example output from these:

```
# SELECT sub_name, nconnect, ninsert, ncommit, nupdate, ndelete, ntruncate,
nddl
FROM bdr.stat_subscription;
-[ RECORD 1 ]---------------------------------
-
sub_name  |
bdr_regression_bdrgroup_node1_node2
nconnect  |
3
ninsert   |
10
ncommit   |
5
nupdate   |
0
ndelete   |
0
ntruncate |
0
nddl      |
2
```

In this case, the subscription connected three times to the upstream, inserted 10 rows, and performed two DDL commands inside five transactions.

You can reset the stats counters for these views to zero using the functions `bdr.reset_subscription_stats` and `bdr.reset_relation_stats`.

PGD also monitors statistics regarding subscription replication receivers and subscription replication writers for each subscription, using `bdr.stat_receiver` and `bdr.stat_writer`, respectively.

Standard PostgreSQL statistics views

Statistics on table and index usage are normally updated by the downstream master. This is essential for the correct function ofautovacuum. If there are no local writes on the downstream master and statistics haven't been reset, these two views show corresponding results between upstream and downstream:

- `pg_stat_user_tables`
- `pg_statio_user_tables`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Note**
>
> We don't necessarily expect the upstream table statistics to be *similar* to the downstream ones. We only expect them to *change* by the same amounts. Consider the example of a table whose statistics show 1M inserts and 1M updates. When a new node joins the PGD group, the statistics for the same table in the new node show 1M inserts and zero updates. However, from that moment, the upstream and downstream table statistics change by the same amounts because all changes on one side are replicated to the other side.

Since indexes are used to apply changes, the identifying indexes on the downstream side might appear more heavily used with workloads that perform `UPDATE` and `DELETE` than non-identifying indexes are.

The built-in index monitoring views are:

- `pg_stat_user_indexes`
- `pg_statio_user_indexes`

All these views are discussed in detail in the PostgreSQL documentation on the statistics views.

Monitoring PGD versions

PGD allows running different Postgres versions as well as different BDR extension versions across the nodes in the same cluster. This capability is useful for upgrading.

The view `bdr.group_versions_details` uses the function `bdr.run_on_all_nodes()` to retrieve Postgres and BDR extension versions from all nodes at the same time. For example:

```
bdrdb=# SELECT node_name, postgres_version,
bdr_version
        FROM bdr.group_versions_details;
 node_name | postgres_version |
bdr_version
-----------+------------------+-------------
 node1     | 15.2.0           |
5.0.0
 node2     | 15.2.0           |
5.0.0
```

The recommended setup is to try to have all nodes running the same (and latest) versions as soon as possible. We recommend that the cluster doesn't run different versions of the BDR extension for too long.

For monitoring purposes, we recommend the following alert levels:

- status=UNKNOWN, message=This node is not part of any PGD group
- status=OK, message=All nodes are running same PGD versions
- status=WARNING, message=There is at least 1 node that is not accessible
- status=WARNING, message=There are node(s) running different PGD versions when compared to other nodes

The described behavior is implemented in the function `bdr.monitor_group_versions()`, which uses PGD version information returned from the view `bdr.group_version_details` to provide a cluster-wide version check. For example:

```
bdrdb=# SELECT * FROM
bdr.monitor_group_versions();
 status |
message
--------+----------------------------------------
 OK     | All nodes are running same BDR
versions
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Monitoring Raft consensus

Raft consensus must be working cluster-wide at all times. The impact of running an EDB Postgres Distributed cluster without Raft consensus working might be as follows:

- The replication of PGD data changes might still work correctly.
- Global DDL/DML locks doesn't work.
- Galloc sequences eventually run out of chunks.
- Eager Replication doesn't work.
- Cluster maintenance operations (join node, part node, promote standby) are still allowed, but they might not finish (hanging instead).
- Node statuses might not be correctly synced among the PGD nodes.
- PGD group replication slot doesn't advance LSN and thus keeps WAL files on disk.

The view `bdr.group_raft_details` uses the functions `bdr.run_on_all_nodes()` and `bdr.get_raft_status()` to retrieve Raft consensus status from all nodes at the same time. For example:

```
bdrdb=# SELECT node_id, node_name, state,
leader_id
FROM bdr.group_raft_details;
  node_id   | node_name | node_group_name |     state     |
leader_id
------------+-----------+-----------------+---------------+------------
 1148549230 | node1     | top_group       | RAFT_LEADER   |
1148549230
 3367056606 | node2     | top_group       | RAFT_FOLLOWER |
1148549230
```

Raft consensus is working correctly if all of these conditions are met:

- A valid state (`RAFT_LEADER` or `RAFT_FOLLOWER`) is defined on all nodes.
- Only one of the nodes is the `RAFT_LEADER` .
- The `leader_id` is the same on all rows and must match the `node_id` of the row where `state = RAFT_LEADER` .

From time to time, Raft consensus starts a new election to define a new `RAFT_LEADER` . During an election, there might be an intermediary situation where there's no `RAFT_LEADER` , and some of the nodes consider themselves as `RAFT_CANDIDATE` . The whole election can't take longer than `bdr.raft_global_election_timeout` (by default it's set to 6 seconds). If the query above returns an in-election situation, then wait for `bdr.raft_global_election_timeout` , and run the query again. If after `bdr.raft_global_election_timeout` has passed and some the listed conditions are still not met, then Raft consensus isn't working.

Raft consensus might not be working correctly on only a single node. For example, one of the nodes doesn't recognize the current leader and considers itself as a `RAFT_CANDIDATE` . In this case, it's important to make sure that:

- All PGD nodes are accessible to each other through both regular and replication connections (check file `pg_hba.conf`).
- PGD versions are the same on all nodes.
- `bdr.raft_global_election_timeout` is the same on all nodes.

In some cases, especially if nodes are geographically distant from each other or network latency is high, the default value of `bdr.raft_global_election_timeout` (6 seconds) might not be enough. If Raft consensus is still not working even after making sure everything is correct, consider increasing `bdr.raft_global_election_timeout` to 30 seconds on all nodes. For PGD 3.6.11 and later, setting `bdr.raft_global_election_timeout` requires only a server reload.

Given how Raft consensus affects cluster operational tasks, and also as Raft consensus is directly responsible for advancing the group slot, monitoring alert levels are defined as follows:

- status=UNKNOWN, message=This node is not part of any PGD group
- status=OK, message=Raft Consensus is working correctly
- status=WARNING, message=There is at least 1 node that is not accessible
- status=WARNING, message=There are node(s) as RAFT_CANDIDATE, an election might be in progress
- status=WARNING, message=There is no RAFT_LEADER, an election might be in progress
- status=CRITICAL, message=There is a single node in Raft Consensus
- status=CRITICAL, message=There are node(s) as RAFT_CANDIDATE while a RAFT_LEADER is defined
- status=CRITICAL, message=There are node(s) following a leader different than the node set as RAFT_LEADER

The described behavior is implemented in the function `bdr.monitor_group_raft()` , which uses Raft consensus status information returned from the view `bdr.group_raft_details` to provide a cluster-wide Raft check. For example:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
bdrdb=# SELECT * FROM bdr.monitor_group_raft();
node_group_name | status |
message
----------------/--------+-------------------------------------
mygroup          | OK     | Raft Consensus is working
correctly
```

Two further views that can give a finer-grained look at the state of Raft consensus are `bdr.stat_raft_state`, which provides the state of the Raft consensus on the local node, and `bdr.stat_raft_followers_state`, which provides a view when on the Raft leader (it is empty on other nodes) regarding the state of the followers of that Raft leader.

Monitoring replication slots

Each PGD node keeps:

- One replication slot per active PGD peer
- One group replication slot

For example:

```
bdrdb=# SELECT slot_name, database, active,
confirmed_flush_lsn
FROM pg_replication_slots ORDER BY slot_name;
        slot_name         | database | active |
confirmed_flush_lsn
--------------------------+----------+--------+--------------------
 bdr_bdrdb_bdrgroup       | bdrdb    | f      |
0/3110A08
 bdr_bdrdb_bdrgroup_node2 | bdrdb    | t      |
0/31F4670
 bdr_bdrdb_bdrgroup_node3 | bdrdb    | t      |
0/31F4670
 bdr_bdrdb_bdrgroup_node4 | bdrdb    | t      |
0/31F4670
```

Peer slot names follow the convention `bdr_<DATABASE>_<GROUP>_<PEER>`, while the PGD group slot name follows the convention `bdr_<DATABASE>_<GROUP>`. You can access the group slot using the function `bdr.local_group_slot_name()`.

Peer replication slots must be active on all nodes at all times. If a peer replication slot isn't active, then it might mean either:

- The corresponding peer is shut down or not accessible.
- PGD replication is broken.

Grep the log file for `ERROR` or `FATAL`, and also check `bdr.event_summary` on all nodes. The root cause might be, for example, an incompatible DDL was executed with DDL replication disabled on one of the nodes.

The PGD group replication slot is, however, inactive most of the time. PGD maintains this slot and advances its LSN when all other peers already consumed the corresponding transactions. Consequently, it's not necessary to monitor the status of the group slot.

The function `bdr.monitor_local_replslots()` provides a summary of whether all PGD node replication slots are working as expected. This summary is also available on subscriber-only nodes that are operating as subscriber-only group leaders in a PGD cluster when optimized topology is enabled. For example:

```
bdrdb=# SELECT * FROM bdr.monitor_local_replslots();
 status |
message
--------+-----------------------------------------------
 OK     | All BDR replication slots are working
correctly
```

One of the following status summaries is returned:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Status	Message
UNKNOWN	This node is not part of any BDR group
OK	All BDR replication slots are working correctly
OK	This node is part of a subscriber-only group
CRITICAL	There is at least 1 BDR replication slot which is inactive
CRITICAL	There is at least 1 BDR replication slot which is missing

Monitoring transaction COMMITs

By default, PGD transactions are committed only to the local node. In that case, a transaction's `COMMIT` is processed quickly.

PGD's Commit Scopes feature offers a range of synchronous transaction commit scopes that allow you to balance durability, consistency, and performance for your particular queries. You can monitor these transactions by examining the `bdr.stat_activity` catalog. The processes report different `wait_event` states as a transaction is committed. This monitoring only covers transactions in progress and doesn't provide historical timing information.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

20 Testing and tuning PGD clusters

You can test PGD applications using the following approaches:

- Trusted Postgres Architect
- pgd_bench with CAMO/failover options

Trusted Postgres Architect

Trusted Postgres Architect is the system used by EDB to deploy reference architectures, including those based on EDB Postgres Distributed.

Trusted Postgres Architect includes test suites for each reference architecture. It also simplifies creating and managing a local collection of tests to run against a TPA cluster, using a syntax like the following:

```
tpaexec test mycluster mytest
```

We strongly recommend that developers write their own multi-node suite of Trusted Postgres Architect tests that verify the main expected properties of the application.

pgd_bench

The Postgres benchmarking application `pgbench` was extended in PGD 5.0 in the form of a new application: pgd_bench.

pgd_bench is a regular command-line utility that's added to the PostgreSQL bin directory. The utility is based on the PostgreSQL pgbench tool but supports benchmarking CAMO transactions and PGD-specific workloads.

Functionality of pgd_bench is a superset of pgbench functionality but requires the BDR extension to be installed to work properly.

Key differences include:

- Adjustments to the initialization (`-i` flag) with the standard pgbench scenario to prevent global lock timeouts in certain cases.
- `VACUUM` command in the standard scenario is executed on all nodes.
- pgd_bench releases are tied to the releases of the BDR extension and are built against the corresponding Postgres distribution. This information is reflected in the output of the `--version` flag.

The current version allows you to run failover tests while using CAMO or regular PGD deployments.

The following options were added:

```
-m, --mode=regular|camo|failover
mode in which pgbench should run (default: regular)
```

- Use `-m camo` or `-m failover` to specify the mode for pgd_bench. You can use the `-m failover` specification to test failover in regular PGD deployments.

```
--retry
retry transactions on failover
```

- Use `--retry` to specify whether to retry transactions when failover happens with `-m failover` mode. This option is enabled by default for `-m camo` mode.

In addition to these options, you must specify the connection information about the peer node for failover inDSN form.

Here's an example in a CAMO environment:

```
    pgd_bench -m camo -p $node1_port -h $node1_host bdrdemo \
        "host=$node2_host user=postgres port=$node2_port dbname=bdrdemo"
```

This command runs in CAMO mode. It connects to node1 and runs the tests. If the connection to node1 is lost, then pgd_bench connects to node2. It queries node2 to get the status of in-flight transactions. Aborted and in-flight transactions are retried in CAMO mode.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

In failover mode, if you specify `--retry`, then in-flight transactions are retried. In this scenario, there's no way to find the status of in-flight transactions.

Notes on pgd_bench usage

- When using custom init-scripts, it's important to understand implications behind the DDL commands. We generally recommend waiting for the secondary nodes to catch up on the data-load steps before proceeding with DDL operations such as `CREATE INDEX`. The latter acquire global locks that can't be acquired until the data load is complete and thus might time out.

- No extra steps are taken to suppress client messages, such as `NOTICE` and `WARNING` messages emitted by PostgreSQL and or any possible extensions, including the BDR extension. It's your responsibility to suppress them by setting appropriate variables, such as `client_min_messages`, `bdr.camo_enable_client_warnings`, and so on.

Performance testing and tuning

PGD allows you to issue write transactions onto multiple nodes. Bringing those writes back together onto each node has a performance cost.

First, replaying changes from another node has a CPU cost and an I/O cost, and it generates WAL records. The resource use is usually less than in the original transaction since CPU overhead is lower as a result of not needing to reexecute SQL. In the case of UPDATE and DELETE transactions, there might be I/O costs on replay if data isn't cached.

Second, replaying changes holds table-level and row-level locks that can produce contention against local workloads. The conflict-free replicated data types (CRDT) and column-level conflict detection (CLCD) features ensure you get the correct answers even for concurrent updates, but they don't remove the normal locking overheads. If you get locking contention, try to avoid conflicting updates, or keep transactions as short as possible. A heavily updated row in a larger transaction causes a bottleneck on performance for that transaction. Complex applications require some thought to maintain scalability.

If you think you're having performance problems, develop performance tests using the benchmarking tools. pgd_bench allows you to write custom test scripts specific to your use case so you can understand the overhead of your SQL and measure the impact of concurrent execution.

If PGD is running slow, then we suggest the following:

1. Write a custom test script for pgd_bench, as close as you can make it to the production system's problem case.
2. Run the script on one node to give you a baseline figure.
3. Run the script on as many nodes as occur in production, using the same number of sessions in total as you did on one node. This technique shows you the effect of moving to multiple nodes.
4. Increase the number of sessions for these two tests so you can plot the effect of increased contention on your application.
5. Make sure your tests are long enough to account for replication delays.
6. Ensure that replication delay isn't growing during your tests.

Use all of the normal Postgres tuning features to improve the speed of critical parts of your application.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21 Upgrading

While PGD and Postgres are closely related, they're separate products with separate upgrade paths. This section covers how to upgrade both PGD and Postgres.

Upgrading PGD

EDB Postgres Distributed is a flexible platform. This means that your upgrade path depends largely on how you installed PGD.

- Upgrading with TPA — If you installed using TPA, you can use its automated upgrade feature to upgrade to the latest minor versions.
- Upgrading manually — If you manually installed and configured your PGD cluster, you can move a cluster between versions, both minor and major.
- Upgrade paths — Several supported upgrade paths are available.
- Compatibility changes — If you're upgrading from PGD 3.x or 4.x to PGD 5.x or later, you need to understand the compatibility changes between versions.

Upgrading Postgres or Postgres and PGD major versions

- In-place Postgres major version upgrades — How to use `pgd node upgrade` to manually upgrade the Postgres version or Postgres and PGD major version on one or more nodes.
- Rolling major version upgrades — How to perform a major version upgrade of Postgres on a cluster.

Other upgrades

- Application schema upgrades — A guide for safely upgrading your application's schema when running multiple distributed servers with PGD.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21.1 Upgrading PGD clusters with TPA

> **No Postgres major version upgrades**
>
> TPA doesn't currently support major version upgrades of Postgres.
>
> To perform a major version upgrade of Postgres, see In-place Postgres major version upgrades.

If you used TPA to install your cluster, you can also use TPA to upgrade it. The techniques outlined here can perform minor and major version upgrades of the PGD software. They can also perform minor version upgrades of Postgres.

You can read more about the capabilities of TPA upgrades in Upgrading your cluster in the TPA documentation.

> **Always test first**
>
> Always test upgrade processes in a QA environment first. This helps to ensure that there are no unexpected factors to take into account. TPA's ability to reproducibly deploy a PGD configuration makes it much easier to build a test environment to work with.

Minor and major PGD upgrades

TPA automatically manages minor version upgrades of PGD.

Major version upgrades of PGD require changes to the TPA `config.yml` file, which contains the deployment configuration.

When upgrading to PGD 5 from previous PGD major versions, you can use `tpaexec reconfigure`. This command helps you make appropriate modifications to your deployment configuration.

The `reconfigure` command requires settings for architecture (the only supported setting is `PGD_Always_ON`) and PGD Proxy routing (`--pgd-proxy-routing <global|local>`) to run. Remember to back up your deployment configuration before running, and use the `--describe` and `--output` options to preview the reconfiguration.

Prerequisites

- You need the cluster configuration directory created when TPA deployed your PGD cluster.
- If performing a major version upgrade of PGD, ensure that `tpaexec reconfigure` was run and appropriate configuration changes were made.

Upgrading

Run:

```
tpaexec upgrade clustername
```

Where `clustername` is the name of the cluster and the path to the cluster configuration directory. By default, TPA upgrades each node of the cluster to the latest minor versions of the software the nodes were configured with.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

TPA's automated rolling upgrade procedure

TPA first tests the cluster and then the nodes.

Each node is then isolated from the cluster, upgraded, and returned to operation within the cluster.

TPA upgrades - step by step

- Checks that all preconditions for upgrading the cluster are met.
- For each instance in the cluster:
    - Checks that it has the correct repositories configured.
        - Checks that the required Postgres packages are available in those repositories.
    - For each BDR node in the cluster, one at a time:
        - Fences the node off to ensure that pgd-proxy doesn't send any connections to it.
        - Stops, updates, and restarts Postgres.
        - Unfences the node so it can receive connections again.
        - Updates pgbouncer, pgd-proxy, and pgd-cli, as applicable for this node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21.2 Upgrading PGD clusters manually

Because EDB Postgres Distributed consists of multiple software components, the upgrade strategy depends partially on the components that are being upgraded.

In general, you can upgrade the cluster with almost zero downtime by using an approach called *rolling upgrade*. Using this approach, nodes are upgraded one by one, and the application connections are switched over to already upgraded nodes.

You can also stop all nodes, perform the upgrade on all nodes, and only then restart the entire cluster. This approach is the same as with a standard PostgreSQL setup. This strategy of upgrading all nodes at the same time avoids running with mixed versions of software and therefore is the simplest. However, it incurs downtime and we don't recommend it unless you can't perform the rolling upgrade for some reason.

To upgrade an EDB Postgres Distributed cluster:

1. Plan the upgrade.
2. Prepare for the upgrade.
3. Upgrade the server software.
4. Check and validate the upgrade.

Upgrade planning

There are broadly two ways to upgrade each node:

- Upgrade nodes in place to the newer software version. See Rolling server software upgrades.
- Replace nodes with ones that have the newer version installed. See Rolling upgrade using node join.

You can use both of these approaches in a rolling manner.

Rolling upgrade considerations

While the cluster is going through a rolling upgrade, mixed versions of software are running in the cluster. For example, suppose nodeA has PGD 4.3.6, while nodeB and nodeC have 5.6.1. In this state, the replication and group management uses the protocol and features from the oldest version (4.3.6 in this example), so any new features provided by the newer version that require changes in the protocol are disabled. Once all nodes are upgraded to the same version, the new features are enabled.

Similarly, when a cluster with WAL-decoder-enabled nodes is going through a rolling upgrade, WAL decoder on a higher version of PGD node produces logical change records (LCRs) with a higher pglogical version. WAL decoder on a lower version of PGD node produces LCRs with a lower pglogical version. As a result, WAL senders on a higher version of PGD nodes aren't expected to use LCRs due to a mismatch in protocol versions. On a lower version of PGD nodes, WAL senders can continue to use LCRs. Once all the PGD nodes are on the same PGD version, WAL senders use LCRs.

A rolling upgrade starts with a cluster with all nodes at a prior release. It then proceeds by upgrading one node at a time to the newer release, until all nodes are at the newer release. There must be no more than two versions of the software running at the same time. An upgrade must be completed, with all nodes fully upgraded, before starting another upgrade.

Where additional caution is required to reduce business risk, more time may be required to perform an upgrade. For maximum caution and to reduce the time required upgrading production systems, we suggest performing the upgrades in a separate test environment first.

Don't run with mixed versions of the software for any longer than is absolutely necessary to complete the upgrade. You can check on the versions in the cluster using the `pgd nodes list --versions` command.

The longer you run with mixed versions, the more likely you are to encounter issues, the more difficult it is to diagnose and resolve them.
We recommend upgrading in off peak hours for your business, and over a short period of time.

While you can use a rolling upgrade for upgrading a major version of the software, we don't support mixing PostgreSQL, EDB Postgres Extended, and EDB Postgres Advanced Server in one cluster. So you can't use this approach to change the Postgres variant.

> **Warning**
>
> Downgrades of EDB Postgres Distributed aren't supported. They require that you manually rebuild the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Rolling server software upgrades

A rolling upgrade is where the server software upgrade is upgraded sequentially on each node in a cluster without stopping the cluster. Each node is temporarily stopped from participating in the cluster and its server software is upgraded. Once updated, it's returned to the cluster, and it then catches up with the cluster's activity during its absence.

The actual procedure depends on whether the Postgres component is being upgraded to a new major version.

During the upgrade process, you can switch the application over to a node that's currently not being upgraded to provide continuous availability of the database for applications.

Rolling upgrade using node join

The other method to upgrade the server software is to join a new node to the cluster and later drop one of the existing nodes running the older version of the software.

For this approach, the procedure is always the same. However, because it includes node join, a potentially large data transfer is required.

Take care not to use features that are available only in the newer Postgres version until all nodes are upgraded to the newer and same release of Postgres. This is especially true for any new DDL syntax that was added to a newer release of Postgres.

> **Note**
>
> `bdr_init_physical` makes a byte-by-byte copy of the source node so you can't use it while upgrading from one major Postgres version to another. In fact, currently `bdr_init_physical` requires that even the PGD version of the source and the joining node be exactly the same. You can't use it for rolling upgrades by way of joining a new node method. Instead, use a logical join.

Upgrading a CAMO-enabled cluster

Upgrading a CAMO-enabled cluster requires upgrading CAMO groups one by one while disabling the CAMO protection for the group being upgraded and reconfiguring it using the new commit scope-based settings.

We recommended the following approach for upgrading two BDR nodes that constitute a CAMO pair to PGD 5.0:

1. Ensure `bdr.enable_camo` remains `off` for transactions on any of the two nodes, or redirect clients away from the two nodes. Removing the CAMO pairing while attempting to use CAMO leads to errors and prevents further transactions.
2. Uncouple the pair by deconfiguring CAMO either by resetting `bdr.camo_origin_for` and `bdr.camo_parter_of` (when upgrading from BDR 3.7.x) or by using `bdr.remove_camo_pair` (on BDR 4.x).
3. Upgrade the two nodes to PGD 5.0.
4. Create a dedicated node group for the two nodes and move them into that node group.
5. Create a commit scope for this node group and thus the pair of nodes to use CAMO.
6. Reactivate CAMO protection again either by setting a `default_commit_scope` or by changing the clients to explicitly set `bdr.commit_scope` instead of `bdr.enable_camo` for their sessions or transactions.
7. If necessary, allow clients to connect to the CAMO-protected nodes again.

Upgrade preparation

Each major release of the software contains several changes that might affect compatibility with previous releases. These might affect the Postgres configuration, deployment scripts, as well as applications using PGD. We recommend considering these changes and making any needed adjustments in advance of the upgrade.

See individual changes mentioned in the release notes and any version-specific upgrade notes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Server software upgrade

Upgrading EDB Postgres Distributed on individual nodes happens in place. You don't need to back up and restore when upgrading the BDR extension.

BDR extension upgrade

The BDR extension upgrade process consists of a few steps.

Stop Postgres

During the upgrade of binary packages, it's usually best to stop the running Postgres server first. Doing so ensures that mixed versions don't get loaded in case of an unexpected restart during the upgrade.

Upgrade packages

The first step in the upgrade is to install the new version of the BDR packages. This installation installs both the new binary and the extension SQL script. This step is specific to the operating system.

> **Upgrading to PGD 6**
>
> The PGD 6 packages include the PGD CLI and intentionally conflict with the standalone `edb-pgd5-cli` package. When you upgrade to PGD 6, remove all PGD 5 packages, including `edb-pgd5-cli`, before you install the PGD 6 packages. If you skip this step, the installation fails with a package conflict error. See Upgrading PGD 5 to PGD 6.

Start Postgres

Once packages are upgraded, you can start the Postgres instance. The BDR extension is upgraded upon start when the new binaries detect the older version of the extension.

Upgrading to a later PGD 5 release

You can upgrade from any PGD 5.x release to a later 5.x release. See Supported PGD upgrade paths. For a rolling upgrade, run the following on each node, one at a time.

> **Note**
>
> Before you upgrade PGD, upgrade Postgres to the latest minor version of your Postgres major version. Doing so reduces the risk of the upgrade, because you avoid known vulnerabilities and bugs that can interfere with it. See Minor version Postgres upgrade and PGD compatibility.
>
> Newer PGD packages can require a newer Postgres minor version. If your Postgres version is older, the package manager upgrades Postgres as a dependency in the middle of the PGD upgrade.

> **Connection Manager changes in PGD 5.10.0**
>
> If you use Connection Manager, PGD 5.10.0 changes how it handles client TLS and client certificates. Check both changes before you upgrade:
>
> - Connection Manager now offers TLS to clients only when `ssl` is `on` in `postgresql.conf`. Earlier releases offered TLS whenever `ssl_cert_file` and `ssl_key_file` pointed to existing files, whatever `ssl` was set to. If clients connect to Connection Manager over TLS, set `ssl = on` on each node before you upgrade it. With `ssl` on, both files must be set.
> - Connection Manager now verifies client certificates against `ssl_ca_file`, `ssl_crl_file`, and `ssl_crl_dir`. If you use `cert` rules in the Connection Manager HBA configuration, set `ssl_ca_file` before you upgrade, because `cert` authentication fails without it.
>
> See TLS and client certificates.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

1. Fence the node, so it doesn't become the write leader:

   ```
   pgd node <node_name> set-option route_fence true
   ```

   If your installed PGD CLI doesn't support this syntax, use the earlier syntax:

   ```
   pgd set-node-options --node-name <node_name> --option route_fence=true
   ```

2. Stop Postgres:

   ```
   sudo systemctl stop postgres
   ```

3. Upgrade the PGD packages:

```
```shell
sudo apt update
sudo apt install --only-upgrade edb-bdr5-<distribution><postgres_version> edb-pgd5-cli edb-pgd5-proxy
```
```

```
```shell
sudo dnf upgrade -y edb-bdr5-<distribution><postgres_version> edb-pgd5-cli edb-pgd5-proxy
```
```

```
```shell
sudo zypper refresh
sudo zypper -n update edb-bdr5-<distribution><postgres_version> edb-pgd5-cli edb-pgd5-proxy
```
```

1. Start Postgres:

   ```
   sudo systemctl start postgres
   ```

2. Restart PGD Proxy, so it runs the new version. Upgrading the package replaces the binary, but the running service keeps using the old version until you restart it:

   ```
   sudo systemctl restart pgd-proxy
   ```

3. Unfence the node. The package upgrade installed the new PGD CLI, so use the newer syntax even if you fenced the node with the earlier one:

   ```
   pgd node <node_name> set-option route_fence false
   ```

Postgres upgrade

The process of in-place upgrade of Postgres depends on whether you're upgrading to a new minor version of Postgres or to a new major version of Postgres.

Minor version Postgres upgrade

Upgrading to a new minor version of Postgres is similar to upgrading the BDR extension. Stopping Postgres, upgrading packages, and starting Postgres again is typically all that's needed.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Upgrade every installed package of your Postgres distribution, not only the server package. Subpackages such as the JIT library stay on the old minor version otherwise, and PGD packages upgrade only the Postgres packages they depend on. For example, for EDB Postgres Advanced Server 14:

```
sudo apt update
sudo apt install --only-upgrade <postgres_package>
```

```
sudo dnf upgrade -y $(rpm -qa --qf '%{NAME}\n' 'edb-as14-server*')
```

```
sudo zypper refresh
sudo zypper -n update 'edb-as14-server*'
```

However, sometimes more steps, like reindexing, might be recommended for specific minor version upgrades. Refer to the release notes of the version of Postgres you're upgrading to.

Major version Postgres upgrade

Upgrading to a new major version of Postgres is more complicated than upgrading to a minor version.

EDB Postgres Distributed provides a `pgd node upgrade` command line utility, which you can use to do in-place Postgres major version upgrades.

> **Note**
>
> When upgrading to a new major version of any software, including Postgres, the BDR extension, and others, it's always important to ensure your application is compatible with the target version of the software you're upgrading.

Upgrade check and validation

After you upgrade your PGD node, you can verify the current version of the binary:

```
SELECT bdr.bdr_version();
```

Always check your monitoring after upgrading a node to confirm that the upgraded node is working as expected.

Moving from HARP to PGD Proxy

HARP can temporarily coexist with the new connection management configuration. This means you can:

- Upgrade a whole pre-5 cluster to a PGD 5 cluster.
- Set up the connection routing.
- Replace HARP Proxy with PGD Proxy.
- Move application connections to PGD Proxy instances.
- Remove the HARP Manager from all servers.

We strongly recommend doing this as soon as possible after upgrading nodes to PGD 5. HARP isn't certified for long-term use with PGD 5.

TPA provides some useful tools for this and will eventually provide a single-command upgrade path between PGD 4 and PGD 5.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21.3 Supported PGD upgrade paths

Upgrading within version 5

EDB Postgres Distributed uses semantic versioning. All changes within the same major version are backward compatible, lowering the risk when upgrading and allowing you to choose any later minor or patch release as the upgrade target.

You can upgrade from any version 5.x release to a later 5.x release.

Upgrading from version 4 to version 5

We generally recommend you upgrade your cluster to the latest PGD 4 release before upgrading to the latest PGD 5 release.

Upgrades from PGD 4 to PGD 5 are supported from version 4.3.0 or later.

The following table provides a full list of possible upgrade paths from PGD 4 to PGD 5. Check the "From version" column to confirm the minimum required PGD 4 release necessary before upgrading to your des ired PGD 5 target version.

See Upgrading within version 4 for instructions on upgrading within PGD 4 to reach the required version.

From version	To version (range)
4.3.0	5.0.0 to 5.8.1
4.3.1	5.1.0 to 5.8.1
4.3.2	5.1.0 to 5.8.1
4.3.3	5.1.0 to 5.8.1
4.3.7	5.7.0 to 5.8.1
4.4.0	5.9.0 or later

Upgrading from version 3.7 to version 5

Starting with version 3.7.23, you can upgrade directly to version 5.3.0 or later. For earlier versions, upgrade to 3.7.23 before upgrading to 5. See Upgrading within version 3.7 for more information.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21.4 Compatibility changes

Many changes in PGD 5 aren't backward compatible with PGD 4 or PGD 3.7.

Connection routing

HARP Manager doesn't exist anymore. It's been replaced by new connection management configuration.

HARP Proxy is replaced by similarly functioning PGD Proxy, which removes any deprecated features and is configured through connection management configuration.

Commit At Most Once

CAMO configuration is now done through commit scopes. The `bdr.camo_pairs` catalog and any related manipulation functions don't exist anymore. The `bdr.enable_camo` GUC was removed. The `synchronous_replication_availability` GUC doesn't affect CAMO anymore. Use the `DEGRADE ON ... TO ASYNC` clause of a commit scope.

Eager All-Node Replication

The `global` scope no longer exists. To create scope with the same behavior, use Group Commit.

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'eager_scope',
    origin_node_group := 'top_group',
    rule := 'ALL (top_group) GROUP COMMIT (conflict_resolution = eager, commit_decision = raft) ABORT ON (timeout =
60s)',
    wait_for_ready :=
true
);
```

The `bdr.global_commit_timeout` GUC was removed. Use the `ABORT ON` clause for the commit scope.

Lag Control

Similarly to CAMO and Eager, Lag Control configuration was also moved to commit scopes for more flexible durability configuration.

Catalogs

- `bdr.workers` doesn't show worker-specific info like `worker_commit_timestamp` anymore.
- `bdr.worker_errors` is deprecated and lost most of the info.
- `bdr.state_journal_details` is deprecated and lost most of the info.
- `bdr.event_summary` replaces `bdr.worker_errors` and `bdr.state_journal_details` with additional info like Raft role changes.
- The table `bdr.node_catchup_info` now has the user-consumable view `bdr.node_catchup_info_details`, which shows info in a more friendly way.
- Witness node is no longer distinguished by the replication sets it replicates but by using the `node_kind` value in `bdr.node_summary`.
- All the Raft (consensus) related tables and functions were adjusted to support multiple Raft instances (sub-group Raft).
- `bdr.node_pre_commit` view and the underlying table was removed, as the information is no longer stored in a table.
- `bdr.commit_decisions` view was added and replaces the `bdr.node_pre_commit` one.
- Multiple internal autopartition tables were replaced by taskmgr ones, as the mechanism behind it was generalized.
- `bdr.network_monitoring` view was removed along with underlying tables and functions.
- Many catalogs were added and some have new columns, as described in Catalogs. These aren't breaking changes strictly speaking, but we recommend reviewing them when upgrading.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21.5 Application schema upgrades

Similar to the upgrade of EDB Postgres Distributed, there are two approaches to upgrading the application schema. The simpler option is to stop all applications affected, preform the schema upgrade, and restart the application upgraded to use the new schema variant. This approach imposes some downtime.

To eliminate this downtime, EDB Postgres Distributed offers useful tools to perform a rolling application schema upgrade.

The following recommendations and tips reduce the impact of the application schema upgrade on the cluster.

Rolling application schema upgrades

By default, DDL is automatically sent to all nodes. You can control this behavior manually, as described in DDL replication. You can use this approach to create differences between database schemas across nodes.

PGD is designed to allow replication to continue even with minor differences between nodes. These features are designed to allow application schema migration without downtime or to allow logical standby nodes for reporting or testing.

> **Warning**
>
> You must manage rolling application schema upgrades outside of PGD.
>
> Careful scripting is required to make this work correctly on production clusters. We recommend extensive testing.

See Replicating between nodes with differences for details.

When one node runs DDL that adds a new table, nodes that haven't yet received the latest DDL need to handle the extra table. In view of this, the appropriate setting for rolling schema upgrades is to configure all nodes to apply the `skip` resolver in case of a `target_table_missing` conflict. Perform this configuration before adding tables to any node. This setting is intended to be permanent.

Execute the following query **separately on each node**. Replace `node1` with the actual node name.

```
SELECT
bdr.alter_node_set_conflict_resolver('node1',
        'target_table_missing', 'skip');
```

When one node runs DDL that adds a column to a table, nodes that haven't yet received the latest DDL need to handle the extra columns. In view of this, the appropriate setting for rolling schema upgrades is to configure all nodes to apply the `ignore` resolver in case of a `target_column_missing` conflict. Perform this before adding columns to one node. This setting is intended to be permanent.

Execute the following query **separately on each node**. Replace `node1` with the actual node name.

```
SELECT
bdr.alter_node_set_conflict_resolver('node1',
        'target_column_missing', 'ignore');
```

When one node runs DDL that removes a column from a table, nodes that haven't yet received the latest DDL need to handle the missing column. This situation causes a `source_column_missing` conflict, which uses the `use_default_value` resolver. Thus, columns that don't accept NULLs and don't have a DEFAULT value require a two-step process:

1. Remove the NOT NULL constraint, or add a DEFAULT value for a column on all nodes.
2. Remove the column.

You can remove constraints in a rolling manner. There's currently no supported way for handling adding table constraints in a rolling manner, one node at a time.

When one node runs a DDL that changes the type of an existing column, depending on the existence of binary coercibility between the current type and the target type, the operation might not rewrite the underlying table data. In that case, it's only a metadata update of the underlying column type. Rewriting a table is normally restricted. However, in controlled DBA environments, you can change the type of a column to an automatically castable one by adopting a rolling upgrade for the type of this column in a non-replicated environment on all the nodes, one by one. See ALTER TABLE for more details.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21.6 In-place Postgres or Postgres and PGD major version upgrades

You can upgrade a PGD node to a newer major version of Postgres or a major version of Postgres and PGD using the command-line utility pgd node upgrade.

> **Note**
>
> In previous versions before 5.7.0, the command used for in-place major version upgrades was `bdr_pg_upgrade`. However, this command didn't have an option to upgrade both Postgres major versions and PGD versions simultaneously, as `pgd node upgrade` does.

`pgd node upgrade` is a wrapper around the standard pg_upgrade that adds PGD-specific logic to the process to ensure a smooth upgrade.

Terminology

This terminology is used when describing the upgrade process and components involved:

Postgres cluster — The database files, both executables and data, that make up a Postgres database instance on a system when run.

Old Postgres cluster — The existing Postgres cluster to upgrade, the one from which to migrate data.

New Postgres cluster — The new Postgres cluster that data is migrated to. This Postgres cluster must be one major version ahead of the old cluster.

Precautions

Standard Postgres major version upgrade precautions apply, including the fact both Postgres clusters must meet all the requirements for pg_upgrade.

Additionally, don't use `pgd node upgrade` if other tools are using replication slots and replication origins. Only PGD slots and origins are restored after the upgrade.

You must meet several prerequisites for `pgd node upgrade`:

- Disconnect applications using the old Postgres cluster. You can, for example, redirect them to another node in the PGD cluster.
- Configure peer authentication for both Postgres clusters. bdr_pg_upgrade requires peer authentication.
- The same PGD version must be installed on both clusters.
- The PGD version must be 4.1.0 or later. Version 3.7.22 and later is also supported.
- The new cluster must be in a shutdown state.
- You must install PGD packages in the new cluster.
- The new cluster must already be initialized and configured as needed to match the old cluster configuration.
- Databases, tables, and other objects must not exist in the new cluster.

> **Note**
>
> When upgrading to PGD 5.7.0+, you don't need to have both clusters run the same PGD version. The new cluster must be running 5.7.0+. In that case `pgd node upgrade` will upgrade the PGD version to 5.7.x and upgrade the Postgres major version.

We also recommend having the old Postgres cluster up prior to running `pgd node upgrade`. The CLI starts the old Postgres cluster if it's shut down.

Usage

To upgrade to a newer major version of Postgres or Postgres and PGD, you must first install the new version packages.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`pgd node upgrade` command-line

`pgd node upgrade` passes all parameters to pg_upgrade. Therefore, you can specify any parameters supported by pg_upgrade.

Synopsis

```
pgd node <NODE_NAME> upgrade [OPTION] ...
```

Options

In addition to the options for pg_upgrade, you can pass the following parameters to `pgd node upgrade`.

Required parameters

Specify these parameters either in the command line or, for all but the `--database` parameter, in their equivalent environment variable. They're used by `pgd node upgrade`.

- `-b, --old-bindir` — Old Postgres cluster bin directory.
- `-B, --new-bindir` — New Postgres cluster bin directory.
- `-d, --old-datadir` — Old Postgres cluster data directory.
- `-D, --new-datadir` — New Postgres cluster data directory.
- `--database` — PGD database name.

Optional parameters

These parameters are optional and are used by `pgd node upgrade`:

- `-p, --old-port` — Old cluster port number.
- `-s, --socketdir` — Directory to use for postmaster sockets during upgrade.
- `--check` — Specify to only perform checks and not modify clusters.

Other parameters

Any other parameter that's not one of the above is passed to pg_upgrade. pg_upgrade accepts the following parameters:

- `-j, --jobs` — Number of simultaneous processes or threads to use.
- `-k, --link` — Use hard links instead of copying files to the new cluster.
- `-o, --old-options` — Option to pass to old postgres command. Multiple invocations are appended.
- `-O, --new-options` — Option to pass to new postgres command. Multiple invocations are appended.
- `-N, --no-sync` — Don't wait for all files in the upgraded cluster to be written to disk.
- `-P, --new-port` — New cluster port number.
- `-r, --retain` — Retain SQL and log files even after successful completion.
- `-U, --username` — Cluster's install user name.
- `--clone` — Use efficient file cloning.

Environment variables

You can use these environment variables in place of command-line parameters:

- `PGBINOLD` — Old Postgres cluster bin directory.
- `PGBINNEW` — New Postgres cluster bin directory.
- `PGDATAOLD` — Old Postgres cluster data directory.
- `PGDATANEW` — New Postgres cluster data directory.
- `PGPORTOLD` — Old Postgres cluster port number.
- `PGSOCKETDIR` — Directory to use for postmaster sockets during upgrade.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Example

Given a scenario where:

- Node name of the cluster you want to upgrade is kaolin.
- Old Postgres cluster bin directory is `/usr/lib/postgresql/16/bin`.
- New Postgres cluster bin directory is `/usr/lib/postgresql/17/bin`.
- Old Postgres cluster data directory is `/var/lib/postgresql/16/main`.
- New Postgres cluster data directory is `/var/lib/postgresql/17/main`.
- Database name is `bdrdb`.

You can use the following command to upgrade the cluster:

```
pgd node kaolin upgrade \
--old-bindir /usr/lib/postgresql/16/bin \
--new-bindir /usr/lib/postgresql/17/bin \
--old-datadir /var/lib/postgresql/16/main \
--new-datadir /var/lib/postgresql/17/main \
--database bdrdb
```

Steps performed

These steps are performed when running `pgd node upgrade`.

> **Note**
>
> When `--check` is supplied as an argument to `pgd node upgrade`, the CLI skips steps that modify the database.

PGD Postgres checks

Steps	`--check` supplied
Collecting pre-upgrade new cluster control data	`run`
Checking new cluster state is shutdown	`run`
Checking PGD versions	`run`
Starting old cluster (if shutdown)	`skip`
Connecting to old cluster	`skip`
Checking if bdr schema exists	`skip`
Turning DDL replication off	`skip`
Terminating connections to database	`skip`
Waiting for all slots to be flushed	`skip`
Disconnecting from old cluster	`skip`
Stopping old cluster	`skip`
Starting old cluster with PGD disabled	`skip`
Connecting to old cluster	`skip`
Collecting replication origins	`skip`
Collecting replication slots	`skip`
Disconnecting from old cluster	`skip`
Stopping old cluster	`skip`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

pg_upgrade steps

Standard pg_upgrade steps are performed.

> **Note**
>
> If supplied, `--check` is passed to pg_upgrade.

PGD post-upgrade steps

Steps	`--check` supplied
Collecting old cluster control data	`skip`
Collecting new cluster control data	`skip`
Advancing LSN of new cluster	`skip`
Starting new cluster with PGD disabled	`skip`
Connecting to new cluster	`skip`
Creating replication origin, repeated for each origin	`skip`
Advancing replication origin, repeated for each origin	`skip`
Creating replication slot, repeated for each slot	`skip`
Stopping new cluster	`skip`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

21.7 Performing a Postgres major version rolling upgrade on a PGD cluster

Upgrading Postgres major versions

Upgrading a Postgres database's major version to access improved features, performance enhancements, and security updates is a common administration task. Doing the same for an EDB Postgres Distributed (PGD) cluster is essentially the same process but performed as a rolling upgrade.

The rolling upgrade process allows updating individual cluster nodes to a new major Postgres version while maintaining cluster availability and operational continuity. This approach minimizes downtime and ensures data integrity by allowing the rest of the cluster to remain operational as each node is upgraded sequentially.

While the upgrade process is in progress, the cluster will have mixed Postgres major versions running on different nodes. DDL replication is not supported between different major versions of Postgres, so you must ensure that no DDL changes are made to the cluster while the upgrade is in progress. That includes not running the `ALTER EXTENSION` commands generated by the upgrade processes until all nodes in the cluster are upgraded to the same major version.

The following overview of the general instructions and worked example help to provide a smooth and controlled upgrade process.

> **Note**
>
> The following overview and worked example assume you're upgrading to or from 5.7.0+. For upgrading to older versions of PGD, you need to use the command `bdr_pg_upgrade`, which has almost the same behavior and requirements as `pgd node upgrade`. The only difference is that with `bdr_pg_upgrade` you can only upgrade major versions of Postgres (community/PGE/EDB Postgres Advanced Server), but with `pgd node upgrade` you can upgrade major versions of PGD and Postgres at once.

Prepare the upgrade

To prepare for the upgrade, identify the subgroups and nodes you're trying to upgrade and note an initial upgrade order.

To do this, connect to one of the nodes using SSH and run the `pgd nodes list` command:

```
sudo -u postgres pgd nodes
list
```

The `pgd nodes list` command shows you all the nodes in your PGD cluster and the subgroup to which each node belongs. Then you want to find out which node is the write leader in each subgroup:

```
sudo -u postgres pgd group <group_name> show --
summary
```

This command shows you information about the pgd group tokened by your `<group_name>` running in your cluster, including which node is the write leader. To maintain operational continuity, you need to switch write leaders over to another node in their subgroup before you can upgrade them. To keep the number of planned switchovers to a minimum, when upgrading a subgroup of nodes, upgrade the writer leaders last.

Even though you verified which node is the current write leader for planning purposes, the write leader of a subgroup could change to another node at any moment for operational reasons before you upgrade that node. Therefore, you still need to verify that a node isn't the write leader just before upgrading that node.

> **Note**
>
> Nodes that run Postgres client tools but not a PGD data node use the Postgres client libraries. Before upgrading the PGD data nodes, upgrade those nodes to the `edb-as<xx>-server-client` (EPAS) or `postgresql-client-<xx>` (PG) package for the new major version.

You now have enough information to determine your upgrade order, one subgroup at a time, aiming to upgrade the identified write leader node last in each subgroup.

Perform the upgrade on each node

> **Note**
>
> To help prevent data loss, before starting the upgrade process, ensure that your databases and configuration files are backed up.

Using the preliminary order, perform the following steps on each node while connected via SSH:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- **Confirm the current Postgres version**
  - View versions from PGD:

    `sudo -u postgres pgd nodes list --versions`.

  - Ensure that the expected major version is running.
- **Verify that the target node isn't the write leader**
  - Check whether the target node is the write leader for the group you're upgrading:

    ```
    sudo -u postgres pgd group <group_name> show --summary
    ```

  - If the target node is the current write leader for the group/subgroup you're upgrading, perform a planned switchover to another node:

    ```
    sudo -u postgres pgd group <group_name> set-leader <new_leader_node_name>
    ```

- **Stop Postgres on the target node**
  - Stop the Postgres service on the current node:

    ```
    sudo systemctl stop postgres
    ```

    The target node is no longer actively participating as a node in the cluster.
- **Install PGD and utilities**
  - Install PGD and its utilities compatible with the Postgres version you're upgrading to:

    ```
    sudo apt install edb-bdr5-pg<new_postgres_version_number> edb-bdr-utilities
    ```

- **Initialize the new Postgres instance**
  - Create a directory to house the database files for the new version of PostgreSQL:

    ```
    sudo mkdir -p /opt/postgres/datanew
    ```

  - Ensure that the user postgres has ownership permissions to the directory using `chown`.
  - Initialize a new PostgreSQL database cluster in the directory you just created. This step involves using the `initdb` command provided by the newly installed version of PostgreSQL. Include the `--data-checksums` flag to ensure the cluster uses data checksums.

    ```
    sudo -u postgres <path_to_postgres_bin>/initdb -D /opt/postgres/datanew --data-checksums
    ```

    Replace `<path_to_postgres_bin>` with the path to the bin directory of the newly installed PostgreSQL version.

    You may need to run this command as the postgres user or another user with appropriate permissions.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- **Migrate configuration to the new Postgres version**

  - Locate the following configuration files in your current PostgreSQL data directory:

    - `postgresql.conf` — The main configuration file containing settings related to the database system.
    - `postgresql.auto.conf` — Contains settings set by PostgreSQL, such as those modified by the `ALTER SYSTEM` command.
    - `pg_hba.conf` — Manages client authentication, specifying which users can connect to which databases from which hosts.
    - The entire `conf.d` directory (if present) — Allows for organizing configuration settings into separate files for better manageability.

  - Copy these files and the `conf.d` directory to the new data directory you created for the upgraded version of PostgreSQL.

  - Remove or rename any configuration parameters that the new major version no longer supports, or the new server won't start. For example, `operator_precedence_warning` was removed in Postgres 14. `wal_keep_segments` was removed in Postgres 13 and replaced by `wal_keep_size`. Set `wal_keep_size` to the old value multiplied by the write-ahead log (WAL) segment size. For example, `wal_keep_segments = 64` becomes `wal_keep_size = '1024MB'` with 16MB segments. See the Postgres release notes of the versions between your old and new version.

    If `log_destination` is set to `syslog`, the `pg_upgrade` log doesn't show why the new server failed to start. Check the system log instead.

- **Verify the Postgres service is inactive**

  - Before proceeding, it's important to ensure that no PostgreSQL processes are active for both the old and the new data directories. This verification step prevents any data corruption or conflicts during the upgrade process.

    Use the `sudo systemctl status postgres` command to verify that Postgres was stopped. If it isn't stopped, run `systemctl stop postgres` and verify again that it was stopped.

- **Swap PGDATA directories for version upgrade**

  - Rename `/opt/postgres/data` to `/opt/postgres/dataold` and `/opt/postgres/datanew` to `/opt/postgres/data`.

  This step readies your system for the next crucial phase: running pgd node upgrade to finalize the PostgreSQL version transition.

- **Verify upgrade feasibility**

  - The `pgd node upgrade` tool offers a `--check` option designed to perform a preliminary scan of your current setup, identifying any potential issues that could hinder the upgrade process.

    You need to run this check from an upgrade directory with ownership given to user postgres, such as `/home/upgrade/`, so that the upgrade log files created by `pgd node upgrade` can be stored. To initiate the safety check, append the `--check` option to your `pgd node upgrade` command.

    This operation simulates the upgrade process without making any changes, providing insights into any compatibility issues, deprecated features, or configuration adjustments required for a successful upgrade.

  - If your old cluster doesn't use the defaults, pass the `--old-port` and `--socketdir` options. The defaults are port 5432 and the `/var/run/postgresql` socket directory, which doesn't exist on RHEL. EDB Postgres Advanced Server listens on port 5444 by default. For example, on RHEL with EDB Postgres Advanced Server, add `--socketdir /tmp --old-port 5444`. Without a valid socket directory, the new server fails with an error such as `could not create lock file "/var/run/postgresql/.s.PGSQL.5432.lock"`.

  - Address any warnings or errors indicated by this check to ensure an uneventful transition to the new version.

- **Execute the Postgres major version upgrade**

  - Execute the upgrade process by running the `pgd node <node_name> upgrade` command without the `--check` option, and with the same options, including `--old-port` and `--socketdir` if you needed them for the check.
  - It's essential to monitor the command output for any errors or warnings that require attention.
  - The time the upgrade process take depends on the size of your database and the complexity of your setup.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- **Update the Postgres service configuration**
  - Update the service configuration to reflect the new PostgreSQL version by updating the version number in the `postgres.service` file:

    ```
    sudo sed -i -e 's/<old_version_number>/<new_version_number>/g' /etc/systemd/system/postgres.service
    ```

  - Refresh the system's service manager to apply these changes:

    ```
    sudo systemctl daemon-reload
    ```

- **Restart Postgres**
  - Proceed to restart the PostgreSQL service:

    ```
    systemctl start postgres
    ```

- **Update the extensions**
  - The upgrade process checks for extension updates and generates a script named `updated_extensions.sql` in the current directory if needed. This contains `ALTER EXTENSION` commands for any extensions that need updating after the upgrade.

  As the script contains are DDL commands, if you have to run the script before all nodes are upgraded, you shouldturn off DDL replication temporarily. You can do this using `SET bdr.ddl_replication = off;` to avoid issues with mixed major versions, but you will have to ensure that the script keeps DDL replication off during the course of its running. Check for any commands in the script that would change database (such as `\c dbname`) and repeat the `SET bdr.ddl_replication = off;` command.

  If you can defer running the script until all nodes are upgraded, it is easier and simpler to run the script on each node after the upgrade of that node is complete.

- **Validate the new Postgres version**
  - Verify that your PostgreSQL instance is now upgraded:

    ```
    sudo -u postgres pgd nodes list --versions
    ```

- **Clean up post-upgrade**
  - Run `vacuumdb` with the `ANALYZE` option immediately after the upgrade but before introducing a heavy production load. Running this command minimizes the immediate performance impact, preparing the database for more accurate testing.
  - Remove the old version's data directory, `/opt/postgres/dataold`.

The worked example that follows shows upgrading the Postgres major version from 16 to 17 on a PGD 5 cluster deployed with TPA in detail.

Worked example

This worked example starts with a TPA-managed PGD cluster deployed using the AWS quick start, which create Debian OS nodes. The cluster has three nodes: kaboom, kaolin, and kaftan, all running Postgres 16.

This example starts with the node named `kaboom`.

> **Note**
>
> Some steps of this process involve running commands as the Postgres owner. We refer to this user as postgres throughout, when appropriate. If you're running EDB Postgres Advanced Server, substitute the postgres user with enterprisedb in all relevant commands.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Confirm the current Postgres version

SSH into kaboom to confirm the major version of Postgres is expected:

```
sudo -u postgres pgd nodes list --
versions
```

The output will be similar to this for your cluster:

```
Node Name BDR Version                   Postgres Version
--------- ----------------------------- --------------------------------
kaboom    5.7.0-dev (snapshot 8516bb3ab) 16.6 (Debian 16.6-1EDB.bullseye)
kaftan    5.7.0-dev (snapshot 8516bb3ab) 16.6 (Debian 16.6-1EDB.bullseye)
kaolin    5.7.0-dev (snapshot 8516bb3ab) 16.6 (Debian 16.6-1EDB.bullseye)
```

Confirm that the Postgres version is the expected version.

Verify that the target node isn't the write leader

The cluster must be available throughout the process (that is, a*rolling* upgrade). There must always be an available write leader to maintain continuous cluster availability. So, if the target node is the current write leader, you must perform a planned switchover of the write leader node before upgrading it so that a write leader is always available.

While connected via SSH to kaboom, see which node is the current write leader of the group you're upgrading using the `pgd group show --summary` command:

```
sudo -u postgres pgd group dc1_subgroup show --
summary
```

In this case, you can see that kaboom is the current write leader of the sole subgroup `dc1_subgroup`:

```
Group Property    Value
----------------- ------------
Group Name        dc1_subgroup
Parent Group Name democluster
Group Type        data
Write Leader      kaboom
Commit Scope
```

So you must perform a planned switchover of the write leader of `dc1_subgroup` to another node in the cluster.

Perform a planned switchover

Change the write leader to kaftan so kaboom's Postgres instance can be stopped:

```
sudo -u postgres pgd group dc1_subgroup set-leader
kaftan
```

After the switchover is successful, this message appears:

```
Command executed successfully
```

Then it's safe to stop Postgres on the target node. Of course, if kaftan is switched back to being the write leader when you come to upgrading it, you'll need to perform another planned switchover at that time.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Stop Postgres on the target node

While connected via SSH to the target node (in this case, kaboom), stop Postgres on the node by running:

```
sudo systemctl stop
postgres
```

This command halts the server on kaboom. Your cluster continues running using the other two nodes.

Install PGD and utilities

Next, install the new version of Postgres (PG17) and the upgrade tool:

```
sudo apt install edb-bdr5-pg17 edb-bdr-
utilities
```

Initialize the new Postgres instance

Make a new data directory for the upgraded Postgres, and give the postgres user ownership of the directory:

```
sudo mkdir
/opt/postgres/datanew
sudo chown -R postgres:postgres
/opt/postgres/datanew
```

Then, initialize Postgres 17 in the new directory:

```
sudo -u postgres /usr/lib/postgresql/17/bin/initdb
\
  -D /opt/postgres/datanew
\
  -E UTF8 \
  --lc-collate=en_US.UTF-8 \
  --lc-ctype=en_US.UTF-8 \
  --data-checksums
```

This command populates the PG17 data directory for configuration, `/opt/postgres/datanew`.

Migrate configuration to the new Postgres version

The next step copies the configuration files from the old Postgres version (PG16) to the new Postgres version's (PG17). Configuration files reside in each version's data directory.

Copy over the `postgresql.conf`, `postgresql.auto.conf`, and `pg_hba.conf` files and the whole `conf.d` directory:

```
sudo -u postgres cp /opt/postgres/data/postgresql.conf
/opt/postgres/datanew/
sudo -u postgres cp /opt/postgres/data/postgresql.auto.conf
/opt/postgres/datanew/
sudo -u postgres cp /opt/postgres/data/pg_hba.conf
/opt/postgres/datanew/
sudo -u postgres cp -r /opt/postgres/data/conf.d/
/opt/postgres/datanew/
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Verify the Postgres service is inactive

Although you previously stopped the Postgres service on the target node, kaboom, to verify it's stopped, run the `systemctl status postgres` command:

```
sudo systemctl status
postgres
```

The output of the `status` command shows that the Postgres service has stopped running:

```
● postgres.service - Postgres 16 (TPA)
     Loaded: loaded (/etc/systemd/system/postgres.service; enabled; vendor preset: enabled)
     Active: inactive (dead) since Tue 2025-02-11 18:14:25 UTC; 7min ago
   Main PID: 20370 (code=exited, status=0/SUCCESS)
        CPU: 11.375s

Feb 11 18:14:25 kaboom postgres[21066]: [22-1] 2025-02-11 18:14:25 UTC [pgdproxy@10.33.217.238(194>
Feb 11 18:14:25 kaboom postgres[20372]: [24-1] 2025-02-11 18:14:25 UTC [@//:20372]: [15] LOG:  che>
Feb 11 18:14:25 kaboom postgres[21067]: [22-1] 2025-02-11 18:14:25 UTC [pgdproxy@10.33.217.237(426>
Feb 11 18:14:25 kaboom postgres[21068]: [22-1] 2025-02-11 18:14:25 UTC [pgdproxy@10.33.217.237(426>
Feb 11 18:14:25 kaboom postgres[20370]: [22-1] 2025-02-11 18:14:25 UTC [@//:20370]: [23] LOG:  dat>
Feb 11 18:14:25 kaboom systemd[1]: postgres.service: Succeeded.
Feb 11 18:14:25 kaboom systemd[1]: Stopped Postgres 16 (TPA).
```

Swap PGDATA directories for version upgrade

Next, swap the PG16 and PG17 data directories:

```
sudo mv /opt/postgres/data
/opt/postgres/dataold
sudo mv /opt/postgres/datanew
/opt/postgres/data
```

> **Important**
>
> If something goes wrong at some point during the procedure, you may want to roll back/revert a node to the older major version. To do this, rename directories again so that the current data directory, `/opt/postgres/data`, becomes `/opt/postgres/datafailed` and the old data directory, `/opt/postgres/dataold`, becomes the current data directory:
>
> ```
> sudo mv /opt/postgres/data
> /opt/postgres/datafailed
> sudo mv /opt/postgres/dataold
> /opt/postgres/data
> ```
>
> This rolls back/reverts the node to the previous major version of Postgres.

Verify upgrade feasibility

The `pgd node upgrade` tool has a `--check` option, which performs a dry run of some of the upgrade process. You can use this option to ensure the upgrade goes smoothly.

However, first, you need a directory for the files created by `pgd node upgrade`. For this example, create an `/upgrade` directory in the `/home` directory. Then give ownership of the directory to the user postgres.

```
sudo mkdir /home/upgrade
sudo chown postgres:postgres /home/upgrade
```

Next, navigate to `/home/upgrade` and run:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
sudo -u postgres pgd node kaboom upgrade
\
  --old-bindir /usr/lib/postgresql/16/bin/ \
  --new-bindir /usr/lib/postgresql/17/bin/ \
  --old-datadir /opt/postgres/dataold/ \
  --new-datadir /opt/postgres/data/
\
  --database bdrdb \
  --username postgres
\
  --check
```

The following is the output:

```
Performing BDR Postgres Checks
------------------------------
Getting old PG instance shared directory                    ok
Getting new PG instance shared directory                    ok
Collecting pre-upgrade new PG instance control data         ok
Checking new cluster state is shutdown                      ok
Checking BDR extension versions                             ok
Checking Postgres versions                                  ok

Finished BDR pre-upgrade steps, calling pg_upgrade
--------------------------------------------------

Performing Consistency Checks
-----------------------------
Checking cluster versions                                   ok
Checking database user is the install user                  ok
Checking database connection settings                       ok
Checking for prepared transactions                          ok
Checking for contrib/isn with bigint-passing mismatch       ok
Checking data type usage                                    ok
Checking for presence of required libraries                 ok
Checking database user is the install user                  ok
Checking for prepared transactions                          ok
Checking for new cluster tablespace directories             ok

*Clusters are compatible*
```

!!! Note

If you didn't initialize Postgres 17 with checksums using the `--data-checksums` option but did initialize checksums with your Postgres 16 instance, an error tells you about the incompatibility:

```
old cluster uses data checksums but the new one does
not
```

Execute the Postgres major version upgrade

You're ready to run the upgrade. On the target node, run:

```
sudo -u postgres pgd node kaboom upgrade
\
  --old-bindir /usr/lib/postgresql/16/bin/ \
  --new-bindir /usr/lib/postgresql/17/bin/ \
  --old-datadir /opt/postgres/dataold/ \
  --new-datadir /opt/postgres/data/
\
  --database bdrdb \
  --username
postgres
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

The following is the expected output:

```
Performing BDR Postgres Checks
------------------------------
Getting old PG instance shared directory                      ok
Getting new PG instance shared directory                      ok
Collecting pre-upgrade new PG instance control data           ok
Checking new cluster state is shutdown                        ok
Checking BDR extension versions                               ok
Checking Postgres versions                                    ok

Collecting Pre-Upgrade BDR Information
--------------------------------------
Collecting pre-upgrade old PG instance control data           ok
Starting old PG instance                                      ok
Connecting to the old PG instance                             ok
Checking for BDR extension                                    ok
Checking BDR node name                                        ok
Terminating connections to database                           ok
Waiting for all slots to be flushed                           ok
Disconnecting from old cluster PG instance                    ok
Stopping old PG instance                                      ok
Starting old PG instance with BDR disabled                    ok
Connecting to the old PG instance                             ok
Collecting replication origins                                ok
Collecting replication slots                                  ok
Disconnecting from old cluster PG instance                    ok
Stopping old PG instance                                      ok

Finished BDR pre-upgrade steps, calling pg_upgrade
--------------------------------------------------

Performing Consistency Checks
-----------------------------
Checking cluster versions                                     ok
Checking database user is the install user                    ok
Checking database connection settings                         ok
Checking for prepared transactions                            ok
Checking for contrib/isn with bigint-passing mismatch         ok
Checking data type usage                                      ok
Creating dump of global objects                               ok
Creating dump of database schemas
                                                              ok
Checking for presence of required libraries                   ok
Checking database user is the install user                    ok
Checking for prepared transactions                            ok
Checking for new cluster tablespace directories               ok

If pg_upgrade fails after this point, you must re-initdb the
new cluster before continuing.

Performing Upgrade
------------------
Setting locale and encoding for new cluster                   ok
Analyzing all rows in the new cluster                         ok
Freezing all rows in the new cluster                          ok
Deleting files from new pg_xact                               ok
Copying old pg_xact to new server                             ok
Setting oldest XID for new cluster                            ok
Setting next transaction ID and epoch for new cluster         ok
Deleting files from new pg_multixact/offsets                  ok
Copying old pg_multixact/offsets to new server                ok
Deleting files from new pg_multixact/members                  ok
Copying old pg_multixact/members to new server                ok
Setting next multixact ID and offset for new cluster          ok
Resetting WAL archives                                        ok
Setting frozenxid and minmxid counters in new cluster         ok
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
Restoring global objects in the new cluster                   ok
Restoring database schemas in the new cluster
                                                              ok
Copying user relation files
                                                              ok
Setting next OID for new cluster                              ok
Sync data directory to disk                                   ok
Creating script to delete old cluster                         ok
Checking for extension updates                                notice

Your installation contains extensions that should be updated
with the ALTER EXTENSION command.  The file
    update_extensions.sql
when executed by psql by the database superuser will update
these extensions.

Upgrade Complete
----------------
Optimizer statistics are not transferred by pg_upgrade.
Once you start the new server, consider running:
    /usr/lib/postgresql/17/bin/vacuumdb -U postgres --all --analyze-in-stages
Running this script will delete the old cluster's data files:
    ./delete_old_cluster.sh

pg_upgrade complete, performing BDR post-upgrade steps
------------------------------------------------------
Collecting post-upgrade old PG instance control data          ok
Collecting post-upgrade new PG instance control data          ok
Checking LSN of the new PG instance                           ok
Starting new PG instance with BDR disabled                    ok
Connecting to the new PG instance                             ok
Creating replication origin bdr_bdrdb_democluster11_kaolin    ok
Advancing replication origin bdr_bdrdb_democluster11_kaol...  ok
Creating replication origin pgl_writer_origin_2_1             ok
Advancing replication origin pgl_writer_origin_2_1 to 0/2...  ok
Creating replication origin bdr_bdrdb_democluster11_kaftan    ok
Advancing replication origin bdr_bdrdb_democluster11_kaft...  ok
Creating replication origin pgl_writer_origin_4_1             ok
Advancing replication origin pgl_writer_origin_4_1 to 0/2...  ok
Creating replication slot bdr_bdrdb_democluster11_kaolin      ok
Creating replication slot bdr_bdrdb_democluster11_kaftan      ok
Creating replication slot bdr_bdrdb_democluster11             ok
Stopping new PG instance
```

Update the Postgres service configuration

The Postgres service on the system is configured to start the old version of Postgres (PG16). You need to modify the `postgres.service` file to start the new version (PG17).

You can do this using `sed` to replace the old version number `16` with `17` throughout the file.

```
sudo sed -i -e  's/16/17/g'
/etc/systemd/system/postgres.service
```

After you've changed the version number, you can tell the systemd daemon to reload the configuration. On the target node, run:

```
sudo systemctl daemon-reload
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Restart Postgres

Start the modified Postgres service:

```
sudo systemctl start
postgres
```

Update the extensions

After the upgrade, you may need to update the extensions. The upgrade process checks for extension updates and generates a script named `updated_extensions.sql` in the current directory if needed. In this case, no script was generated, so no extensions need updating.

Validate the new Postgres version

Repeating the first step, check the version of Postgres to confirm that you upgraded kaboom correctly. While still on kaboom, run:

```
sudo -u postgres pgd nodes list --
versions
```

Use the output to confirm that kaboom is running the upgraded Postgres version:

```
Node Name BDR Version Postgres Version
--------- ----------- --------------------------------
kaboom    5.7.0       17.3 (Debian 17.3-1EDB.bullseye)
kaftan    5.7.0       16.7 (Debian 16.7-1EDB.bullseye)
kaolin    5.7.0       16.7 (Debian 16.7-1EDB.bullseye)
```

Here kaboom has been upgraded to major version 17.

Clean up post-upgrade

As a best practice, run a vacuum over the database at this point. When the upgrade ran, you may have noticed the post-upgrade report included:

```
Once you start the new server, consider running:
    /usr/lib/postgresql/17/bin/vacuumdb --all --analyze-in-stages
```

You can run the vacuum now. On the target node, run:

```
sudo -u postgres /usr/lib/postgresql/17/bin/vacuumdb --all --analyze-in-
stages
```

If you're sure you don't need to revert this node, you can also clean up the old data directory folder `dataold`:

```
sudo rm -r
/opt/postgres/dataold
```

Upgrading the target node is now complete.

Next steps

After completing the upgrade on kaboom, run the same steps on kaolin and kaftan.

If you followed along with this example and kaftan is the write leader, to ensure availability, you must perform a planned switchover to another node that was already upgraded before running the upgrade steps on kaftan.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Check Postgres versions across the cluster

After completing the upgrade on all nodes, while connected to one of the nodes, you can check your versions again:

```
sudo -u postgres pgd nodes list --
versions
```

The output will be similar to the following:

```
Node Name BDR Version Postgres Version
--------- ----------- --------------------------------
kaboom    5.7.0       17.3 (Debian 17.3-1EDB.bullseye)
kaftan    5.7.0       17.3 (Debian 17.3-1EDB.bullseye)
kaolin    5.7.0       17.3 (Debian 17.3-1EDB.bullseye)
```

This output shows that all the nodes are successfully upgraded to the new Postgres version 17.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

22 Data migration to EDB Postgres Distributed

Moving data from one data source to another is a common task in the world of data management. This section provides information on how to migrate data to EDB Postgres Distributed from various data sources.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

22.1 EDB*Loader and PGD

EDB*Loader is a high-speed data loading utility for EDB Postgres Advanced Server. It provides an interface compatible with Oracle databases, allowing you to load data into EDB Postgres Advanced Server. It's designed to load large volumes of data into EDB Postgres Advanced Server quickly and efficiently.

The EDB*Loader command line utility loads data from an input source into one or more tables using a subset of the parameters offered by Oracle SQL*Loader. The source can be a flat file, pipe, or other programs.

Use with PGD

As EDB*Loader is a utility for EDB Postgres Advanced Server, it's available for EDB Postgres Distributed when EDB Postgres Advanced Server is the database in use for PGD data nodes. PGD deployments can use EDB*Loader in the same way as it's used on EDB Postgres Advanced Server. See the EDB*Loader documentation for more information on how to use EDB*Loader with EDB Postgres Advanced Server.

Replication and EDB*Loader

As with EDB Postgres Advanced Server, EDB*Loader works with PGD in a replication environment. You cannot use the direct load path method because the direct path load method skips use of the WAL, upon which all replication relies. That means that only the node connected to by EDB*Loader gets the data that EDB*Loader is loading and no data replicates to the other nodes.

With PGD, you can make use of EDB*loader's direct load path method by running it independently on each node. You can perform this either on one node at a time or in parallel to all nodes, depending on the use case. When using the direct path load method on multiple nodes, it's important to ensure there are no other writes happening to the table concurrently as this can result in inconsistencies.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23 EDB Postgres Distributed Command Line Interface (PGD CLI)

The EDB Postgres Distributed Command Line Interface (PGD CLI) is a tool for managing your EDB Postgres Distributed cluster. It's the key tool for inspecting and managing cluster resources.

It allows you to run commands against EDB Postgres Distributed clusters to:

- Determine the health of the cluster, inspect the cluster's configuration, and manage the cluster's resources.
- Inspect and manage the cluster's nodes and groups.
- Perform a write-leader change operation on the group.

PGD CLI is installed automatically on systems in a TPA-deployed PGD cluster.

You can also install it manually on Linux and macOS systems that can connect to a PGD cluster, including:

- EDB Cloud Service distributed high-availability clusters.
- PGD clusters deployed using the EDB PGD for Kubernetes operator.
- Manually deployed PGD clusters.
- TPA-deployed PGD clusters.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.1 Installing PGD CLI

You can install PGD CLI on any system that can connect to the PGD cluster. Linux and macOS are currently supported platforms to install PGD CLI on.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.1.1 Installing PGD CLI on Linux

PGD CLI is available for most Linux distributions. You can install it from the EDB repositories, which you can access with your EDB account. PGD users and EDB Cloud Service users, including those on a free trial, have an EDB account and access to PGD CLI.

Obtain your EDB subscription token

To install the PGD CLI, you will need an EDB Repos 2.0 token to gain access to the EDB private software repositories. For instructions on obtaining this token, see:Get your token.

Set the EDB_SUBSCRIPTION_TOKEN environment variable

Once you have the token, execute the command shown for your operating system, substituting your token for `<your-token>`.

```
export EDB_SUBSCRIPTION_TOKEN=<your-token>
```

Then run the appropriate commands for your operating system.

Install on Debian or Ubuntu

```
curl -1sSLf "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.deb.sh" | sudo -E
bash
```

If this command returns an error like `curl: (22) The requested URL returned error: 404`, check that you entered the correct token.

When the command is successful, you'll see output like this:

```
Executing the  setup script for the 'enterprisedb/postgres_distributed' repository ...
...
```

You can now install the PGD CLI package using the command:

```
sudo apt-get install edb-pgd5-cli
```

Install on RHEL, Rocky, AlmaLinux, or Oracle Linux

```
curl -1sSLf "https://downloads.enterprisedb.com/$EDB_SUBSCRIPTION_TOKEN/postgres_distributed/setup.rpm.sh" | sudo -E
bash
```

If this command returns an error like `curl: (22) The requested URL returned error: 404`, check that you entered the correct token.

When the command is successful, you'll see output like this:

```
Executing the  setup script for the 'enterprisedb/postgres_distributed' repository ...
...
```

You can now install the PGD CLI package using the command:

```
sudo yum install edb-pgd5-cli
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Next: Using PGD CLI

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.1.2 Installing PGD CLI on macOS

PGD CLI is available for macOS as a Homebrew formula. To install it, run the following commands:

```
brew tap enterprisedb/tap
brew install pgd-cli
```

To verify the installation, run:

```
pgd --version
```

Next: Using PGD CLI

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.1.3 Installing PGD CLI with TPA

By default, Trusted Postgres Architect installs and configures PGD CLI on each PGD node.

If you want to install PGD CLI on any non-PGD instance in the cluster, attach the pgdcli role to that instance in Trusted Postgres Architect's configuration file before deploying.

See Trusted Postgres Architect for more information.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.2 Using PGD CLI

What is the PGD CLI?

The PGD CLI is a convenient way to connect to and manage your PGD cluster. To use it, you need a user with PGD superuser privileges or equivalent. The PGD user with superuser privileges is the bdr_superuser role. An example of an equivalent user is edb_admin on an EDB Cloud Service distributed high-availability cluster.

> **Setting passwords**
>
> PGD CLI doesn't interactively prompt for your password. You must pass your password using one of the following methods:
>
> - Adding an entry to your `.pgpass` password file, which includes the host, port, database name, user name, and password.
> - Setting the password in the `PGPASSWORD` environment variable.
> - Including the password in the connection string.
>
> We recommend the first option, as the other options don't scale well with multiple databases, or they compromise password confidentiality.

Running the PGD CLI

Once you have installed pgd-cli, run the `pgd` command to access the PGD command line interface. The `pgd` command needs details about the host, port, and database to connect to, along with your username and password.

Passing a database connection string

Use the `--dsn` flag to pass a database connection string to the `pgd` command. When you pass the connection string with the `--dsn` flag, you don't need a configuration file. The flag takes precedence even if a configuration file is present. For example:

```
pgd nodes list --dsn "host=bdr-a1 port=5432 dbname=bdrdb user=enterprisedb"
```

See PGD CLI Command reference for a description of the command options.

Specifying a configuration file

If a `pgd-cli-config.yml` file is in `/etc/edb/pgd-cli` or `$HOME/.edb/pgd-cli`, `pgd` uses it. You can override this behavior using the optional `-f` or `--config-file` flag. For example:

```
pgd nodes list -f /opt/my-
config.yml
```

output

```
Node Name Group Name   Node Kind Join State Node Status
--------- ------------ --------- ---------- -----------
kaftan    dc1_subgroup data      ACTIVE     Up
kaolin    dc1_subgroup data      ACTIVE     Up
kaboom    dc1_subgroup data      ACTIVE     Up
```

Specifying the output format

Use the `-o` or `--output` flag to change the default output format to JSON. For example:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
pgd nodes list -o json
[

{
    "node_name": "kaftan",
    "node_group_name": "dc1_subgroup",
    "node_kind_name": "data",
    "join_state": "ACTIVE",
    "node_status": "Up",
    "node_id":
3490219809,
    "node_seq_id": 2,
    "node_local_dbname": "bdrdb"
  },
  {
    "node_name": "kaolin",
    "node_group_name": "dc1_subgroup",
    "node_kind_name": "data",
    "join_state": "ACTIVE",
    "node_status": "Up",
    "node_id":
2111777360,
    "node_seq_id": 1,
    "node_local_dbname": "bdrdb"
  },
  {
    "node_name": "kaboom",
    "node_group_name": "dc1_subgroup",
    "node_kind_name": "data",
    "join_state": "ACTIVE",
    "node_status": "Up",
    "node_id":
2710197610,
    "node_seq_id": 3,
    "node_local_dbname": "bdrdb"
  }
]
```

The PGD CLI supports the following output formats.

Setting	Format	Description
`simple`	Tabular	A simple tabular view. (Default).
`json`	JSON	Presents the raw data with no formatting. For some commands, the JSON output might show more data than the tabular output, such as extra fields and more detailed messages.
`psql`	PSQL	A tabular view in the style of PSQL output. format.
`modern`	Tabular	A tabular view which uses box characters to deliniate the table.
`markdown`	Markdown	A Markdown style output which may product long-form, non-tabular output for some commands such as `pgd assess`.

Accessing the command line help

To list the supported commands, enter:

```
pgd --help
```

For help with a specific command and its parameters, enter `pgd <command_name> --help`. For example:

```
pgd nodes list --help
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Avoiding stale data**
>
> The PGD CLI can return stale data on the state of the cluster if it's still connecting to nodes previously parted from the cluster. Edit the `pgd-cli-config.yml` file, or change your `--dsn` settings to ensure you are connecting to active nodes in the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.3 Configuring PGD CLI

PGD CLI can be installed on any system that can connect to the PGD cluster. To use PGD CLI, you need a user with PGD superuser privileges or equivalent. The PGD user with superuser privileges is the bdr_superuser role. An example of an equivalent user is edb_admin on a EDB Cloud Service distributed high-availability cluster.

PGD CLI and database connection strings

You might not need a database connection string. For example, when Trusted Postgres Architect installs the PGD CLI on a system, it also configures the connection to the PGD cluster, which means that the PGD CLI can connect to the cluster when run.

If you're installing PGD CLI manually, you must give PGD CLI a database connection string so it knows which PGD cluster to connect to.

> **Setting passwords**
>
> PGD CLI doesn't interactively prompt for your password. You must pass your password using one of the following methods:
>
> - Adding an entry to your `.pgpass` password file, which includes the host, port, database name, user name, and password.
> - Setting the password in the `PGPASSWORD` environment variable.
> - Including the password in the connection string.
>
> We recommend the first option, as the other options don't scale well with multiple databases, or they compromise password confidentiality.

If you don't know the database connection strings for your PGD-powered deployment, see discovering connection strings, which helps you to find the right connection strings for your cluster.

Once you have that information, you can continue.

Configuring the database to connect to

PGD CLI takes its database connection information from either the PGD CLI configuration file or the command line.

Using database connection strings in the command line

You can pass the connection string directly to `pgd` using the `--dsn` option. For details, see the sample use case. For example:

```
pgd --dsn "host=kaboom port=5444 user=enterprisedb dbname=bdrdb" nodes show --versions
```

Using a configuration file

Use the `pgd-cli-config.yml` configuration file to specify the database connection string for your cluster. The configuration file must contain the database connection string for at least one PGD node in the cluster. The cluster name is optional and isn't validated.

For example:

```
cluster:
  name: cluster-
name
  endpoints:
  - "host=bdr-a1 port=5444 dbname=bdrdb user=enterprisedb"
  - "host=bdr-b1 port=5444 dbname=bdrdb user=enterprisedb"
  - "host=bdr-c1 port=5444 dbname=bdrdb user=enterprisedb"
```

By default, `pgd-cli-config.yml` is located in the `/etc/edb/pgd-cli` directory. The PGD CLI searches for `pgd-cli-config.yml` in the following locations. Precedence order is high to low.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

1. `/etc/edb/pgd-cli` (default)
2. `$HOME/.edb/pgd-cli`

If your configuration file isn't in either of these directories, you can use the optional `-f` or `--config-file` flag on a `pgd` command to set the file to read as configuration. See the sample use case.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.4 Discovering connection strings

You can install PGD CLI on any system that can connect to the PGD cluster. To use PGD CLI, you need a user with PGD superuser privileges or equivalent. The PGD user with superuser privileges is the bdr_superuser role. An example of an equivalent user is edb_admin on an EDB Cloud Service distributed high-availability cluster.

PGD CLI and database connection strings

You might not need a database connection string. For example, when Trusted Postgres Architect installs the PGD CLI on a system, it also configures the connection to the PGD cluster. This means that PGD CLI can connect to the cluster when run.

Getting your database connection string

Because of the range of different configurations that PGD supports, every deployment method has a different way of deriving a connection string for it. Generally, you can obtain the required information from the configuration of your deployment. You can then assemble that information into connection strings.

For a TPA-deployed PGD cluster

Because TPA is so flexible, you have to derive your connection string from your cluster configuration file (`config.yml`).

- You need the name or IP address of a host with the role pgd-proxy listed for it. This host has a proxy you can connect to. Usually the proxy listens on port 6432. (Check the setting for `default_pgd_proxy_options` and `listen_port` in the config to confirm.)
- The default database name is `bdrdb` . (Check the setting `bdr_database` in the config to confirm.)
- The default PGD superuser is enterprisedb for EDB Postgres Advanced Server and postgres for PostgreSQL and EDB Postgres Extended Server.

You can then assemble a connection string based on that information:

```
"host=<hostnameOrIPAddress> port=<portnumber> dbname=<databasename> user=<username> sslmode=require"
```

To illustrate this, here are some excerpts of a `config.yml` file for a cluster:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
...
cluster_vars:

...
  bdr_database: bdrdb

...

default_pgd_proxy_options:
    listen_port: 6432

...

instances:
- Name:
kaboom
  backup: kapok
  location:
dc1
  node:
1
  role:
  -
bdr
  - pgd-
proxy
  networks:
  - ipv4_address:
192.168.100.2
    name:
tpanet
...
```

The connection string for this cluster is:

```
"host=192.168.100.2 port=6432 dbname=bdrdb user=enterprisedb sslmode=require"
```

> **Host name versus IP address**
>
> The example uses the IP address because the configuration is from a Docker TPA install with no name resolution available. Generally, you can use the host name as configured.

For an EDB Cloud Service distributed high-availability cluster

1. Log in to the Cloud Service clusters view.
2. In the filter, set **Cluster Type** to **Distributed High Availability** to show only clusters that work with PGD CLI.
3. Select your cluster.
4. In the view of your cluster, select the **Connect** tab.
5. Copy the read/write URI from the connection info. This is your connection string.

For a cluster deployed with EDB PGD for Kubernetes

As with TPA, EDB PGD for Kubernetes is very flexible, and there are multiple ways to obtain a connection string. It depends, in large part, on the configuration of the deployment's services:

- If you use the Node Service Template, direct connectivity to each node and proxy service is available.
- If you use the Group Service Template, there's a gateway service to each group.
- If you use the Proxy Service Template, a single proxy provides an entry point to the cluster for all applications.

Consult your configuration file to determine this information.

Establish a host name or IP address, port, database name, and username. The default database name is `bdrdb`. The default username is enterprisedb for EDB Postgres Advanced Server and postgres for PostgreSQL and EDB Postgres Extended Server.

You can then assemble a connection string based on that information:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
"host=<hostnameOrIPAddress> port=<portnumber> dbname=<databasename> user=<username>"
```

If the deployment's configuration requires it, add `sslmode=<sslmode>`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5 Command reference

The command name for the PGD command line interface is `pgd`.

Synopsis

The EDB Postgres Distributed Command Line Interface (PGD CLI) is a tool to manage your EDB Postgres Distributed cluster. It allows you to run commands against EDB Postgres Distributed clusters. You can use it to inspect and manage cluster resources.

Commands

- cluster: Cluster-level commands for managing the cluster.
  - show: Show cluster-level information.
  - verify: Verify cluster-level information.
- group: Group-level commands for managing groups.
  - show: Show group-level information.
  - set-option: Set group-level options.
  - get-option: Get group-level options.
  - set-leader: Set the write leader of a group (perform a switchover).
- groups: Group related commands for listing groups.
  - list: List groups.
- node: Node-level commands for managing nodes.
  - show: Show node-level information.
  - set-option: Set node-level options.
  - get-option: Get node-level options.
  - upgrade: Perform a major version upgrade of a PGD Postgres node.
- nodes: Node related commands for listing nodes.
  - list: List nodes.
- events: Event log commands for viewing events.
  - show: Show events.
- replication: Replication related-commands for managing replication.
  - show: Show replication information.
- raft: Raft related commands for managing Raft consensus.
  - show: Show information about Raft state.
- commit-scope: Commit scope related commands for managing PGD commit scopes.
  - show: Show information about a commit-scope.
  - create: Create a commit-scope.
  - update: Update a commit-scope.
  - drop: Drop a commit-scope.
- assess: Assesses a Postgres server's PGD compatibility.
- completion: Generate shell completion scripts.

Global Options

All commands accept the following global options:

Short	Long	Description

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Short	Long	Description
`-f`	`--config-file`	Name/Path to config file. This is ignored if --dsn flag is present Default "/etc/edb/pgd-cli/pgd-cli-config.yml"
	`--dsn`	Database connection string For example "host=bdr-a1 port=5432 dbname=bdrdb user=postgres"
`-h`	`--help`	Help for pgd - will show specific help for any command used
`-o`	`--output`	Output format: `json` , `psql` , `modern` , `markdown` , `simple` (see Output formats)

Additional Options

Run `pgd -V` to see the version information for the pgd CLI.

Output formats

Used with the `-o` / `--output` ß option:

Format	Description
simple	Simple format - Output as a simple ASCII table (Default).
json	JSON format - Output as a JSON document, non-tabular
psql	PSQL format - Output as an ASCII table in the style of PSQL
modern	Modern format - Output as a table using box characters
markdown	Markdown table format - Output as a markdown compatible ASCII table

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.1 pgd assess

Synopsis

The `pgd assess` commands are used to assess the suitability of a Postgres server instance for migration to the EDB Postgres Distributed cluster.

The command must be run with a DSN that connects to the Postgres server instance that you want to assess. The command will check the Postgres server instance for compatibility with the EDB Postgres Distributed cluster, and will provide a report on the compatibility of the Postgres server instance.

Syntax

```
pgd assess [OPTIONS]
```

Options

The assess command has no command specific options.

See also Global Options.

Example

```
pgd
assess
```

output

```
Assessment                       Result                   Details
-------------------------------- ------------------------ ------------------------------------------------------------
---------
Multiple Databases               Compatible               Found only one user database
Sequences                        Compatible               No user sequences found
Tables with Multiple Unique Indexes Compatible               No tables with multiple unique indexes found
Materialized Views               Compatible               No materialized views found
EPAS Queue Tables                Compatible               No EPAS Queue Tables found
LOCK TABLE Usage                 Requires workload analysis Could not analyze LOCK TABLE usage with
pg_stat_statements
DDL Command Usage                Requires workload analysis Cannot be checked automatically at this time
LISTEN/NOTIFY Usage              Requires workload analysis Could not analyze LISTEN/NOTIFY usage with
pg_stat_statements
Row-Level Lock Usage             Requires workload analysis Could not analyze row-level locking commands using
pg_stat_statements
Advisory Lock Usage              Requires workload analysis Could not analyze advisory lock commands using
pg_stat_statements
Large Objects                    Compatible               No large objects found
Trigger/Reference Privileges     Compatible               No triggers with incompatible privileges found
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.2 pgd cluster

The `pgd cluster` commands are used to manage the EDB Postgres Distributed cluster.

Subcommands

- show: Show cluster-level information.
- verify: Verify cluster-level information.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.2.1 pgd cluster show

Synopsis

The `pgd cluster show` command is used to display the cluster-level information in the EDB Postgres Distributed cluster.

Syntax

```
pgd cluster show [OPTIONS]
```

Options

The following table lists the options available for the `pgd cluster show` command:

Short	Long	Description
	--clock-drift	Only show detailed clock drift information.
	--summary	Only show cluster summary information.
	--health	Only show cluster health information.

Only one of the above options can be specified at a time.

See also Global Options.

Clock Drift

Please note that the current implementation of clock drift may return an inaccurate value if the cluster is under high load while running this command or has large number of nodes in it.

Symbol	Meaning
`*`	ok
`~`	warning (drift > 2 seconds)
`!`	critical (drift > 5 seconds)
`x`	down / unreachable
`?`	unknown
`-`	not applicable

Examples

Display the cluster information

```
pgd cluster show
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

output

```
# Summary
Group Name    Parent Group  Group Type Node Name Node Kind
------------- ------------- ---------- --------- ---------
democluster                 global
dc1_subgroup  democluster   data       kaboom    data
dc1_subgroup  democluster   data       kaftan    data
dc1_subgroup  democluster   data       kaolin    data

# Health
Check             Status Details
----------------- ------ -----------------------------------------------
Connections       Ok     All BDR nodes are accessible
Raft              Ok     Raft Consensus is working correctly
Replication Slots Ok     All PGD replication slots are working correctly
Clock Drift        Ok     Clock drift is within permissible limit
Versions          Ok     All nodes are running the same PGD version

# Clock Drift
Reference Node Node Name Clock Drift
-------------- --------- -----------
kaftan         kaboom    *
kaftan         kaolin    *
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.2.2 pgd cluster verify

Synopsis

The `pgd cluster verify` command is used to verify the configuration of an EDB Postgres Distributed cluster.

Syntax

```
pgd cluster verify [OPTIONS]
```

Options

The following table lists the options available for the `pgd cluster verify` command:

Short	Long	Description
	--settings	Verify Postgres settings in the cluster
	--arch	Verify the cluster architecture
-v	--verbose	Display verbose output

With no option set, the command verifies both `settings` and `arch` by default and the output is not verbose.

Use `--verbose` alongside `--arch` or `--settings` to include detailed information and specific advice about the cluster status.

Include the global option `-o markdown` to display the results in an inline Markdown format.

See also Global Options.

Examples

Verify the cluster settings and architecture

```
pgd cluster verify
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

output

```
## Architecture
Check                   Status Groups
----------------------- ------ ------
Cluster has data nodes  Ok
Witness nodes per group Ok
Witness-only groups     Ok
Data nodes per group    Ok
Empty groups            Ok

# Settings
Setting Name                      Status
--------------------------------- ------
bdr.accept_connections            Ok
bdr.ddl_locking                   Ok
bdr.max_writers_per_subscription Ok
bdr.raft_group_max_connections    Ok
bdr.replay_progress_frequency     Ok
bdr.role_replication              Ok
bdr.standby_slot_names            Ok
bdr.standby_slots_min_confirmed   Ok
bdr.start_workers                 Ok
bdr.writers_per_subscription      Ok
bdr.xact_replication              Ok
max_connections                   Ok
max_prepared_transactions         Ok
max_replication_slots             Ok
max_wal_senders                   Ok
max_worker_processes              Ok
shared_preload_libraries          Ok
track_commit_timestamp            Ok
wal_level                         Ok
```

Verify the cluster architecture with verbose output

```
pgd cluster verify --verbose --arch
```

output

```
 Check                       | Status  | Groups | Details
-----------------------------+---------+--------+--------------------------------------------------
 Cluster has data nodes      | Ok      |        |
 Max data nodes in a cluster | Ok      |        |
 Witness nodes per group     | Ok      |        |
 Witness-only groups         | Ok      |        |
 Data nodes per group        | Ok      |        |
 Routing enabled groups      | Warning | dc-1   | Recommended to enable routing only on global-group dc-1
 Empty groups                | Ok      |        |
 Nodes have node kind set    | Ok      |        |
```

Verify the cluster architecture, display output Markdown formatted

```
pgd cluster verify --arch -o markdown
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

output

```
Cluster has data nodes
----------------------
Cluster must have at least one data node

Result: Ok


Max data nodes in a cluster
---------------------------
A PGD Essential cluster must have at most three data nodes

Result: Ok


Witness nodes per group
-----------------------
Each data group has at most one witness node

Result: Ok


Witness-only groups
-------------------
Cluster has at most one witness-only group

Result: Ok


Data nodes per group
--------------------
Each data group has at least one data node

Result: Ok


Routing enabled groups
----------------------
A PGD Essential cluster must have routing enabled for global group only

Following groups have problems:

 - dc-1

Details:

 - Recommended to enable routing only on global-group dc-1

Result: Warning


Empty groups
------------
There are no empty groups

Result: Ok


Nodes have node kind set
------------------------
All nodes should have node_kind properly set

Result: Ok
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.3 pgd commit-scope

The `pgd commit-scope` commands are used to display and manage the commit scopes in the EDB Postgres Distributed cluster.

Subcommands

- show: Show information about a commit scope.
- create: Create a commit scope.
- update: Update a commit scope.
- drop: Drop a commit scope.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.3.1 pgd commit-scope create

Synopsis

The `pgd commit-scope create` command is used to create a commit scope in the EDB Postgres Distributed cluster.

Syntax

```
pgd commit-scope <COMMIT_SCOPE> create [OPTIONS] <RULE_DEFINITION> [GROUP_NAME]
```

Where `<COMMIT_SCOPE>` is the name of the commit scope to create.

The `<RULE_DEFINITION>` is the rule that defines the commit scope. The rule specifies the conditions that must be met for a transaction to be considered committed. See Commit Scopes and Commit Scope Rules for more information on the rule syntax.

The optional `[GROUP_NAME]` is the name of the group to which the commit scope belongs. If omitted, it defaults to the top-level group.

Options

No command specific options. See Global Options.

Examples

Creating a Commit Scope

The following example creates a commit scope named `abc1` with the rule `ANY 2 (dc1) on replicated group commit` on the `dc1_subgroup` group:

```
pgd commit-scope abc1 create "ANY 2 (dc1_subgroup) SYNCHRONOUS COMMIT" dc1_subgroup
```

```
output
Command executed successfully
```

Verify the commit scope:

```
pgd commit-scope abc1 show
```

```
output
Commit Scope Group Name   Rule Definition
------------ ------------ ---------------------------------------
abc1         dc1_subgroup ANY 2 (dc1_subgroup) SYNCHRONOUS COMMIT
```

Creating a Commit Scope with the top-level group

The following example creates a commit scope named `abc2` with the rule `ANY 2 (dc1_subgroup) SYNCHRONOUS COMMIT` on the top-level group:

```
pgd commit-scope abc2 create "ANY 2 (dc1_subgroup) SYNCHRONOUS COMMIT"
```

```
output
Command executed successfully
```

Verify the commit scope:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
pgd commit-scope abc2 show
```

output

```
Commit Scope Group Name  Rule Definition
------------ ----------- ---------------------------------------
abc2         democluster ANY 2 (dc1_subgroup) SYNCHRONOUS COMMIT
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.3.2 pgd commit-scope drop

Synopsis

The `pgd commit-scope drop` command is used to drop a commit scope from the EDB Postgres Distributed cluster.

Syntax

```
pgd commit-scope <COMMIT_SCOPE> drop [OPTIONS] [GROUP_NAME]
```

Where `<COMMIT_SCOPE>` is the name of the commit scope to drop.

The optional `[GROUP_NAME]` is the name of the group to which the commit scope belongs. If omitted, it defaults to the top-level group. Note that the name of the group must match the group name the commit scope was created with.

Options

No command specific options. See Global Options.

Examples

Drop a Commit Scope

The following example drops the commit scope named `abc2` from the top-level group:

```
pgd commit-scope abc2 drop
```

```
output
Command executed successfully
```

Drop a Commit Scope from a Group

The following example drops the commit scope named `abc1` from the `dc1_subgroup` group:

```
pgd commit-scope abc1 drop dc1_subgroup
```

```
output
Command executed successfully
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.3.3 pgd commit-scope show

Synopsis

The `pgd commit-scope show` command is used to display information about a commit scope in the EDB Postgres Distributed cluster.

Syntax

```
pgd commit-scope <COMMIT_SCOPE> show [OPTIONS]
```

Where `<COMMIT_SCOPE>` is the name of the commit scope for which you want to display information.

Options

No command specific options. See Global Options.

Example

Showing a Commit Scope

The following example shows the information about the commit scope `abc1` :

```
pgd commit-scope abc1 show
```

```
                                                output
Commit Scope Group Name   Rule Definition
------------ ------------ ---------------------------------------
abc1         dc1_subgroup ANY 2 (dc1_subgroup) SYNCHRONOUS COMMIT
```

The `Group Name` column shows the name of the group to which the commit scope belongs. In this case, the commit scope belongs to the `dc1_subgroup` group.

The `Rule Definition` column shows the rule that defines the commit scope. In this case, the rule is `ANY 2 (dc1) SYCHRONOUS COMMIT` . The `dc1_subgroup` group is a replicated group, so the commit must be replicated to at least two nodes in the group and any two nodes within it must acknowledge the commit before it is considered committed.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.3.4 pgd commit-scope update

Synopsis

The `pgd commit-scope update` command is used to update a commit scope in the EDB Postgres Distributed cluster.

Syntax

```
pgd commit-scope <COMMIT_SCOPE> update [OPTIONS] <RULE_DEFINITION>[GROUP_NAME]
```

Where `<COMMIT_SCOPE>` is the name of the commit scope to update.

The `<RULE_DEFINITION>` is the rule that defines the commit scope. The rule specifies the conditions that must be met for a transaction to be considered committed. See Commit Scopes and Commit Scope Rules for more information on the rule syntax.

The optional `[GROUP_NAME]` is the name of the group to which the commit scope belongs. If omitted, it defaults to the top-level group.

Options

No command specific options. See Global Options.

Examples

Updating a Commit Scope

The following example updates the commit scope `abc1` with the rule `ANY 1 (dc1_subgroup) SYNCHRONOUS COMMIT`:

```
pgd commit-scope abc1 update "ANY 1 (dc1_subgroup) SYNCHRONOUS COMMIT" dc1_subgroup
```

```
output
Command executed successfully
```

Updating a Commit Scope in the Top-Level Group

The following example updates the commit scope `abc2` with the rule `ANY 1 (dc1_subgroup) SYNCHRONOUS COMMIT` in the top-level group:

```
pgd commit-scope abc2 update "ANY 1 (dc1_subgroup) SYNCHRONOUS COMMIT"
```

```
output
Command executed successfully
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.4 pgd completion

Synopsis

The `pgd completion` commands are used to manage the completion settings for the EDB Postgres Distributed CLI.

Syntax

```
pgd completion <SHELL>
```

Where `<SHELL>` is the shell for which to generate the autocompletion script.

Possible values for shell are `bash`, `fish`, `zsh` and `powershell`.

Options

No command specific options. See Global Options.

Example

```
pgd completion zsh
```

This command would normally be evaluated as part of a shell session's startup files. It generates a completion script for the Zsh shell and writes it to the standard output. Therfore you would add to your `.zshrc` file:

```
eval "$(pgd completion zsh)"
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.5 pgd events

The `pgd events` commands are used to display the events in the EDB Postgres Distributed cluster.

Subcommands

- show: Show events.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.5.1 pgd events show

Synopsis

The `pgd events show` command is used to display the events in the EDB Postgres Distributed cluster. With no additional flags, the command displays the 20 most recent events for all nodes and groups.

Syntax

```
pgd events show [OPTIONS]
```

Options

The following table lists the options available for the `pgd events show` command:

Short	Long	Description
	`--node <NODE_NAME>`	Only show events for the node with the specified name.
	`--group <GROUP_NAME>`	Only show events for the group with the specified name.
`-n`	`--limit <LIMIT>`	Limit the number of events to show. Defaults to 20.

See also Global Options.

Node States

State	Description
NONE	Node state is unset when the worker starts, expected to be set quickly to the current known state.
CREATED	bdr.create_node() has been executed, but the node isn't a member of any EDB Postgres Distributed cluster yet.
JOIN_START	bdr.join_node_group() begins to join the local node to an existing EDB Postgres Distributed cluster.
JOINING	The node join has started and is currently at the initial sync phase, creating the schema and data on the node.
CATCHUP	Initial sync phase is complete; now the join is at the last step of retrieving and applying transactions that were performed on the upstream peer node since the join started.
STANDBY	Node join has finished, but not yet started to broadcast changes. All joins spend some time in this state, but if defined as a Logical Standby, the node will continue in this state.
PROMOTE	Node was a logical standby and we just called bdr.promote_node to move the node state to ACTIVE. These two PROMOTE states have to be coherent to the fact, that only one node can be with a state higher than STANDBY but lower than ACTIVE.
PROMOTING	Promotion from logical standby to full BDR node is in progress.
ACTIVE	The node is a full BDR node and is currently ACTIVE. This is the most common node status.
PART_START	Node was ACTIVE or STANDBY and we just called bdr.part_node to remove the node from the EDB Postgres Distributed cluster.
PARTING	Node disconnects from other nodes and plays no further part in consensus or replication.
PART_CATCHUP	Non-parting nodes synchronize any missing data from the recently parted node.
PARTED	Node parting operation is now complete on all nodes.

Only one node at a time can be in either of the states PROMOTE or PROMOTING. STANDBY indicates that the node is in a read-only state.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Examples

Display the last 5 events

```
$ pgd events show -n 5
```

output

```
Event Time                     Event Observer Event Subject Event Source Event Type Event Subtype Event Text    Event
Detail
------------------------------ -------------- ------------- ------------ ---------- ------------- ------------- -------
-------------------------------------------------------------------------------------------
2025-02-21 17:44:00.444902 UTC kaolin         kaftan        consensus    ROUTING    STATE_CHANGE  WRITE_LEADER
dc1_subgroup
2025-02-21 17:44:00.445080 UTC kaolin         kaolin        consensus    ROUTING    STATE_CHANGE  RAFT_LEADER
{"raft_leader":"kaolin","group_name":"dc1_subgroup","read_nodes_version":1,"read_nodes":"kaboom,kaolin"}
2025-02-21 17:44:00.452029 UTC kaftan         kaftan        consensus    ROUTING    STATE_CHANGE  LEADER_UPDATE
2025-02-21 17:44:00.456483 UTC kaboom         kaboom        consensus    ROUTING    STATE_CHANGE  LEADER_UPDATE
2025-02-21 17:44:00.456667 UTC kaolin         kaolin        consensus    ROUTING    STATE_CHANGE  LEADER_UPDATE
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.6 pgd group

The `pgd group` commands are used to manage the groups in the EDB Postgres Distributed cluster.

Subcommands

- show: Show group-level information.
- set-option: Set group-level options.
- get-option: Get group-level options.
- set-leader: Set the write leader of a group (perform a switchover).

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.6.1 pgd group show

Synopsis

The `pgd group show` command is used to display group-level information in the EDB Postgres Distributed cluster.

Syntax

```
pgd group <GROUP_NAME> show [OPTIONS]
```

Where `<GROUP_NAME>` is the name of the group for which you want to display information.

Options

No command specific options. See Global Options.

Examples

Show group information

```
pgd group dc1_subgroup show
```

output

```
# Summary
Group Property    Value
----------------- -------------
Group Name        dc1_subgroup
Parent Group Name democluster15
Group Type        data
Write Leader      kaftan
Commit Scope

# Nodes
Node Name Node Kind Join State Node Status
--------- --------- ---------- -----------
kaftan    data      ACTIVE     Up
kaboom    data      ACTIVE     Up
kaolin    data      ACTIVE     Up

# Options
Option Name             Option Value
----------------------- --------------------
apply_delay             00:00:00 (inherited)
check_constraints       true (inherited)
default_commit_scope     (inherited)
enable_proxy_routing    true
enable_raft             true
enable_wal_decoder      false (inherited)
location                dc1
num_writers             -1 (inherited)
route_reader_max_lag    -1
route_writer_max_lag    -1
route_writer_wait_flush false
streaming_mode          default (inherited)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Show group information as JSON

```
pgd group dc1_subgroup show -o json
```

output


```
[
  {
    "Summary": [
      {
        "info": "Group Name",
        "value": "dc1_subgroup"
      },
      {
        "info": "Parent Group Name",
        "value": "democluster15"
      },
      {
        "info": "Group Type",
        "value": "data"
      },
      {
        "info": "Write Leader",
        "value": "kaftan"
      },
      {
        "info": "Commit Scope",
        "value": ""
      }
    ]
  },
  {
    "Nodes": [
      {
        "join_state": "ACTIVE",
        "node_kind_name": "data",
        "node_name": "kaftan",
        "node_status": "Up"
      },
      {
        "join_state": "ACTIVE",
        "node_kind_name": "data",
        "node_name": "kaboom",
        "node_status": "Up"
      },
      {
        "join_state": "ACTIVE",
        "node_kind_name": "data",
        "node_name": "kaolin",
        "node_status": "Up"
      }
    ]
  },
  {
    "Options": [
      {
        "option_name": "apply_delay",
        "option_value": "00:00:00 (inherited)"
      },
      {
        "option_name": "check_constraints",
        "option_value": "true (inherited)"
      },
      {
        "option_name": "default_commit_scope",
        "option_value": " (inherited)"
      },
      {
        "option_name": "enable_proxy_routing",
```


Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
        "option_value": "true"
      },
      {
        "option_name": "enable_raft",
        "option_value": "true"
      },
      {
        "option_name": "enable_wal_decoder",
        "option_value": "false (inherited)"
      },
      {
        "option_name": "location",
        "option_value": "dc1"
      },
      {
        "option_name": "num_writers",
        "option_value": "-1 (inherited)"
      },
      {
        "option_name": "route_reader_max_lag",
        "option_value": "-1"
      },
      {
        "option_name": "route_writer_max_lag",
        "option_value": "-1"
      },
      {
        "option_name": "route_writer_wait_flush",
        "option_value": "false"
      },
      {
        "option_name": "streaming_mode",
        "option_value": "default (inherited)"
      }
    ]
  }
]
```


Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.6.2 pgd group set-option

Synopsis

The `pgd group set-option` command is used to set group-level options in the EDB Postgres Distributed cluster.

Syntax

```
pgd group <GROUP_NAME> set-option [OPTIONS] <OPTION> <VALUE>
```

Where `<GROUP_NAME>` is the name of the group for which you want to get options.

And `<OPTION>` is the name of a specific group option you want to get and `<VALUE>` is the value you want it set to. The following options are available:

Group options

Option	Description
apply_delay	The delay in applying changes to the group.
check_constraints	Whether to check constraints in the group.
default_commit_scope	The default commit scope of the group.
enable_proxy_routing	Whether to enable proxy routing in the group.
enable_raft	Whether to enable Raft in the group.
enable_wal_decoder	Whether to enable the WAL decoder in the group.
location	The location of the group.
num_writers	The number of writers in the group.
route_reader_max_lag	The maximum lag for the reader in the group.
route_writer_max_lag	The maximum lag for the writer in the group.
streaming_mode	The streaming mode of the group.
route_writer_wait_flush	The wait time for flushing the writer in the group.
default_seqkind	The default sequence kind of the group.
default_replica_identity	The default replica identity of the group.
conflict_detection_method	The conflict detection method of the group.
replay_progress_frequency	The replay progress frequency of the group.
batch_inserts	Whether to enable batch inserts in the group.
analytics_storage_location	The storage location for analytics in the group.
analytics_autoadd_tables	Whether to automatically add tables to analytics in the group.

Group Connection Manager options

Option	Description
read_write_port	which port to listen on for read-write connections
read_only_port	which port to listen on for read-only connections
http_port	which http port to listen for REST API calls (for integration purposes)
use_https	whether http listener should use HTTPS, if enabled, the server certificate is used to TLS
read_write_max_client_connections	maximum read-write client connections allowed, defaults to max_connections
read_write_max_server_connections	maximum read-write connections that will be opened to server
read_only_max_client_connections	maximum read-only client connections allowed
read_only_max_server_connections	maximum read-only connections that will be opened to server

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Option	Description
read_write_consensus_timeout	how long to wait on loss of consensus before read-write connections are no longer accepted
read_only_consensus_timeout	how long to wait on loss of consensus before read-only connections are no longer accepted.

Group Proxy options

Option	Description
proxy_listen_address	The listen address for the proxy in the group.
proxy_listen_addresses	The listen addresses for the proxy in the group.
proxy_listen_port	The listen port for the proxy in the group.
proxy_max_client_conn	The maximum number of client connections for the proxy in the group.
proxy_max_server_conn	The maximum number of server connections for the proxy in the group.
proxy_server_conn_timeout	The server connection timeout for the proxy in the group.
proxy_server_conn_keepalive	The server connection keepalive for the proxy in the group.
proxy_fallback_node_groups	The fallback node groups for the proxy in the group.
proxy_fallback_node_group_timeout	The fallback node group timeout for the proxy in the group.
proxy_consensus_grace_period	The consensus grace period for the proxy in the group.
proxy_read_listen_address	The listen address for the read proxy in the group.
proxy_read_listen_addresses	The listen addresses for the read proxy in the group.
proxy_read_listen_port	The listen port for the read proxy in the group.
proxy_read_max_client_conn	The maximum number of client connections for the read proxy in the group.
proxy_read_max_server_conn	The maximum number of server connections for the read proxy in the group.
proxy_read_server_conn_keepalive	The server connection keepalive for the read proxy in the group.
proxy_read_server_conn_timeout	The server connection timeout for the read proxy in the group.
proxy_read_consensus_grace_period	The consensus grace period for the read proxy in the group.

Options

No command specific options. See Global Options.

Examples

Set the location of a group

```
pgd group dc1_subgroup set-option location London
```

output

```
Command executed successfully
```

Setting an option to a value with a space in it

```
pgd group dc1_subgroup set-option location "New York"
```

output

```
Command executed successfully
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.6.3 pgd group get-option

Synopsis

The `pgd group get-option` command is used to get group-level options in the EDB Postgres Distributed cluster.

Syntax

```
pgd group <GROUP_NAME> get-option [OPTIONS] <OPTION>
```

Where `<GROUP_NAME>` is the name of the group for which you want to get options.

And `<OPTION>` is the name of a specific group option you want to get. If you don't specify an option, the command lists all group options. The following options are available:

Group options

Option	Description
apply_delay	The delay in applying changes to the group.
check_constraints	Whether to check constraints in the group.
default_commit_scope	The default commit scope of the group.
enable_proxy_routing	Whether to enable proxy routing in the group.
enable_raft	Whether to enable Raft in the group.
enable_wal_decoder	Whether to enable the WAL decoder in the group.
location	The location of the group.
num_writers	The number of writers in the group.
route_reader_max_lag	The maximum lag for the reader in the group.
route_writer_max_lag	The maximum lag for the writer in the group.
streaming_mode	The streaming mode of the group.
route_writer_wait_flush	The wait time for flushing the writer in the group.
default_seqkind	The default sequence kind of the group.
default_replica_identity	The default replica identity of the group.
conflict_detection_method	The conflict detection method of the group.
replay_progress_frequency	The replay progress frequency of the group.
batch_inserts	Whether to enable batch inserts in the group.
analytics_storage_location	The storage location for analytics in the group.
analytics_autoadd_tables	Whether to automatically add tables to analytics in the group.

Group Connection Manager options

Option	Description
read_write_port	which port to listen on for read-write connections
read_only_port	which port to listen on for read-only connections
http_port	which http port to listen for REST API calls (for integration purposes)
use_https	whether http listener should use HTTPS, if enabled, the server certificate is used to TLS
read_write_max_client_connections	maximum read-write client connections allowed, defaults to max_connections
read_write_max_server_connections	maximum read-write connections that will be opened to server
read_only_max_client_connections	maximum read-only client connections allowed

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Option	Description
read_only_max_server_connections	maximum read-only connections that will be opened to server
read_write_consensus_timeout	how long to wait on loss of consensus before read-write connections are no longer accepted
read_only_consensus_timeout	how long to wait on loss of consensus before read-only connections are no longer accepted.

Group Proxy options

Option	Description
proxy_listen_address	The listen address for the proxy in the group.
proxy_listen_addresses	The listen addresses for the proxy in the group.
proxy_listen_port	The listen port for the proxy in the group.
proxy_max_client_conn	The maximum number of client connections for the proxy in the group.
proxy_max_server_conn	The maximum number of server connections for the proxy in the group.
proxy_server_conn_timeout	The server connection timeout for the proxy in the group.
proxy_server_conn_keepalive	The server connection keepalive for the proxy in the group.
proxy_fallback_node_groups	The fallback node groups for the proxy in the group.
proxy_fallback_node_group_timeout	The fallback node group timeout for the proxy in the group.
proxy_consensus_grace_period	The consensus grace period for the proxy in the group.
proxy_read_listen_address	The listen address for the read proxy in the group.
proxy_read_listen_addresses	The listen addresses for the read proxy in the group.
proxy_read_listen_port	The listen port for the read proxy in the group.
proxy_read_max_client_conn	The maximum number of client connections for the read proxy in the group.
proxy_read_max_server_conn	The maximum number of server connections for the read proxy in the group.
proxy_read_server_conn_keepalive	The server connection keepalive for the read proxy in the group.
proxy_read_server_conn_timeout	The server connection timeout for the read proxy in the group.
proxy_read_consensus_grace_period	The consensus grace period for the read proxy in the group.

When a value is shown followed by `(inherited)`, this means the value is not specifically set on the group, but is inherited from a parent group.

Options

No command specific options. See Global Options.

Examples

```
pgd group dc1_subgroup get-option location
```

output

```
Option Name Option Value
----------- ------------
location    London
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.6.4 pgd group set-leader

Synopsis

The `pgd group set-leader` command is used to set the write leader of a group in the EDB Postgres Distributed cluster.

This command performs a switchover operation.

Syntax

```
pgd group <GROUP_NAME> set-leader [OPTIONS] <LEADER>
```

Where `<GROUP_NAME>` is the name of the group for which you want to set the write leader and `<LEADER>` is the name of the node that you want to set as the write leader.

Options

The following table lists the options available for the `pgd group set-leader` command:

Short	Long	Description
	`--strict`	Strict method (default).
	`--timeout`	Timeout period when method is strict. (Defaults to 30s (30 seconds))
	`--fast`	Fast method.

Strict method is the default method. The strict method waits for the new leader to be in sync with the old leader before switching the leader. The fast method is immediate as it does not wait for the new leader to be in sync with the old leader before switching the leader, ignoring `route_write_max_lag`.

See also Global Options.

Examples

Setting the write leader of a group

```
pgd group dc1_subgroup set-leader kaboom
```

output

```
Command executed successfully
```

Setting the write leader when node is already the leader

```
pgd group dc1_subgroup set-leader kaboom
```

output

```
Node kaboom is already the write leader
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.7 pgd groups

The `pgd groups` commands are used to display the groups in the EDB Postgres Distributed cluster.

Subcommands

- list: List groups.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.7.1 pgd groups list

Synopsis

The `pgd groups list` command is used to display the groups in the EDB Postgres Distributed cluster.

Syntax

```
pgd groups list [OPTIONS]
```

Options

The following options are available for the `pgd groups list` command:

Short	Long	Description
-v	--verbose	Display detailed information about the groups.

See the Global Options for common global options.

Examples

List all groups

```
pgd groups list
```

output

```
Group Name    Parent Group Name Group Type Nodes
------------- ----------------- ---------- -----
democluster                     global     0
dc1_subgroup  democluster       data       3
```

List all groups with detailed information

```
pgd groups list --verbose
```

output

```
Group Name    Parent Group Name Group Type Nodes Raft Leader Write Leader Commit Scope Node Group ID
------------- ----------------- ---------- ----- ----------- ------------ ------------ -------------
democluster                     global     0     kaftan                                150732310
dc1_subgroup  democluster       data       3     kaftan      kaboom                    1302278103
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.8 pgd node

The `pgd node` commands are used to manage the nodes in the EDB Postgres Distributed cluster.

Subcommands

- show: Show node-level information.
- set-option: Set node-level options.
- get-option: Get node-level options.
- upgrade: Perform a major version upgrade of a PGD Postgres node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.8.1 pgd node get-option

Synopsis

The `pgd node get-option` command is used to get node-level options in the EDB Postgres Distributed cluster.

Syntax

```
pgd node <NODE_NAME> get-option [OPTIONS] [OPTION]
```

Where `<NODE_NAME>` is the name of the node for which you want to get options.

And `[OPTION]` is the name of a specific group option you want to get. If no option is specified, all options are displayed.

The following options are available:

Node Options

Option	Description
route_priority	Priority assigned to the node.
route_fence	Set to fence the node
route_writes	Set to allow node to route writes.
route_reads	Set to allow node to route reads.
route_dsn	DSN for connections to this node

Options

No command specific options. See Global Options.

Examples

Get all node options

```
pgd node kaboom get-option
```

output

```
Option Name    Option Value
-------------- --------------------------------------------------
route_dsn      host=kaboom port=5444 dbname=bdrdb user=pgdproxy
route_fence    false
route_priority 100
route_reads    true
route_writes   true
```

Get a specific node option

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
pgd node kaboom get-option route_priority
```

output

```
Option Name    Option Value
-------------- ------------
route_priority 100
```

Get all node options as json

```
pgd node kaboom get-option -o json
```

output

```
[
  {
    "option_name": "route_dsn",
    "option_value": "host=kaboom port=5444 dbname=bdrdb user=pgdproxy "
  },
  {
    "option_name": "route_fence",
    "option_value": "false"
  },
  {
    "option_name": "route_priority",
    "option_value": "100"
  },
  {
    "option_name": "route_reads",
    "option_value": "true"
  },
  {
    "option_name": "route_writes",
    "option_value": "true"
  }
]
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.8.2 pgd node set-option

Synopsis

The `pgd node set-option` command is used to set node-level options in the EDB Postgres Distributed cluster.

Syntax

```
pgd node <NODE_NAME> set-option [OPTIONS] <OPTION> <VALUE>
```

Where `<NODE_NAME>` is the name of the node for which you want to get options.

And `<OPTION>` is the name of a specific node option you want to get and `<VALUE>` is the value you want it set to.

The following options are available:

Node Options

Option	Description
route_priority	Priority assigned to the node.
route_fence	Set to fence the node
route_writes	Set to allow node to route writes.
route_reads	Set to allow node to route reads.
route_dsn	DSN for connections to this node

Options

No command specific options. See Global Options.

Examples

Set a specific node option

```
pgd node kaboom set-option route_priority 100
```

```
output
Command executed successfully
```

Set a specific node option with a space in the value

```
pgd node kaboom set-option route_dsn "host=kaboom port=5444 dbname=bdrdb user=pgdproxy"
```

```
output
Command executed successfully
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.8.3 pgd node show

Synopsis

The `pgd node show` command is used to display node-level information in the EDB Postgres Distributed cluster.

Syntax

```
pgd node <NODE_NAME> show [OPTIONS]
```

Where `<NODE_NAME>` is the name of the node for which you want to display information.

Options

No command specific options. See Global Options.

Examples

Show node information

```
pgd node kaboom show
```

output

```
# Summary
Node Property   Value
--------------- ------------
Node Name       kaboom
Group Name      dc1_subgroup
Node Kind       data
Join State      ACTIVE
Node Status     Up
Node ID         2710197610
Snowflake SeqID 2
Database        bdrdb

# Options
Option Name    Option Value
-------------- --------------------------------------------------
route_dsn      host=kaboom port=5444 dbname=bdrdb user=pgdproxy
route_fence    false
route_priority 100
route_reads    true
route_writes   true
```

Show node information as JSON

```
pgd node kaboom show -o json
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

output


```
[
  {
    "Summary": [
      {
        "info": "Node Name",
        "value": "kaboom"
      },
      {
        "info": "Group Name",
        "value": "dc1_subgroup"
      },
      {
        "info": "Node Kind",
        "value": "data"
      },
      {
        "info": "Join State",
        "value": "ACTIVE"
      },
      {
        "info": "Node Status",
        "value": "Up"
      },
      {
        "info": "Node ID",
        "value": "2710197610"
      },
      {
        "info": "Snowflake SeqID",
        "value": "2"
      },
      {
        "info": "Database",
        "value": "bdrdb"
      }
    ]
  },
  {
    "Options": [
      {
        "option_name": "route_dsn",
        "option_value": "host=kaboom port=5444 dbname=bdrdb user=pgdproxy "
      },
      {
        "option_name": "route_fence",
        "option_value": "false"
      },
      {
        "option_name": "route_priority",
        "option_value": "100"
      },
      {
        "option_name": "route_reads",
        "option_value": "true"
      },
      {
        "option_name": "route_writes",
        "option_value": "true"
      }
    ]
  }
]
```


Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.8.4 pgd node upgrade

Synopsis

The `pgd node upgrade` command is used to upgrade the Postgres version on a node in the EDB Postgres Distributed cluster.

> **Note**
>
> On Postgres 17 and later, `pgd node upgrade` can fail with an invalid logical replication slot error when upgrading from PGD 5 to PGD 6. PGD 5.9.4 fixes the issue by hiding BDR-managed slots from `pg_upgrade`'s slot queries, allowing the upgrade to complete successfully. Upgrade to PGD 5.9.4 before running `pgd node upgrade` on Postgres 17+.

Syntax

```
pgd node <NODE_NAME> upgrade [OPTIONS] --old-bindir <OLD_BINDIR> --new-bindir <NEW_BINDIR> --old-datadir
<OLD_DATADIR> --new-datadir <NEW_DATADIR> --database <DATABASE> --username <USER_NAME>
```

Where `<NODE_NAME>` is the name of the node which you want to upgrade and `<OLD_BINDIR>`, `<NEW_BINDIR>`, `<OLD_DATADIR>`, `<NEW_DATADIR>`, `<DATABASE>`, and `<USER_NAME>` are the old and new Postgres instance bin directories, old and new Postgres instance data directories, database name, and cluster's install user name respectively.

Options

The following table lists the options available for the `pgd node upgrade` command:

Short	Long	Default	Env	Description
-b	--old-bindir		PGBINOLD	Old Postgres instance bin directory.
-B	--new-bindir		PGBINNEW	New Postgres instance bin directory.
-d	--old-datadir		PGDATAOLD	Old Postgres instance data directory.
-D	--new-datadir		PGDATANEW	New Postgres instance data directory.
	--database		PGDATABASE	PGD database name.
-p	--old-port	5432	PGPORTOLD	Old Postgres instance port.
	--socketdir	/var/run/postgresql	PGSOCKETDIR	Directory to use for postmaster sockets during upgrade.
	~~--new-socketdir~~	~~/var/run/postgresql~~	~~PGSOCKETDIRNEW~~	~~Directory to use for postmaster sockets in the new cluster~~ Removed in 5.8.1.
	--check			Specify to only perform checks and not modify clusters.
-j	--jobs	1		Number of simultaneous processes or threads to use.
-k	--link			Use hard links instead of copying files to the new cluster.
	--old-options			Option to pass to old postgres command, multiple invocations are appended.
	--new-options			Option to pass to new postgres command, multiple invocations are appended.
-N	--no-sync			Don't wait for all files in the upgraded cluster to be written to disk.
-P	--new-port	5432	PGPORTNEW	New Postgres instance port number.
-r	--retain			Retain SQL and log files even after successful completion.
-U	--username		PGUSER	Cluster's install user name.
	--clone			Use efficient file cloning.
	--copy-by-block			Used to migrate data between clusters with different encryption settings. This option is supported for databases that use Transparent Data Encryption (TDE).
	--key-unwrap-command		PGDATAKEYUNWRAPCMD	Command to unwrap (decrypt) the data encryption key and access the files to copy. The command must be the same specified during the server initialization.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

See also Global Options.

Examples

In the following examples, "kaolin" is the name of the node to upgrade, from the Quickstart democluster.

Upgrade the Postgres version on a node

```
pgd node kaolin upgrade --old-bindir /usr/pgsql-16/bin --new-bindir /usr/pgsql-17/bin --old-datadir
/var/lib/pgsql/16/data --new-datadir /var/lib/pgsql/17/data --database bdrdb --username enterprisedb
```

Upgrade the Postgres version on a node with hard links

```
pgd node kaolin upgrade --old-bindir /usr/pgsql-16/bin --new-bindir /usr/pgsql-17/bin --old-datadir
/var/lib/pgsql/16/data --new-datadir /var/lib/pgsql/17/data --database bdrdb --username enterprisedb --link
```

Upgrade the Postgres version on a node with efficient file cloning

```
pgd node kaolin upgrade --old-bindir /usr/pgsql-16/bin --new-bindir /usr/pgsql-17/bin --old-datadir
/var/lib/pgsql/16/data --new-datadir /var/lib/pgsql/17/data --database bdrdb --username enterprisedb --clone
```

Upgrade the Postgres version on a node with a different port number

```
pgd node kaolin upgrade --old-bindir /usr/pgsql-16/bin --new-bindir /usr/pgsql-17/bin --old-datadir
/var/lib/pgsql/16/data --new-datadir /var/lib/pgsql/17/data --database bdrdb --username enterprisedb --old-port 5433
--new-port 5434
```

Upgrade the Postgres Extended version on a node with Transparent Data Encryption (TDE)

```
pgd node kaolin upgrade --database pgddb -B /usr/lib/edb-pge/16/bin --socketdir /var/run/edb-pge/ --old-bindir
/usr/lib/edb-pge/15/bin  --old-datadir /var/lib/edb-pge/15/main --new-datadir /var/lib/edb-pge/16/main --username
postgres --key-unwrap-command "openssl enc -d -aes-128-cbc -pbkdf2 -pass pass:secret -in %p" --copy-by-block
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.9 pgd nodes

The `pgd nodes` commands are used to display the nodes in the EDB Postgres Distributed cluster.

Subcommands

- list: List nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.9.1 pgd nodes list

Synopsis

The `pgd nodes list` command is used to display the nodes in the EDB Postgres Distributed cluster. By default, this shows the node name, group name, node kind, join state of the node and whether it is up or down.

Syntax

```
pgd nodes list [OPTIONS]
```

Options

The following options are available for the `pgd nodes list` command:

Short	Long	Description
	--versions	Display only version information about the nodes. For each node, the BDR version and Postgres version are shown.
-v	--verbose	Display detailed information about the nodes. For each node, this option addes the node id, Snowflake sequence id and database name.

See the Global Options for common global options.

Examples

List all nodes

```
pgd nodes list
```

output

```
Node Name Group Name   Node Kind Join State Node Status
--------- ------------ --------- ---------- -----------
kaftan    dc1_subgroup data      ACTIVE     Up
kaboom    dc1_subgroup data      ACTIVE     Up
kaolin    dc1_subgroup data      ACTIVE     Up
```

List all nodes with detailed information

```
pgd nodes list --verbose
```

output

```
Node Name Group Name   Node Kind Join State Node Status Node ID    Snowflake SeqID Database
--------- ------------ --------- ---------- ----------- ---------- --------------- --------
kaftan    dc1_subgroup data      ACTIVE     Up          3490219809 1               bdrdb
kaboom    dc1_subgroup data      ACTIVE     Up          2710197610 2               bdrdb
kaolin    dc1_subgroup data      ACTIVE     Up          2111777360 3               bdrdb
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

List all nodes version information

```
pgd nodes list --versions
```

output

```
Node Name BDR Version Postgres Version
--------- ----------- ----------------------------------
kaboom    5.7.0       15.12.0 (Debian 15.12.0-1.bullseye)
kaftan    5.7.0       15.12.0 (Debian 15.12.0-1.bullseye)
kaolin    5.7.0       15.12.0 (Debian 15.12.0-1.bullseye)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.10 pgd raft

The `pgd raft` commands are used to display the raft status in the EDB Postgres Distributed cluster.

Subcommands

- show: Show raft status for the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.10.1 pgd raft show

Synopsis

The `pgd raft show` command is used to display the Raft status in the EDB Postgres Distributed cluster. In particular, it lists all nodes in all groups, including the top level group, and their Raft status - leader or follower, number of nodes in the group with them, number of voting nodes in the group, presence of a leader, and the term number.

Syntax

```
pgd raft show [OPTIONS]
```

Options

No command specific options. See Global Options.

Examples

Show Raft status

```
pgd raft show
```

output

```
Group Name    Node Name State         Leader Name Current Term Commit Index Nodes Voting Nodes Protocol Version
------------- --------- ------------- ----------- ------------ ------------ ----- ------------ ----------------
dc1_subgroup  kaftan    RAFT_LEADER   kaftan      1            4            3     3            0
dc1_subgroup  kaboom    RAFT_FOLLOWER kaftan      1            4            3     3            0
dc1_subgroup  kaolin    RAFT_FOLLOWER kaftan      1            4            3     3            0
democluster   kaftan    RAFT_LEADER   kaftan      0            335          3     3            5007
democluster   kaboom    RAFT_FOLLOWER kaftan      0            335          3     3            5007
democluster   kaolin    RAFT_FOLLOWER kaftan      0            335          3     3            5007
```

Note that `dc1_subgroup` here is a data group with local routing, and `democluster` is the top level group with global routing.

The `Protocol Version` column shows the version of the Raft protocol in use. A version of 5011 or later means Raft PreVote is active. See Raft elections in depth. The `Commit Index` column shows the index of the last committed log entry. The `Nodes` column shows the total number of nodes in the group. The `Voting Nodes` column shows the number of nodes that participate in the Raft consensus. The `State` column shows the Raft state of the node - leader or follower. The `Leader Name` column shows the name of the leader node in the group. The `Current Term` column shows the current term number.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.11 pgd replication

The `pgd replication` commands are used to display the various aspects of replication status in the EDB Postgres Distributed cluster.

Subcommands

- show: Show replication status for the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

23.5.11.1 pgd replication show

Synopsis

The `pgd replication show` command is used to display the replication status in the EDB Postgres Distributed cluster.

By default, with no options, it produces reports on the following:

- Node Replication Progress: A matrix of the replication status between nodes.
- Replication Slots: The replication slots status for each node's slots.
- Subscriptions: The subscription status for each subscription between nodes.
- Analytics Replication: The analytics replication status for each node.

Options can be used to restrict the output to any one of the above reports. The `--verbose` option can be used to increase the detail in the default report to show the LSN and the replication lag for each node's connection to other nodes.

Syntax

```
pgd replication show [OPTIONS]
```

Options

The following options are available for the `pgd replication show` command:

Short	Long	Description
	--nodes	Display only node to node replication status in a matrix format.
	--slots	Display the replication slots for each node.
	--subscriptions	Display the subscription status for each subscription between nodes.
	--analytics	Display the analytics replication status for each node.
-v	--verbose	Display detailed information about the replication status.

See the Global Options for common global options.

--slots

This shows Shows the status of BDR replication slots. Output with the verbose flag gives details such as is slot active, replication state (disconnected, streaming, catchup), and approximate lag.

Symbol	Meaning
`*`	ok
`~`	warning (lag > 10M)
`!`	critical (lag > 100M OR slot is 'inactive' OR 'disconnected')
`x`	down / unreachable
`-`	n/a

In matrix view, sometimes byte lag is shown in parentheses. It is maxOf(WriteLag, FlushLag, ReplayLag, SentLag).

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Examples

Display the replication status in the EDB Postgres Distributed cluster

```
pgd replication show
```

output

```
# Node Replication Progress
Node   kaboom kaftan kaolin
------ ------ ------ ------
kaboom -      *      *
kaftan *      -      *
kaolin *      *      -

# Replication Slots
Group Name   Origin Node Target Node Slot Name                      Active State     Write Lag Replay Lag Sent Lag
Bytes Write Lag Bytes Replay Lag Bytes
------------ ----------- ----------- ------------------------------ ------ --------- --------- ---------- -------------
-------------- ----------------
dc1_subgroup kaboom      kaftan      bdr_bdrdb_democluster15_kaftan t      streaming 00:00:00  00:00:00   0
0              0
dc1_subgroup kaboom      kaolin      bdr_bdrdb_democluster15_kaolin t      streaming 00:00:00  00:00:00   0
0              0
dc1_subgroup kaftan      kaboom      bdr_bdrdb_democluster15_kaboom t      streaming 00:00:00  00:00:00   0
0              0
dc1_subgroup kaftan      kaolin      bdr_bdrdb_democluster15_kaolin t      streaming 00:00:00  00:00:00   0
0              0
dc1_subgroup kaolin      kaboom      bdr_bdrdb_democluster15_kaboom t      streaming 00:00:00  00:00:00   0
0              0
dc1_subgroup kaolin      kaftan      bdr_bdrdb_democluster15_kaftan t      streaming 00:00:00  00:00:00   0
0              0

# Subscriptions
Origin Node Target Node Last Applied Tx Timestamp      Last Applied Tx Age Subscription Status
----------- ----------- ------------------------------ ------------------- -------------------
kaboom      kaftan      2025-02-21 19:18:12.661520 UTC 00:00:18.616        replicating
kaboom      kaolin      2025-02-21 19:18:12.661520 UTC 00:00:18.939        replicating
kaftan      kaboom      2025-02-21 19:18:12.658069 UTC 00:00:18.787        replicating
kaftan      kaolin      2025-02-21 19:18:12.658069 UTC 00:00:18.943        replicating
kaolin      kaboom      2025-02-21 19:18:12.663201 UTC 00:00:18.782        replicating
kaolin      kaftan      2025-02-21 19:18:12.663201 UTC 00:00:18.614        replicating

# Analytics Replication Progress
Origin Node Replicating Node Replicated LSN Last Updated
----------- ---------------- -------------- ------------
```

Display only the node to node replication status in a matrix format

```
pgd replication show --nodes
```

output

```
Node   kaboom kaftan kaolin
------ ------ ------ ------
kaboom -      *      *
kaftan *      -      *
kaolin *      *      -
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24 Node types and capabilities

A PGD cluster can contain several different types of node, each with its own role. This section describes the different types of node that can be configured in a PGD cluster.

- Overview is an overview the kinds of node that can exist in PGD clusters and their associated roles.
- Witness nodes looks at the witness node, a special class of PGD node, dedicated to establishing consensus in a group.
- Logical standby nodes shows how to efficiently keep a node on standby synchronized and ready to step in as a primary in the case of failure.
- Subscriber-only nodes and groups looks at how subscriber-only nodes work with subscriber-only groups, how they boost read scalability and the different options for configuring them.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.1 An overview of PGD Node types

Data nodes

A data node in PGD is a node that runs a Postgres instance. It replicates data to all other data nodes. It also participates in the cluster-wide Raft decision-making around locking and leadership. It can be a member of one or more groups and is, by default, a member of the "top level" group that spans all data nodes in the cluster.

The data node is also the foundation on which the other three nodes are built.

Witness nodes

A witness node behaves like a data node in that it participates in the cluster-wide Raft decision-making around locking and leadership. It doesn't replicate or store data, though. The purpose of a witness node is to be available to ensure that the cluster can achieve a majority it seeks a consensus. Witness nodes has more details.

Logical standby nodes

Logical standby nodes are nodes that receive the logical data changes from another node and replicate them locally. PGD can use a logical standby node to replace the node it's replicating if that node becomes unavailable, with some caveats. See Logical standby nodes for more details.

Subscriber-only nodes

A subscriber-only node is a data node that, as the name suggests, only subscribes to changes in the cluster but doesn't replicate changes to other nodes. You can use subscriber-only nodes as read-only nodes for applications. You create subscriber-only nodes by specifying a data node is `subscriber-only` when you create the node and then adding it to a subscriber-only group. See Subscriber-only nodes and groups for more details.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.2 Witness nodes

A witness node is a lightweight node that functions as a data node but that doesn't store or replicate data. Use a witness node to allow a PGD cluster that uses Raft consensus to have an odd number of voting nodes and therefore be able to achieve a majority when making decisions.

Witness nodes within PGD groups or regions

One typical use of witness nodes is when a PGD group has two data nodes but resources aren't available for the recommended three data nodes. In this case, you can add a witness node to the PGD group to provide a third voting node to local Raft decision-making. These decisions are primarily about who will be electing a write leader for the proxies to use. With only two nodes, it's possible to have no consensus over which data node is write leader. With two data nodes and a witness, there are two candidates (the data nodes) and three voters (the data nodes and the witness). When a data node is down, then, there are still two voters that can select a write leader.

Witness node outside regions

At a higher level, you can use witness nodes when multiple PGD groups are mapped to different regions. For example, with three data nodes per region in two regions, while running normally, all six data nodes can participate in Raft decisions and obtain DDL and DML global locks. Even when a data node is down, there are sufficient data nodes to obtain a consensus. But if a network partition occurs and connectivity with the other region is lost, then now only three nodes out of six are available, which isn't enough for a consensus. To avoid this scenario, you can deploy a witness node in a third region as part of the PGD cluster. This witness node will allow a consensus to be achieved for most operational requirements of the PGD cluster while a region is unavailable.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.3 Logical standby nodes

PGD allows you to create a *logical standby node*, also known as an offload node, a read-only node, receive-only node, or logical-read replicas. A master node can have zero, one, or more logical standby nodes.

> **Note**
>
> Logical standby nodes can be used in environments where network traffic between data centers is a concern. Otherwise, having more data nodes per location is always preferred.

Logical standby nodes are nodes that are held in a state of continual recovery, constantly updating until they're required. This behavior is similar to how Postgres physical standbys operate while using logical replication for better performance. `bdr.join_node_group` has the `pause_in_standby` option to make the node stay in halfway-joined as a logical standby node. Logical standby nodes receive changes but don't send changes made locally to other nodes.

Later, if you want, use `bdr.promote_node` to move the logical standby into a full, normal send/receive node.

A logical standby is sent data by one source node, defined by the DSN in `bdr.join_node_group`. Changes from all other nodes are received from this one source node, minimizing bandwidth between multiple sites.

For high availability, if the source node dies, one logical standby can be promoted to a full node and replace the source in a failover operation similar to single-master operation. If there are multiple logical standby nodes, the other nodes can't follow the new master, so the effectiveness of this technique is limited to one logical standby.

In case a new standby is created from an existing PGD node, the needed replication slots for operation aren't synced to the new standby until at least 16 MB of LSN has elapsed since the group slot was last advanced. In extreme cases, this might require a full 16 MB before slots are synced or created on the streaming replica. If a failover or switchover occurs during this interval, the streaming standby can't be promoted to replace its PGD node, as the group slot and other dependent slots don't exist yet.

The slot sync-up process on the standby solves this by invoking a function on the upstream. This function moves the group slot in the entire EDB Postgres Distributed cluster by performing WAL switches and requesting all PGD peer nodes to replay their progress updates. This behavior causes the group slot to move ahead in a short time span. This reduces the time required by the standby for the initial slot's sync-up, allowing for faster failover to it, if required.

On PostgreSQL, it's important to ensure that the slot's sync-up completes on the standby before promoting it. You can run the following query on the standby in the target database to monitor and ensure that the slots synced up with the upstream. The promotion can go ahead when this query returns `true`.

```
SELECT true FROM pg_catalog.pg_replication_slots
WHERE
    slot_type = 'logical' AND confirmed_flush_lsn IS NOT
NULL;
```

You can also nudge the slot sync-up process in the entire PGD cluster by manually performing WAL switches and by requesting all PGD peer nodes to replay their progress updates. This activity causes the group slot to move ahead in a short time and also hastens the slot sync-up activity on the standby. You can run the following queries on any PGD peer node in the target database for this:

```
SELECT bdr.run_on_all_nodes('SELECT
pg_catalog.pg_switch_wal()');
SELECT bdr.run_on_all_nodes('SELECT
bdr.request_replay_progress_update()');
```

Use the monitoring query on the standby to check that these queries do help in faster slot sync-up on that standby.

A logical standby does allow write transactions. You can use this to great benefit, since it allows the logical standby to have additional indexes, longer retention periods for data, intermediate work tables, LISTEN/NOTIFY, temp tables, materialized views, and other differences.

Any changes made locally to logical standbys that commit before the promotion aren't sent to other nodes. All transactions that commit after promotion are sent onwards. If you perform writes to a logical standby, take care to quiesce the database before promotion.

You might make DDL changes to logical standby nodes, but they aren't replicated and they don't attempt to take global DDL locks. PGD functions that act similarly to DDL also aren't replicated. See DDL replication. If you made incompatible DDL changes to a logical standby, then the database is a *divergent node*. Promotion of a divergent node currently results in replication failing. As a result, plan to either ensure that a logical standby node is kept free of divergent changes if you intend to use it as a standby, or ensure that divergent nodes are never promoted.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.4 Subscriber-only nodes and groups

Subscriber-only nodes and groups offer a powerful way to build read scaling into your PGD cluster.

- The Overview introduces how subscriber-only nodes and groups work in PGD.
- Creating a subscriber-only group explains how to create a subscriber-only group and node.
- Joining a node to a subscriber-only group explains how to join a node to an existing subscriber-only group which has members.
- Optimizing subscriber-only groups provides details on how to configure the PGD 5.6 subscriber-only optimized topology feature which uses a group leader for more efficient replication.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.4.1 An overview of Subscriber-only nodes

Overview

While many use cases rely on accessing a database node which can handle queries and updates, there are also use cases which only require access to a node that can handle read-only database queries. Read scaling like this, by moving the read-only traffic away from active database nodes in the cluster, can improve the performance of the core cluster, whilst making database access more widely available.

Subscriber-only nodes

The basic idea of subscriber-only nodes is to provide a read-only node that you can use to offload read-only queries from the main cluster. The default topology of a PGD cluster is what's called a full mesh topology, where every node connects to every other node. This is the most robust and fault-tolerant way to connect nodes, but it can be inefficient for some use cases.

Each subscriber-only node has to be member of a subscriber-only group, which is a group of nodes that only replicate changes from the rest of the cluster. You can't have a subscriber-only node that's not part of a subscriber-only group.

> **Note**
>
> A subscriber-only node isn't considered a source when the cluster picks a node to catch up the peers of a parting node, even if the subscriber-only node is the most caught-up node available. If a subscriber-only node moves ahead of the regular data nodes and a data node then parts under load, the remaining nodes can miss transactions that only the subscriber-only node received, causing them to diverge.
>
> To prevent this divergence, set `bdr.standby_slot_names` on each data node to include the logical replication slots of your subscriber-only nodes, and set `bdr.standby_slots_min_confirmed` to at least 1. See `bdr.standby_slot_names` for details.

Subscriber-only groups

Subscriber-only groups in PGD gather together subscriber-only nodes. Each group can address different regions or different application demands.

Unlike data groups, a subscriber-only group has no raft consensus mechanism of its own and no proxies. This also means that a subscriber-only group can have as many subscriber-only nodes as your need.

Previous to PGD 5.6, the existence of a subscriber-only group didn't change the replication topology. All nodes in the subscriber-only group independently received replicated changes from all other nodes in the cluster.

Optimizing subscriber-only groups

In PGD 5.6 and later, you can optionally optimize the topology of subscriber-only groups. For clusters using proxies and raft-enabled groups for their data nodes, subscriber-only groups can use a more efficient model for receiving replicated changes.

The optimized topology option creates a group leader in each subscriber-only group, similar to a write leader in PGD Proxies. The group leader receives all the changes from the cluster and then replicates them to the other nodes in its group. See Optimizing subscriber-only groups for more information on this feature.

Subscriber-only nodes and DDL

Subscriber-only nodes can execute locally issued DDL commands but they don't replicate those changes to other nodes in the cluster and will not attempt to acquire locks on the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.4.2 Creating Subscriber-only groups and nodes

The process of creating a Subscriber-only node or nodes starts with creating a Subscriber-only group to contain the node or nodes. Perform this step on an existing fully joined node in the PGD cluster.

Creating a Subscriber-only group manually

To create a Subscriber-only group, you must specify the `node_group_type` as `subscriber-only` when creating the group. For example, here we are logged into the node "node-one" running on "host-one". It's a member of it's own data group and as for all nodes, a member of the top-level group, here called `topgroup`. Log into this node directly to create a new Subscriber-only group named `sogroup` with the following SQL command:

```
select bdr.create_node_group('sogroup', 'topgroup', false, 'subscriber-only');
```

or more explicitly with parameter names:

```
select
bdr.create_node_group(node_group_name:='sogroup',
        parent_group_name:='topgroup',
        join_node_group:=false,
        node_group_type:='subscriber-only');
```

This creates a Subscriber-only group named `sogroup` which is a child of the `topgroup` group. The false parameter for `join_node_group` indicates that the node executing this command shouldn't join to the newly created group. Automatically joining the group is the default behavior, which in this case needs to be supressed.

Adding a node to a new Subscriber-only group manually

You can now initialize a new data node and then add it to the Subscriber-only group. Create a data node and configure the bdr extension on it as you would for any other data node. If you deployed manually, see the manual install guide for instructions on how to install and deploy a data node.

You now have to create this new node as a `subscriber-only` node. To do this, log into the new node and run the following SQL command:

```
select bdr.create_node('so-node-1', 'host=so-host-1 dbname=bdrdb port=5444', 'subscriber-
only');
```

Then, log into that new node and add it to the `sogroup` group with the following SQL command:

```
 select bdr.join_node_group('host=host-one dbname=bdrdb port=5444','sogroup');
```

or more explicitly with parameter names:

```
select bdr.join_node_group(dsn:='host=host-one dbname=bdrdb port=5444',
        node_group_name:='sogroup');
```

This instructs the new node to join the `sogroup` group. As it has no knowledge of the cluster topology, it will connect to the node specified in the DSN to receive the necessary information to join the group. In this example, this happens to be the same node as we used to create the subscriber-only group, but it could be any node that's fully joined to the cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.4.3 Joining nodes to a Subscriber-only group

If you have no subscriber-only groups in your PGD cluster, you must create the groups following the process inCreating Subscriber-only groups and nodes. After you have created a subscriber-only group, you can join subscriber-only nodes to it.

Joining a node to an existing subscriber-only group

Unlike joining a node to a new subscriber-only group, joining a node to an existing subscriber-only group is a simpler process.

First create the new node as a subscriber-only node. Run the following SQL command on the new node:

```
select bdr.create_node('so-node-2', 'host=so-host-2 dbname=bdrdb port=5444', 'subscriber-
only');
```

or more explicitly with parameter names:

```
select bdr.create_node(node_name:='so-node-2',
        dsn:='host=so-host-2 dbname=bdrdb
port=5444',
        node_type:='subscriber-only');
```

This command creates a new node named `so-node-2` on host `so-host-2` and configures it as a subscriber-only node. The node won't be able to join the cluster until joins a group.

In creating a new subscriber-only group, you created a group named `sogroup` and added a subscriber-only node called `so-node-1` on a host `shost-1`. It used a node in an existing data group to facilitate that join. But you can't use this new subscriber-only node to add another subscriber-only node. You must use any active data node that's fully joined to the cluster. In the creating examples, they use `host-one` in the cluster's data group for this task. You can use the following SQL command on `shost-2` to join it to the `sogroup` group:

```
select bdr.join_node_group('host=host-one dbname=bdrdb port=5444','sogroup');
```

or more explicitly with parameter names:

```
select bdr.join_node_group(dsn:='host=host-one dbname=bdrdb port=5444',
        node_group_name:='sogroup');
```

This command instructs the new node to join the `sogroup` group. As it has no knowledge of the cluster topology, it connects to the node specified in the DSN to receive the necessary information to join the group. That node must be fully joined to the cluster as it acts as the source of the request for the new node to join the group.

Once the new node has joined the group, it starts by first synchronizing and then begins to receive replication changes from the other nodes in the cluster.

> **Note**
>
> Unless, the group is using the optimized topology, in which case it replicates changes from a subscriber-only group leader in the subscriber-only group it has joined.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

24.4.4 Optimizing subscriber-only groups

With PGD 5.6 and later, it's possible to optimize the topology of subscriber-only groups.

In this optimized topology, a small number of fully active nodes—the write leaders of the data groups—replicate changes to the group leaders of subscriber-only groups. These group leaders then replicate changes to the other members of its subscriber-only group.

Requirements for the optimized topology

You can't enable this model if a cluster has any of the following:

- Data nodes that are directly members of the top-level group
- No data-node subgroups
- No data-node subgroups with proxy routing enabled

If any of these are the case, the nodes in subscriber-only groups revert to the full mesh topology.

To get the benefit of the new SO group and node replication, you must have your data nodes in subgroups, with proxy routing enabled on the subgroups.

How the optimized topology works

For clusters using groups for their data nodes, subscriber-only groups can use a more efficient model. This model uses subscriber-only group leaders, similar to write leaders in PGD proxies.

Each subscriber-only group uses that group leader to replicate changes to other subscriber-only nodes in its group. The group leader acts as a replication proxy for incoming changes.

The write leader nodes in data groups replicate changes to the group leaders of the subscriber-only groups. Other nodes in the data groups only replicate with nodes in their data group and with data nodes in other data groups. They do not directly replicate their changes to the subscriber-only groups.

Subscriber-only group leaders

With PGD 5.6 and later, each subscriber-only group gets assigned a group leader of its own. This is because subscriber-only groups don't have a group Raft consensus mechanism of their own. Instead, the cluster's top-level group uses its Raft consensus mechanism to handle selecting each subscriber-only group's group leader. This group leader selection is on by default in PGD 5.6, regardless of the topology optimization settings.

Group leaders in subscriber-only groups are regularly tested for connectivity and, if unavailable, the voting nodes of top-level group select a new subscriber-only node from the subscriber-only group to become group leader. The new group leader is then selected.

With optimized technology turned off, this election has no effect on the replication topology. Without the optimized topology, all data nodes replicate changes to all other nodes in the cluster.

Group leaders in the optimized topology

With the optimized topology enabled, only the subscriber-only group's group leader receives changes from other data groups' write leaders in the cluster. The group leader takes on the responsibility of replicating those changes to the other nodes in the subscriber-only group.

The other voting nodes choose the group leader from a subscriber-only group's nodes. Once the group leader is selected, the whole cluster becomes aware of the change, and any data group's write leaders then replicate data only to this newly selected group leader node. Other data nodes in the data groups don't replicate data to the subscriber-only group's nodes.

This approach avoids the explosion of active connections that can happen when there are large numbers of SO nodes and reduces the amount of replication traffic.

The subscriber-only node and group form the building block for PGD tree topologies.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Enabling the optimized model

By default, PGD 5.6 forces the full mesh topology. This means the optimization described here is off. To enable the optimized topology, you must have your data nodes in subgroups, with proxy routing enabled on the subgroups. You can then set the GUC `bdr.force_full_mesh` to `off` to allow the optimization to be activated.

> **Note**
>
> This GUC needs to be set in the `postgresql.conf` file on each data node and each node restarted for the change to take effect.

If any requirements of the optimized topology aren't met, the nodes in a subscriber-only group revert to the full mesh topology. When this happens, you'll find in the logs of the nodes in the cluster messages why the optimization wasn't possible, such as:

When a data node is part of the top-level node group:

```
node: <nodename> is part of top-level nodegroup: <toplevelgroupname>: changing to full mesh".
```

When a data group doesn't have proxy routing enabled:

```
node: <nodename> is in nodegroup: <nodegroupname> that does not have proxy routing: changing to full mesh.
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25 Commit Scopes

EDB Postgres Distributed (PGD) offers a range of synchronous modes to complement its default asynchronous replication. You use commit scopes to configure these synchronous modes. Commit scopes are rules that define how PGD handles synchronous operations and when the system considers a transaction committed.

Introducing

- Overview introduces the concepts and some of the essential terminology that's used when discussing synchronous commits.
- Durability terminology lists terms used around PGD's durability options, including how to refer to nodes in replication.
- Commit scopes is a more in-depth look at the structure of commit scopes and how to define them for your needs.
- Origin groups introduces the notion of an origin group, and how to leverage these when defining commit scopes rules.
- Commit scope rules looks at the syntax of and how to formulate a commit scope rule.
- Comparing durability options compares how commit scope options behave with regard to durability.
- Degrading commit scope rules shows how to set up a commit scope rule that can gracefully degrade to a lower setting in case of timeouts with a stricter setting.

Commit scope kinds

- Synchronous Commit is a commit scope mechanism that works in a similar fashion to legacy synchronous replication, but from within the commit scope framework.
- Group Commit focuses on the Group Commit option, where you can define a transaction as done when a group of nodes agrees it's done.
- CAMO focuses on the Commit At Most Once option, in which applications take responsibility for verifying that a transaction has been committed before retrying. This ensures that their commits only happen at most once.
- Lag Control looks at the commit scope mechanism which dynamically throttle nodes according to the slowest node and regulates how far out of sync nodes may go when a database node goes out of service.

Working with commit scopes

- Administering addresses how to manage a PGD cluster with Group Commit in use.
- Limitations lists the various combinations of durability options that aren't currently supported or aren't possible. Refer to this before deciding on a durability strategy.
- Legacy synchronous replication shows how you can still access traditional Postgres synchronous operations under PGD.
- Internal timing of operations compares legacy replication with PGD's async and synchronous operations, especially the difference in the order by which transactions are flushed to disk or made visible.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.1 Overview of durability options

Overview

EDB Postgres Distributed (PGD) allows you to choose from several replication configurations based on your durability, consistency, availability, and performance needs using *commit scopes*.

In its basic configuration, PGD uses asynchronous replication. However, commit scopes can change both the default and the per-transaction behavior.

It's also possible to configure the legacy Postgres synchronous replication using standard `synchronous_standby_names` in the same way as the built-in physical or logical replication. However, commit scopes provide much more flexibility and control over the replication behavior.

The different synchronization settings affect three properties of interest to applications that are related but can all be implemented individually:

- Durability: Writing to multiple nodes increases crash resilience and allows you to recover the data after a crash and restart.
- Visibility: With the commit confirmation to the client, the database guarantees immediate visibility of the committed transaction on some sets of nodes.
- Conflict handling: Conflicts can be handled optimistically postcommit, with conflicts resolved when the transaction is replicated based on commit timestamps. Or, they can be handled pessimistically precommit. The client can rely on the transaction to eventually be applied on all nodes without further conflicts or get an abort, directly informing the client of an error.

Commit scopes allow four kinds of controlling durability of the transaction:

- Synchronous Commit: This kind of commit scope allows for a behavior where the origin node awaits a majority of nodes to confirm and behaves more like a native Postgres synchronous commit.
- Group Commit: This kind of commit scope controls which and how many nodes have to reach a consensus before the transaction is considered to be committable and at what stage of replication it can be considered committed. This option also allows you to control the visibility ordering of the transaction.
- CAMO: This kind of commit scope is a variant of Group Commit, in which the client takes on the responsibility for verifying that a transaction was committed before retrying.
- Lag Control: This kind of commit scope controls how far behind nodes can be in terms of replication before allowing commit to proceed.

Synchronous commit, group commit, and CAMO each support degrading commit scope rules, for even further control of durability.

> **Legacy synchronization availability**
>
> For backward compatibility, PGD still supports configuring synchronous replication with `synchronous_commit` and `synchronous_standby_names`. See Legacy synchronous replication for more on this option. We recommend that you use PGD Synchronous Commit instead.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.2 Durability terminology

Durability terminology

This page covers terms and definitions directly related to PGD's durability options. For other terms, seeTerminology.

Nodes

PGD nodes take different roles during the replication of a transaction. These are implicitly assigned per transaction and are unrelated even for concurrent transactions.

- The *origin* is the node that receives the transaction from the client or application. It's the node processing the transaction first, initiating replication to other PGD nodes and responding back to the client with a confirmation or an error.
- The *origin node group* is a PGD group which includes the origin.
- A *partner* node is a PGD node expected to confirm transactions according to Group Commit requirements.
- A *commit group* is the group of all PGD nodes involved in the commit, that is, the origin and all of its partner nodes, which can be just a few or all peer nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.3 Commit scopes

Commit scopes give applications granular control about durability and consistency of EDB Postgres Distributed.

A commit scope is a set of rules that describes the behavior of the system as transactions are committed. The actual behavior depends on which a kind of commit scope a commit scope's rule uses Synchronous Commit, Group Commit, Commit At Most Once, Lag Control, or combination of these.

While most commit scope kinds control the processing of the transaction, Lag Control is the exception as it dynamically regulates the performance of the system in response to replication operations being slow or queued up. It is typically used, though, in combination with other commit scope kinds

Commit scope structure

Every commit scope has a name (a `commit_scope_name`).

Each commit scope has one or more rules.

Each rule within the commit scope has an `origin_node_group` which together uniquely identify the commit scope rule.

The `origin_node_group` is a PGD group and it defines the nodes which will apply this rule when they are the originators of a transaction.

Finally there is the rule which defines what kind of commit scope or combination of commit scope kinds should be applied to those transactions.

So if a commit scope has a rule that reads:

```
origin_node_group := 'example_bdr_group',
rule := 'MAJORITY (example_bdr_group) GROUP COMMIT',
```

Then, the rule is applied when any node in the `example_bdr_group` issues a transaction.

The rule itself specifies how many nodes of a specified group will need to confirm the change - `MAJORITY (example_bdr_group)` - followed by the commit scope kind itself - `GROUP COMMIT`. This translates to requiring that any two nodes in `example_bdr_group` must confirm the change before the change can be considered as comitted.

How a commit scope is selected

When any change takes place, PGD looks up which commit scope is should be used for the transaction or node.

If a transaction specifies a commit scope, that scope will be used.

If not specified, the system will search for a default commit scope. Default commit scopes are a group level setting. The system consults the group tree. Starting at the bottom of the group tree with the node's group and working up, it searches for any group which has a default_commit_scope setting defined. This commit scope will then be used.

If no default_commit_scope is found then the node's GUC, bdr.commit_scope is used. And if that isn't set or is set to `local` then no commit scope applies and PGD's async replication is used.

A rule's `origin_node_group` is matched differently depending on how the commit scope is activated:

- As a default commit scope set via a group's `default_commit_scope`, PGD ascends the group tree from the node's group, so a rule defined on a parent or top-level group applies to subgroup nodes.
- Activated explicitly via `SET [LOCAL] bdr.commit_scope`, the rule is matched only against the node's own group. If no rule has that exact group as its `origin_node_group`, no commit scope applies and the transaction silently falls back to async replication.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Warning**
>
> Setting `bdr.commit_scope` to a scope whose rules are all defined on a parent group does not raise an error, but the scope is not applied and the commit uses async replication. To use such a scope with `SET LOCAL bdr.commit_scope` on a subgroup node, create the rule with that subgroup as `origin_node_group`.

Creating a Commit Scope

Use `bdr.create_commit_scope` to add our example rule to a commit scope. For example:

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'example_bdr_group',
    rule := 'MAJORITY (example_bdr_group) GROUP
COMMIT',
    wait_for_ready :=
true
);
```

This will add the rule `MAJORITY (example_bdr_group) GROUP COMMIT` for any transaction originating from the `example_bdr_group` to a scope called `example_scope`.

If no rules previously existed in `example_scope`, then adding this rule would make the scope exist.

When a rule is added, the origin_node_group must already exist. If it does not, the whole add operation will be discarded with an error.

The rule will then be evaluated. If the rule mentions groups that don't exist or the settings on the group are incompatible with other configuration setting on the group's nodes, a warning will be emitted, but the rule will be added.

Once the rule is added, the commit scope will be available for use.

The `wait_for_ready` controls whether the `bdr.create_commit_scope()` call blocks until the rule has been added to the relevant nodes. The setting defaults to true and can be omitted.

Using a commit scope

To use our example scope, we can set `bdr.commit_scope` within a transaction

```
BEGIN;
SET LOCAL bdr.commit_scope =
'example_scope';
...
COMMIT;
```

You must set the commit scope before the transaction writes any data.

You can set a commit scope as a default for a group or subgroup using `bdr.alter_node_group_option`:

```
SELECT bdr.alter_node_group_option(
  node_group_name := 'example_bdr_group',
  config_key := 'default_commit_scope',
  config_value := 'example_scope'
);
```

To completely clear the default for a group or subgroup, set the `default_commit_scope` value to `local`:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
SELECT bdr.alter_node_group_option(
  node_group_name := 'example_bdr_group',
  config_key := 'default_commit_scope',
  config_value := 'local'
);
```

You can also make this change using PGD CLI:

```
pgd group example-bdr-group set-option default_commit_scope "example_scope"
```

And you can clear the default using PGD CLI by setting the value to `local`:

```
pgd group example-bdr-group set-option default_commit_scope "local"
```

Finally, you can set the default commit_scope for a node using:

```
SET bdr.commit_scope =
'example_scope';
```

Set `bdr.commit_scope` to `local` to use the PGD default async replication.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.4 Origin groups

Rules for commit scopes can depend on the node the transaction is committed on, that is, the node that acts as the origin for the transaction. The bottom group of the group tree to which that node belongs is the transaction's *origin group*. To make this transparent for the application, PGD allows a commit scope to define different rules depending on the transaction's origin group.

For example, consider an EDB Postgres Distributed cluster with nodes spread across two data centers: a left (`left_dc`) and a right one (`right_dc`). Assume the top-level PGD node group is called `top_group` . You can use the following commands to set up subgroups and create a commit scope requiring all nodes in the local data center to confirm the transaction but only one node from the remote one:

```
-- create sub-
groups
SELECT bdr.create_node_group(
    node_group_name := 'left_dc',
    parent_group_name := 'top_group',
    join_node_group := false
);
SELECT bdr.create_node_group(
    node_group_name := 'right_dc',
    parent_group_name := 'top_group',
    join_node_group := false
);

-- create a commit scope with individual
rules
-- for each sub-
group
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'left_dc',
    rule := 'ALL (left_dc) GROUP COMMIT (commit_decision=raft) AND ANY 1 (right_dc) GROUP
COMMIT',
    wait_for_ready :=
true
);
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'right_dc',
    rule := 'ANY 1 (left_dc) GROUP COMMIT AND ALL (right_dc) GROUP COMMIT
(commit_decision=raft)',
    wait_for_ready :=
true
);
```

Now, using the `example_scope` on any node that's part of `left_dc` uses the first scope. Using the same scope on a node that's part of `right_dc` uses the second scope. By combining the `left_dc` and `right_dc` origin rules under one commit scope name, an application can simply use `example_scope` on either data center and get the appropriate behavior for that data center.

Each group can also have a default commit scope specified using the `bdr.alter_node_group_option` admin interface.

Making the above scopes the default ones for all transactions originating on nodes in those groups looks like this:

```
SELECT bdr.alter_node_group_option(
  node_group_name := 'left_dc',
  config_key := 'default_commit_scope',
  config_value := 'example_scope'
);
SELECT bdr.alter_node_group_option(
  node_group_name := 'right_dc',
  config_key := 'default_commit_scope',
  config_value := 'example_scope'
);
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

ORIGIN_GROUP

You can also refer to the origin group of a transaction dynamically when creating a commit scope rule by using `ORIGIN_GROUP`.

This can make certain commit scopes rules like those above in `example_scope`, even easier to specify in that you can simply specify one rule instead of two.

For example, again suppose that for transactions originating from nodes in `right_dc` you want all nodes in `right_dc` to confirm and any 1 from `left_dc` to confirm before the transaction is committed. Also, again suppose that for transactions originating in `left_dc` you want all nodes in `left_dc` and any 1 in `right_dc` to confirm before the transaction is commited. Above we used these two rules for this when defining `example_scope`:

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'left_dc',
    rule := 'ALL (left_dc) GROUP COMMIT (commit_decision=raft) AND ANY 1 (right_dc) GROUP
COMMIT',
    wait_for_ready :=
true
);
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'right_dc',
    rule := 'ANY 1 (left_dc) GROUP COMMIT AND ALL (right_dc) GROUP COMMIT
(commit_decision=raft)',
    wait_for_ready :=
true
);
```

However, with `ORIGIN_GROUP`, just adding and using the following single-rule commit scope, `example_scope_2`, will have the same effect as the two individual rules we used above in `example_scope`:

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope_2',
    origin_node_group := 'top_group',
    rule := 'ALL ORIGIN_GROUP GROUP COMMIT (commit_decision=raft) AND ANY 1 NOT ORIGIN_GROUP GROUP
COMMIT';
    wait_for_ready :=
true
);
```

Under `example_scope_2`, when a transaction originates from `left_dc`, `ORIGIN_GROUP` maps to `left_dc` and `NOT ORIGIN_GROUP` maps to `right_dc`. Likewise, when a transaction originates from `right_dc`, `ORIGIN_GROUP` maps to `right_dc` and `NOT ORIGIN_GROUP` maps to `left_dc`. So by only specifying one rule, you get the effect of two.

Note that if you added more subgroups, for instance a third child of `top_group`, `middle_dc`, then according to `example_scope_2` above, for transactions originating from `left_dc`, all the nodes in `left_dc` must plus any 1 in `right_dc` and any 1 in `middle_dc` must confirm before the transaction is committed. Of course then for transactions originating in `right_dc` all the nodes in `right_dc` plus any 1 node in `left_dc` and any 1 node in `middle_dc` must confirm before the transaction is committed. Lastly, because `middle_dc` is a child of `top_group`, `example_scope_2` also means that for transactions originating in `middle_dc`, all the nodes in `middle_dc` plus any 1 node in `left_dc` and any 1 node in `right_dc` must confirm before the transaction is committed.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.5 Commit scope rules

Commit scope rules are at the core of the commit scope mechanism. They define what the commit scope enforces.

Commit scope rules are composed of one or more operations that work in combination. Use an AND between rules.

Each operation is made up of two or three parts: the commit scope group, an optional confirmation level, and the kind of commit scope, which can have its own parameters.

```
commit_scope_group [ confirmation_level ] commit_scope_kind
```

A full formal syntax diagram is available in the Commit scopes reference.

A typical commit scope rule, such as `ANY 2 (group) GROUP COMMIT`, can be broken down into its components. `ANY 2 (group)` is the commit scope group specifying, for the rule, which nodes need to respond and confirm they processed the transaction. In this example, any two nodes from the named group must confirm.

No confirmation level is specified, which means that the default is used. You can think of the rule in full, then, as:

```
ANY 2 (group) ON visible GROUP COMMIT
```

The `visible` setting means the nodes can confirm once all the transaction's changes are flushed to disk and visible to other transactions.

The last part of this operation is the commit scope kind, which in this example is `GROUP COMMIT`. `GROUP COMMIT` is a synchronous two-phase commit that's confirmed when any two nodes in the named group confirm they've flushed the transactions changes and made them visible.

The commit scope group

There are three kinds of commit scope groups: `ANY`, `ALL`, and `MAJORITY`. They're all followed by a list of one or more groups in parentheses. This list of groups combines to make a pool of nodes this operation applies to. This list can be preceded by `NOT`, which inverts the pool to be all other groups that aren't in the list. Witness nodes aren't eligible to be included in this pool, as they don't replicate data.

- `ANY n` is followed by an integer value, `n`. It translates to any `n` nodes in the listed groups' nodes.
- `ALL` is followed by the groups and translates to all nodes in the listed groups' nodes.
- `MAJORITY` is followed by the groups and translates to requiring a half, plus one, of the listed groups' nodes to confirm, to give a majority.
- `ANY n NOT` is followed by an integer value, `n`. It translates to any `n` nodes that aren't in the listed groups' nodes.
- `ALL NOT` is followed by the groups and translates to all nodes that aren't in the listed groups' nodes.
- `MAJORITY NOT` is followed by the groups and translates to requiring a half, plus one, of the nodes that aren't in the listed groups' nodes to confirm, to give a majority.

The confirmation level

PGD nodes can send confirmations for a transaction at different times. In increasing levels of protection, from the perspective of the confirming node, these are:

- `received` — A remote PGD node confirms the transaction immediately after receiving it, prior to starting the local application.
- `replicated` — Confirms after applying changes of the transaction but before flushing them to disk.
- `durable` — Confirms the transaction after all of its changes are flushed to disk.
- `visible` (default) — Confirms the transaction after all of its changes are flushed to disk and it's visible to concurrent transactions.

In rules for commit scopes, you can append these confirmation levels to the node group definition in parentheses with `ON`, as follows:

- `ANY 2 (right_dc) ON replicated`
- `ALL (left_dc) ON visible` (default)
- `ALL (left_dc) ON received AND ANY 1 (right_dc) ON durable`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Note**
>
> If you're familiar with PostgreSQL's `synchronous_standby_names` feature, be aware that while the grammar for `synchronous_standby_names` and commit scopes can look similar, there's a subtle difference. The former doesn't account for the origin node, but the latter does. For example, `synchronous_standby_names = 'ANY 1 (..)'` is equivalent to a commit scope of `ANY 2 (...)`. This difference makes reasoning about majority easier and reflects that the origin node also contributes to the durability and visibility of the transaction.

The commit scope kinds

Currently, there are four commit scope kinds. The following is a summary, with links to more details.

`SYNCHRONOUS COMMIT`

Synchronous Commit is a commit scope option that's designed to behave like the native Postgres `synchronous_commit` option, but is usable from within the commit scope environment. Unlike `GROUP COMMIT`, it's a synchronous non-two-phase commit operation. Like `GROUP COMMIT`, it supports an optional `DEGRADE ON` clause. The commit scope group that comes before this option controls the groups and confirmation requirements the `SYNCHRONOUS COMMIT` uses.

For more details, see `SYNCHRONOUS COMMIT`.

`GROUP COMMIT`

Group Commit is a synchronous, two-phase commit that's confirmed according to the requirements of the commit scope group. `GROUP COMMIT` has options that control:

- Whether to track transactions over interruptions (Boolean, defaults to off)
- How to resolve conflicts (`async` or `eager`, defaults to `async`)
- How to obtain a consensus (`group`, `partner` or `raft`, defaults to `group`)

For more details, see `GROUP COMMIT`.

`CAMO`

Commit At Most Once, or CAMO, allows the client/application, origin node, and partner node to ensure that a transaction is committed to the database at most once. Because the client is involved in the process, an application will require modifications to participate in the CAMO process.

For more details, see `CAMO`.

`LAG CONTROL`

With Lag Control, when the system's replication performance exceeds specified limits, a commit delay can be automatically injected into client interaction with the database, providing a back pressure on clients. Lag Control has parameters to set the maximum commit delay that can be exerted. It also has limits in terms of time to process or queue size that trigger increases in that commit delay.

For more details, see `LAG CONTROL`.

Combining rules

Commit scope rules are composed of one or more operations that work in combination. Use an AND to form a single rule. For example:

```
MAJORITY (Region_A) SYNCHRONOUS COMMIT AND ANY 1 (Region_A) LAG CONTROL (MAX_LAG_SIZE = '50MB')
```

The first operation sets up a synchronous commit against a majority of `Region_A`. The second operation adds lag control that starts pushing the commit delay up when any one of the nodes in `Region_A` has more than 50MB of lag. This combination of operations allows the lag control to operate when any node is lagging.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.6 Comparing durability options

Comparison

Most options for synchronous replication available to PGD allow for different levels of synchronization, offering different tradeoffs between performance and protection against node or network outages.

The following list of confirmation levels explains what a user should expect to see when that confirmation level is in effect and how that can affect performance, durability, and consistency.

ON RECEIVED

Expect: The peer node has received the changes. Nothing has been updated in the peer nodes tuple store or written to storage.

Confirmation on reception means that the peer operating normally can eventually, apply the transaction without requiring any further communication, even in the face of a full or partial network outage. A crash of a peer node might still require retransmission of the transaction, as this confirmation doesn't involve persistent storage.

For: The origin node in the transaction only has to wait for the reception of the transaction. Where transactions are large, it may improve the TPS performance of the system.

Against: An increased likelihood of stale reads. Overall, ON RECEIVED is not robust because data can be lost when either a Postgres server or operating system crash occurs.

ON REPLICATED

Expect: The peer node has received the changes and applied them to the tuple store. The changes have been written to storage, but the storage has not been flushed to disk.

Confirmation on replication means the peer has received and applied the changes. Those changes have been written to storage, but will still be in operating system caches and buffers. The system has yet to persist them to disk.

For: This checkpoint is further down the timeline of transaction processing. The origin node only waits for the transaction to be applied, but not persisted.

Against: There's a slightly lower chance of stale reads over ON RECEIVED. Also, with ON REPLICATED data can survive a Postgres crash but will still not survive an operating system crash.

ON DURABLE

Expect: The peer node has received the changes, applied them to the tuple store and persisted the changes to storage. It has yet to make the changes available to other sessions.

Durable confirmation means that the transaction has been written and flushed to the peer node's storage. This protects against loss of data after a crash and recovery of the peer node. But, if a session commits a transaction with an ON DURABLE rule before disconnecting and reconnecting, the transaction's changes are not guaranteed to be visible to the reconnected session.

When used with the Group Commit commit scope kind, this also means the changes are visible.

For: More robust, able to recover without retransmission in the event of a crash.

Against: Doesn't guarantee consistency in cases of failover.

ON VISIBLE

Expect: The peer node has received and applied the changes, persisted and flushed those changes to storage.

Confirmation of visibility means that the transaction was fully applied remotely. If a session commits a transaction with an ON VISIBLE rule before disconnecting and reconnecting, the transaction's changes are guaranteed to be visible to the reconnected session.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

For: Robust and consistent.

Against: Lower performance.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.7 Degrading commit scope rules

`SYNCHRONOUS COMMIT`, `GROUP COMMIT`, and `CAMO` each have the optional capability of degrading the requirements for transactions when particular performance thresholds are crossed.

When a node is applying a transaction and that transaction times out, it can be useful to trigger a process of degrading the requirements of the transaction to be completed, rather than just rolling back.

`DEGRADE ON` offers a route for gracefully degrading the commit scope rule of a transaction. At its simplest, `DEGRADE ON` takes a timeout and a second set of commit scope operations that the commit scope can gracefully degrade to.

For instance, after 20ms or 30ms timeout, the requirements for satisfying a commit scope could degrade from `ALL (node_group_name) GROUP COMMIT` to `MAJORITY (node_group_name) GROUP COMMIT`, making the transactions apply more steadily.

You can also require that the write leader be the originator of a transaction in order for the degrade clause to be triggered. This can be helpful in "split brain scenarios" where you have, say, 2 data nodes and a witness node. Supposing there is a network split between the two data nodes and you have connections to both of the data nodes, only one of them will be allowed to degrade, because only one of them will be elected leader through the raft election with the witness node.

Behavior

There are two parts to how the generalized `DEGRADE` clause behaves as it is applied to transactions.

Once during the commit, while the commit being processed is waiting for responses that satisfy the commit scope rule, PGD checks for a timeout and, if the timeout has expired, the commit being processed is reconfigured to wait for the commit scope rule in the `DEGRADE` clause. In fact, by this point, the commit scope rule in the `DEGRADE` clause might already be satisfied.

This mechanism alone is insufficient for the intended behavior, as this alone would mean that every transaction—even those that were certain to degrade due to connectivity issues—must wait for the timeout to expire before degraded mode kicks in, which would severely affect performance in such degrading-cluster scenarios.

To avoid this, the PGD manager process also periodically (every 5s) checks the connectivity and apply rate (the one in bdr.node_replication_rates) and if there are commit scopes that would degrade at that point based on the current state of replication, they will be automatically degraded—such that any transaction using that commit scope when processing after that uses the degraded rule instead of waiting for timeout—until the manager process detects that replication is moving swiftly enough again.

SYNCHRONOUS COMMIT and GROUP COMMIT

Both `SYNCHRONOUS COMMIT` and `GROUP COMMIT` have `timeout` and `require_write_lead` parameters, with defaults of `0` and `false` respectively. You should probably always set the `timeout`, as the default of `0` causes an instant degrade. You can also require that the write leader be the originator of the transaction in order to switch to degraded mode (again, default is `false`).

Both `SYNCHRONOUS COMMIT` and `GROUP COMMIT` also have options regarding which rule you can degrade to—which depends on which rule you are degrading from.

First of all, you can degrade to asynchronous operation:

```
ALL (left_dc) SYNCHRONOUS COMMIT DEGRADE ON (timeout=20s) TO
ASYNC
```

You can also degrade to a less restrictive commit group with the same commit scope kind (again as long as the kind is either `SYNCHRONOUS_COMMIT` or `GROUP COMMIT`). For instance, you can degrade as follows:

```
ALL (left_dc) SYNCHRONOUS COMMIT DEGRADE ON (timeout=20s) TO MAJORITY (left_dc) SYNCHRONOUS
COMMIT
```

or as follows:

```
ANY 3 (left_dc) SYNCHRONOUS COMMIT DEGRADE ON (timeout=20s) TO ANY 2 (left_dc) SYNCHRONOUS
COMMIT
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

But you cannot degrade from `SYNCHRONOUS COMMIT` to `GROUP COMMIT` or the other way around.

CAMO

While CAMO supports both the same `timeout` and `require_write_lead` parameters (with the same defaults, `0` and `false` respectively), the options are simpler in that you can only degrade to asynchronous operation.

```
ALL (left_dc) CAMO DEGRADE ON (timeout=20ms, require_write_lead=true) TO
ASYNC
```

Again, you should set the `timeout` parameter, as the default is `0`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.8 Synchronous Commit

Commit scope kind: `SYNCHRONOUS COMMIT`

Overview

PGD's `SYNCHRONOUS COMMIT` is a commit scope kind that works in a way that's more like PostgreSQL's `synchronous_commit` option in its underlying operation. Unlike the PostgreSQL option, though, it's configured as a commit scope and is easier to configure and interact with in PGD.

Unlike other commit scope kinds, such as `GROUP COMMIT` and `CAMO`, the transactions in a `SYNCHRONOUS COMMIT` operation aren't transformed into a two-phase commit (2PC) transaction. They work more like a Postgres `synchronous_commit`.

Example

In this example, when this commit scope is in use, any node in the `left_dc` group uses `SYNCHRONOUS COMMIT` to replicate changes to the other nodes in the `left_dc` group. It looks for a majority of nodes in the `left_dc` group to confirm that they committed the transaction.

```
SELECT bdr.create_commit_scope(
    commit_scope_name := 'example_sc_scope',
    origin_node_group := 'left_dc',
    rule := 'MAJORITY (left_dc) SYNCHRONOUS COMMIT',
    wait_for_ready := true
);
```

Configuration

`SYNCHRONOUS COMMIT` supports the optional `DEGRADE ON` clause. See the `SYNCHRONOUS COMMIT` commit scope reference for specific configuration parameters or see this section regarding Degrade on options.

Confirmation

Confirmation level	PGD Synchronous Commit handling
`received`	A remote PGD node confirms the transaction once it's been fully received and is in the in-memory write queue.
`replicated`	Same behavior as `received`.
`durable`	Confirms the transaction after all of its changes are flushed to disk. Analogous to `synchronous_commit = on` in legacy synchronous replication.
`visible` (default)	Confirms the transaction after all of its changes are flushed to disk and it's visible to concurrent transactions. Analogous to `synchronous_commit = remote_apply` in legacy synchronous replication.

Details

Currently `SYNCHRONOUS COMMIT` doesn't use the confirmation levels of the commit scope rule syntax.

In commit scope rules, the original keyword `SYNCHRONOUS_COMMIT` is now aliased to `SYNCHRONOUS COMMIT`. The use of a space instead of an underscore helps distinguish it from Postgres's native `SYNCHRONOUS_COMMIT`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.9 Group Commit

Commit scope kind: `GROUP COMMIT`

Overview

The goal of Group Commit is to protect against data loss in case of single node failures or temporary outages. You achieve this by requiring more than one PGD node to successfully confirm a transaction at COMMIT time. Confirmation can be sent at a number of points in the transaction processing but defaults to "visible" when the transaction has been flushed to disk and is visible to all other transactions.

> **Warning**
>
> Group commit is currently offered as an experimental feature intended for preview and evaluation purposes. While it provides valuable capabilities, it has known limitations and challenges that make it unsuitable for production environments. We recommend that customers avoid using this feature in production scenarios until these limitations are addressed in future releases.

Example

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'left_dc',
    rule := 'ALL (left_dc) GROUP COMMIT(commit_decision=raft) AND ANY 1 (right_dc) GROUP
COMMIT',
    wait_for_ready :=
true
);
```

This example creates a commit scope where all the nodes in the `left_dc` group and any one of the nodes in the `right_dc` group must receive and successfully confirm a committed transaction.

Requirements

During normal operation, Group Commit is transparent to the application. Transactions that were in progress during failover need the reconciliation phase triggered or consolidated by either the application or a proxy in between. This activity currently happens only when either the origin node recovers or when it's parted from the cluster. This behavior is the same as with Postgres legacy built-in synchronous replication.

Transactions committed with Group Commit use two-phase commit underneath. Therefore, configure `max_prepared_transactions` high enough to handle all such transactions originating per node.

Limitations

See the Group Commit section of Limitations.

Configuration

`GROUP_COMMIT` supports optional `GROUP COMMIT` parameters, as well as `ABORT ON` and `DEGRADE ON` clauses. For a full description of configuration parameters, see the GROUP_COMMIT commit scope reference or for more regarding `DEGRADE ON` options in general, see the Degrade options section.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Confirmation

Confirmation level	Group Commit handling
`received`	A remote PGD node confirms the transaction immediately after receiving it, prior to starting the local application.
`replicated`	Confirms after applying changes of the transaction but before flushing them to disk.
`durable`	Confirms the transaction after all of its changes are flushed to disk.
`visible` (default)	Confirms the transaction after all of its changes are flushed to disk and it's visible to concurrent transactions.

Behavior

The behavior of Group Commit depends on the configuration applied by the commit scope.

Commit decisions

You can configure Group Commit to decide commits in three different ways: `group`, `partner`, and `raft`.

The `group` decision is the default. It specifies that the commit is confirmed by the origin node upon receiving as many confirmations as required by the commit scope group. The difference is that the commit decision is made based on PREPARE replication while the durability checks COMMIT (PREPARED) replication.

The `partner` decision is what Commit At Most Once (CAMO) uses. This approach works only when there are two data nodes in the node group. These two nodes are partners of each other, and the replica rather than origin decides whether to commit something. This approach requires application changes to use the CAMO transaction protocol to work correctly, as the application is in some way part of the consensus. For more on this approach, see CAMO.

The `raft` decision uses PGDs built-in Raft consensus for commit decisions. Use of the `raft` decision can reduce performance. It's currently required only when using `GROUP COMMIT` with an ALL commit scope group.

Using an ALL commit scope group requires that the commit decision must be set to `raft` to avoid reconciliation issues.

Conflict resolution

Conflict resolution can be `async` or `eager`.

Async means that PGD does optimistic conflict resolution during replication using the row-level resolution as configured for a given node. This happens regardless of whether the origin transaction committed or is still in progress. See Conflicts for details about how the asynchronous conflict resolution works.

Eager means that conflicts are resolved eagerly (as part of agreement on COMMIT), and conflicting transactions get aborted with a serialization error. This approach provides greater isolation than the asynchronous resolution at the price of performance.

Using an ALL commit scope group requires that the commit decision must be set to `raft` to avoid reconciliation issues.

For details about how Eager conflict resolution works, see Eager conflict resolution.

Aborts

To prevent a transaction that can't get consensus on the COMMIT from hanging forever, the `ABORT ON` clause allows specifying timeout. After the timeout, the transaction abort is requested. If the transaction is already decided to be committed at the time the abort request is sent, the transaction does eventually COMMIT even though the client might receive an abort message.

See also Limitations.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Transaction reconciliation

A Group Commit transaction's commit on the origin node is implicitly converted into a two-phase commit.

In the first phase (prepare), the transaction is prepared locally and made ready to commit. The data is made durable but is uncomitted at this stage, so other transactions can't see the changes made by this transaction. This prepared transaction gets copied to all remaining nodes through normal logical replication.

The origin node seeks confirmations from other nodes, as per rules in the Group Commit grammar. If it gets confirmations from the minimum required nodes in the cluster, it decides to commit this transaction moving onto the second phase (commit). In the commit phase, it also sends this decision by way of replication to other nodes. Those nodes will also eventually commit on getting this message.

There's a possibility of failure at various stages. For example, the origin node may crash after preparing the transaction. Or the origin and one or more replicas may crash.

This leaves the prepared transactions in the system. The `pg_prepared_xacts` view in Postgres can show prepared transactions on a system. The prepared transactions might be holding locks and other resources. To release those locks and resources, either abort or commit the transaction. That decision must be made with a consensus of nodes.

When `commit_decision` is `raft`, then, Raft acts as the reconciliator, and these transactions are eventually reconciled automatically.

When the `commit_decision` is `group`, then, transactions don't use Raft. Instead the write lead in the cluster performs the role of reconciliator. This is because it's the node that's most ahead with respect to changes in its subgroup. It detects when a node is down and initiates reconciliation for such a node by looking for prepared transactions it has with the down node as the origin.

For all such transactions, it sees if the nodes as per the rules of the commit scope have the prepared transaction, it takes a decision. This decision is conveyed over Raft and needs the majority of the nodes to be up to do reconciliation.

This process happens in the background. There's no command for you to use to control or issue this.

Eager conflict resolution

Eager conflict resolution (also known as Eager Replication) prevents conflicts by aborting transactions that conflict with each other with serializable errors during the COMMIT decision process.

You configure it using commit scopes as one of the conflict resolution options for Group Commit.

Usage

To enable Eager conflict resolution, the client needs to switch to a commit scope, which uses it at session level or for individual transactions as shown here:

```
BEGIN;

SET LOCAL bdr.commit_scope =
'eager_scope';

... other commands
possible...
```

The client can continue to issue a `COMMIT` at the end of the transaction and let PGD manage the two phases:

```
COMMIT;
```

In this case, the `eager_scope` commit scope is defined something like this:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'eager_scope',
    origin_node_group := 'top_group',
    rule := 'ALL (top_group) GROUP COMMIT (conflict_resolution = eager, commit_decision = raft) ABORT ON (timeout =
60s)',
    wait_for_ready :=
true
);
```

> **Upgrading?**
>
> The old `global` commit scope doesn't exist anymore. The above command creates a scope that's the same as the old `global` scope with `bdr.global_commit_timeout` set to `60s`.

The commit scope group for the Eager conflict resolution rule can only be `ALL` or `MAJORITY`. Where `ALL` is used, the `commit_decision` setting must also be set to `raft`.

Error handling

Given that PGD manages the transaction, the client needs to check only the result of the `COMMIT`. This is advisable in any case, including single-node Postgres.

In case of an origin node failure, the remaining nodes eventually (after at least `ABORT ON timeout`) decide to roll back the globally prepared transaction. Raft prevents inconsistent commit versus rollback decisions. However, this requires a majority of connected nodes. Disconnected nodes keep the transactions prepared to eventually commit them (or roll back) as needed to reconcile with the majority of nodes that might have decided and made further progress.

Effects of Eager Replication in general

Increased abort rate

With single-node Postgres, or even with PGD in its default asynchronous replication mode, errors at `COMMIT` time are rare. The added synchronization step due to the use of a commit scope using `eager` for conflict resolution also adds a source of errors. Applications need to be prepared to properly handle such errors, usually by applying a retry loop.

The rate of aborts depends solely on the workload. Large transactions changing many rows are much more likely to conflict with other concurrent transactions.

Effects of MAJORITY and ALL node replication in general

Increased commit latency

Adding a synchronization step due to the use of a commit scope means more communication between the nodes, resulting in more latency at commit time. When `ALL` is used in the commit scope, this also means that the availability of the system is reduced, since any node going down causes transactions to fail.

If one or more nodes are lagging behind, the round-trip delay in getting confirmations can be large, causing high latencies. ALL or MAJORITY node replication adds roughly two network round trips (to the furthest peer node in the worst case). Logical standby nodes and nodes still in the process of joining or catching up aren't included but eventually receive changes.

Before a peer node can confirm its local preparation of the transaction, it also needs to apply it locally. This further adds to the commit latency, depending on the size of the transaction. This setting is independent of the `synchronous_commit` setting.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.10 Commit At Most Once

Commit scope kind: `CAMO`

Overview

The objective of the Commit At Most Once (CAMO) feature is to prevent the application from committing more than once.

Without CAMO, when a client loses connection after a `COMMIT` is submitted, the application might not receive a reply from the server and is therefore unsure whether the transaction committed.

The application can't easily decide between the two options of:

- Retrying the transaction with the same data, since this can in some cases cause the data to be entered twice
- Not retrying the transaction and risk that the data doesn't get processed at all

Either of those is a critical error with high-value data.

One way to avoid this situation is to make sure that the transaction includes at least one `INSERT` into a table with a unique index. However, that depends on the application design and requires application-specific error-handling logic, so it isn't effective in all cases.

The CAMO feature in PGD offers a more general solution and doesn't require an `INSERT`. When activated by `bdr.commit_scope`, the application receives a message containing the transaction identifier, if already assigned. Otherwise, the first write statement in a transaction sends that information to the client.

If the application sends an explicit `COMMIT`, the protocol ensures that the application receives the notification of the transaction identifier before the `COMMIT` is sent. If the server doesn't reply to the `COMMIT`, the application can handle this error by using the transaction identifier to request the final status of the transaction from another PGD node. If the prior transaction status is known, then the application can safely decide whether to retry the transaction.

CAMO works by creating a pair of partner nodes that are two PGD nodes from the same PGD group. In this operation mode, each node in the pair knows the outcome of any recent transaction executed on the other peer and especially (for our need) knows the outcome of any transaction disconnected during `COMMIT`. The node that receives the transactions from the application might be referred to as "origin" and the node that confirms these transactions as "partner." However, there's no difference in the CAMO configuration for the nodes in the CAMO pair. The pair is symmetric.

> **Warning**
>
> CAMO requires changes to the user's application to take advantage of the advanced error handling. Enabling a parameter isn't enough to gain protection. Reference client implementations are provided to customers on request.

> **Note**
>
> The `CAMO` commit scope kind is mostly an alias for `GROUP COMMIT (transaction_tracking = true, commit_decision = partner)` with an additional `DEGRADE ON` clause.

Requirements

To use CAMO, an application must issue an explicit `COMMIT` message as a separate request, not as part of a multi-statement request. CAMO can't provide status for transactions issued from procedures or from single-statement transactions that use implicit commits.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Configuration

See the `CAMO` commit scope reference for configuration parameters.

Confirmation

Confirmation Level	CAMO handling
`received`	Not applicable, only uses the default, `VISIBLE`.
`replicated`	Not applicable, only uses the default, `VISIBLE`.
`durable`	Not applicable, only uses the default, `VISIBLE`.
`visible` (default)	Confirms the transaction after all of its changes are flushed to disk and it's visible to concurrent transactions.

Limitations

See the CAMO section of Limitations.

Failure scenarios

Different failure scenarios occur in different configurations.

Data persistence at receiver side

By default, a PGL writer operates in `bdr.synchronous_commit = off` mode when applying transactions from remote nodes. This holds true for CAMO as well, meaning that transactions are confirmed to the origin node possibly before reaching the disk of the CAMO partner. In case of a crash or hardware failure, a confirmed transaction might be unrecoverable on the CAMO partner by itself. This isn't an issue as long as the CAMO origin node remains operational, as it redistributes the transaction once the CAMO partner node recovers.

This in turn means CAMO can protect against a single-node failure, which is correct for local mode as well as or even in combination with remote write.

To cover an outage of both nodes of a CAMO pair, you can use `bdr.synchronous_commit = local` to enforce a flush prior to the pre-commit confirmation. This doesn't work with either remote write or local mode and has a performance impact due to I/O requirements on the CAMO partner in the latency sensitive commit path.

Asynchronous mode

When the `DEGRADE ON ... TO ASYNC` clause is used in the commit scope, a node detects whether its CAMO partner is ready. If not, it temporarily switches to asynchronous (local) mode. When in this mode, a node commits transactions locally until switching back to CAMO mode.

This doesn't allow COMMIT status to be retrieved, but it does let you choose availability over consistency. This mode can tolerate a single-node failure. In case both nodes of a CAMO pair fail, they might choose incongruent commit decisions to maintain availability, leading to data inconsistencies.

For a CAMO partner to switch to ready, it needs to be connected, and the estimated catchup interval needs to drop below the `timeout` value of `TO ASYNC`. You can check the current readiness status of a CAMO partner with `bdr.is_camo_partner_ready()`, while `bdr.node_replication_rates` provides the current estimate of the catchup time.

The switch from CAMO-protected to asynchronous mode is only ever triggered by an actual CAMO transaction. This is true either because the commit exceeds the `timeout` value of `TO ASYNC` or, in case the CAMO partner is already known, disconnected at the time of commit. This switch is independent of the estimated catchup interval. If the CAMO pair is configured to require the current node to be the write lead of a group as configured through the `enable_proxy_routing` node group option. See Commit scopes for syntax. This can prevent a split brain situation due to an isolated node from switching to asynchronous mode. If `enable_proxy_routing` isn't set for the CAMO group, the origin node switches to asynchronous mode immediately.

The switch from asynchronous mode to CAMO mode depends on the CAMO partner node, which initiates the connection. The CAMO partner tries to reconnect at least every 30 seconds. After connectivity is reestablished, it might therefore take up to 30 seconds until the CAMO partner connects back to its origin node. Any lag that accumulated on the CAMO partner further delays the switch back to CAMO protected mode.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Unlike during normal CAMO operation, in asynchronous mode there's no added commit overhead. This can be problematic, as it allows the node to continuously process more transactions than the CAMO pair can normally process. Even if the CAMO partner eventually reconnects and applies transactions, its lag only ever increases in such a situation, preventing reestablishing the CAMO protection. To artificially throttle transactional throughput, PGD provides the `bdr.camo_local_mode_delay` setting, which allows you to delay a `COMMIT` in local mode by an arbitrary amount of time. We recommend measuring commit times in normal CAMO mode during expected workloads and configuring this delay accordingly. The default is 5 ms, which reflects a asynchronous network and a relatively quick CAMO partner response.

Consider the choice of whether to allow asynchronous mode in view of the architecture and the availability requirements. The following examples provide some detail.

Example

This example considers a setup with two PGD nodes that are the CAMO partner of each other:

```
-- create a CAMO commit scope for a group
over
-- a definite pair of
nodes
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'camo_dc',
    rule := 'ALL (left_dc) CAMO DEGRADE ON (timeout=500ms) TO
ASYNC'
);
```

For this CAMO commit scope to be legal, the number of nodes in the group must equal exactly 2. Using ALL or ANY 2 on a group consisting of several nodes is an error because the unquantified group expression doesn't resolve to a definite pair of nodes.

With asynchronous mode

If asynchronous mode is allowed, there's no single point of failure. When one node fails:

- The other node can determine the status of all transactions that were disconnected during `COMMIT` on the failed node.
- New write transactions are allowed. If the second node also fails, then the outcome of those transactions that were being committed at that time is unknown.

Without asynchronous mode

If asynchronous mode isn't allowed, then each node requires the other node for committing transactions, that is, each node is a single point of failure. When one node fails:

- The other node can determine the status of all transactions that were disconnected during `COMMIT` on the failed node.
- New write transactions are prevented until the node recovers.

Application use

Overview and requirements

CAMO relies on a retry loop and specific error handling on the client side. There are three aspects to it:

- The result of a transaction's `COMMIT` needs to be checked and, in case of a temporary error, the client must retry the transaction.
- Prior to `COMMIT`, the client must retrieve a global identifier for the transaction, consisting of a node id and a transaction id (both 32-bit integers).
- If the current server fails while attempting a `COMMIT` of a transaction, the application must connect to its CAMO partner, retrieve the status of that transaction, and retry depending on the response.

The application must store the global transaction identifier only for the purpose of verifying the transaction status in case of disconnection during `COMMIT`. In particular, the application doesn't need another persistence layer. If the application fails, it needs only the information in the database to restart.

To illustrate this, this example shows a retry loop in a CAMO-aware client application, written in a C-like pseudo-code. It expects two DSNs, `origin_dsn` and `partner_dsn`, providing connection information. These usually are the same DSNs as used for the initial call to `bdr.create_node` and can be looked up in `bdr.node_summary`, column `interface_connstr`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
PGconn *conn = PQconnectdb(origin_dsn);
```

The process starts connecting to the origin node. Now enter the loop:

```
loop {
    PQexec(conn, "BEGIN");
```

Next, start the transaction and begin populating it with changes:

```
    PQexec(conn, "INSERT INTO ...");
    ...
```

Once you're done, you need to make a record of the local node id and the transaction id. Both are available as parameters.

```
    node_id = PQparameterStatus(conn, "bdr.local_node_id");
    xid = PQparameterStatus(conn, "transaction_id");
```

Now it's ready to try to commit.

```
    PQexec(conn, "COMMIT");
    if (PQresultStatus(res) == PGRES_COMMAND_OK)
        return SUCCESS;
```

If the result is `PGRES_COMMAND_OK`, that's good, and you can move on. But if it isn't, you need to use CAMO to track the transaction to completion. The first question to ask is, "Was the connection bad?"

```
    else if (PQstatus(res) == CONNECTION_BAD)
    {
```

If it was a bad connection, then you can check on the CAMO partner node to see if the transaction made it there.

```
        conn = PQconnectdb(partner_dsn);
        if (!connectionEstablished())
            panic();
```

If you can't connect to the partner node, there's not a lot you can do. In this case, panic, or take similar actions.

But if you can connect, you can use `bdr.logical_transaction_status()` to find out how the transaction did. The code recorded the required values, node_id and xid (the transaction id), just before committing the transaction.

```
        sql = "SELECT bdr.logical_transaction_status($node_id, $xid)";
        txn_status = PQexec(conn, sql);
        if (txn_status == "committed")
            return SUCCESS;
        else
            continue;   // to retry the transaction on the partner
    }
```

If the transaction reports it's been committed, then you can call this transaction a success. No more action is required. If, on the other hand, it doesn't report it's been committed, continue in the loop so the transaction can be retried on the partner node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
    else
    {
        if (isPermanentError())
            return FAILURE;
        else
        {
            sleep(increasing_retry_delay);

            continue;
        }
    }
}
```

If status of the transaction wasn't success or bad connection, check if the problem was a permanent error. If so, report a failure of the transaction. If not, you can still retry it. Have the code sleep for a period of time that increases with each retry, and then retry the transaction.

Working with the CAMO partner

> **Permissions required**
>
> A number of the following CAMO functions require permission. Any user wanting to use CAMO must have at least the bdr_application role assigned to them.

The function `bdr.is_camo_partner_connected()` allows checking the connection status of a CAMO partner node configured in pair mode. There currently is no equivalent for CAMO used with Eager Replication.

To check that the CAMO partner is ready, use the function `bdr.is_camo_partner_ready`. Underneath, this triggers the switch to and from local mode.

To find out more about the configured CAMO partner, use `bdr.get_configured_camo_partner()`. This function returns the local node's CAMO partner.

You can wait on the CAMO partner to process the queue with the function `bdr.wait_for_camo_partner_queue()`. This function is a wrapper of `bdr.wait_for_apply_queue`. The difference is that `bdr.wait_for_camo_partner_queue()` defaults to querying the CAMO partner node. It returns an error if the local node isn't part of a CAMO pair.

To check the status of a transaction that was being committed when the node failed, the application must use the function `bdr.logical_transaction_status()`.

You pass this function the the node_id and transaction_id of the transaction you want to check on. With CAMO used in pair mode, you can use this function only on a node that's part of a CAMO pair. Along with Eager Replication, you can use it on all nodes.

In all cases, you must call the function within 15 minutes after of issuing the commit. The CAMO partner must regularly purge such meta-information and therefore can't provide correct answers for older transactions.

Before querying the status of a transaction, this function waits for the receive queue to be consumed and fully applied. This mechanism prevents early negative answers for transactions that were received but not yet applied.

Despite its name, it's not always a read-only operation. If the status is unknown, the CAMO partner decides whether to commit or abort the transaction, storing that decision locally to ensure consistency going forward.

The client must not call this function before attempting to commit on the origin. Otherwise the transaction might be forced to roll back.

Connection pools and proxies

Consider the effect of connection pools and proxies when designing a CAMO cluster. A proxy might freely distribute transactions to all nodes in the commit group, that is, to both nodes of a CAMO pair or to all PGD nodes in case of Eager All-Node Replication.

Take care to ensure that the application fetches the proper node id. When using session pooling, the client remains connected to the same node, so the node id remains constant for the lifetime of the client session. However, with finer-grained transaction pooling, the client needs to fetch the node id for every transaction, as in the example that follows.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

A client that isn't directly connected to the PGD nodes might not even notice a failover or switchover. But it can always use the `bdr.local_node_id` parameter to determine the node it's currently connected to. In the crucial situation of a disconnect during COMMIT, the proxy must properly forward that disconnect as an error to the client applying the CAMO protocol.

For CAMO in `received` mode, a proxy that potentially switches between the CAMO pairs must use the `bdr.wait_for_camo_partner_queue` function to prevent stale reads.

CAMO limitations

CAMO limitations are covered in Durability limitations.

Performance implications

CAMO extends the Postgres replication protocol by adding a message roundtrip at commit. Applications have a higher commit latency than with asynchronous replication, mostly determined by the round-trip time between involved nodes. Increasing the number of concurrent sessions can help to increase parallelism to obtain reasonable transaction throughput.

The CAMO partner confirming transactions must store transaction states. Compared to non-CAMO operation, this might require an added seek for each transaction applied from the origin.

Client application testing

Proper use of CAMO on the client side isn't trivial. We strongly recommend testing the application behavior with the PGD cluster against failure scenarios, such as node crashes or network outages.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.11 Lag Control

Commit scope kind: `LAG CONTROL`

Overview

Lag Control provides a mechanism where, if replication is running outside of limits set, a delay is injected into the origin node's client connections after processing transactions that make replicable updates. This delay is designed to slow the incoming transactions and bring replication back within the defined limits.

Background

The data throughput of database applications on a PGD origin node can exceed the rate at which committed data can replicate to downstream peer nodes.

If this imbalance persists, it can put satisfying organizational objectives, such as RPO, RCO, and GEO, at risk.

- **Recovery point objective (RPO)** specifies the maximum-tolerated amount of data that can be lost due to unplanned events, usually expressed as an amount of time. In PGD, RPO determines the acceptable amount of committed data that hasn't been applied to one or more peer nodes.
- **Resource constraint objective (RCO)** acknowledges that finite storage is available. In PGD, the demands on these storage resources increase as lag increases.
- **Group elasticity objective (GEO)** ensures that any node isn't originating new data at a rate that can't be saved to its peer nodes.

To allow organizations to achieve their objectives, PGD offers Lag Control. This feature provides a means to precisely regulate the potential imbalance without intruding on applications. It does so by transparently introducing a delay to READ WRITE transactions that modify data. This delay, the PGD commit delay, starts at 0ms.

Using the LAG CONTROL commit scope kind, you can set a maximum time that commits can be delayed between nodes in a group, maximum lag time, or maximum lag size (based on the size of the WAL).

If the nodes can process transactions within the specified maximums on enough nodes, the PGD commit delay will stay at 0ms or be reduced toward 0ms. If the maximums are exceeded on enough nodes, though, the PGD commit delay on the originating node is increased. It will continue increasing until the Lag Control constraints are met on enough nodes again.

The PGD commit delay happens after a transaction has completed and released all its locks and resources. This timing of the delay allows concurrent active transactions to carry on observing and modifying the delayed transactions values and acquiring its resources.

Strictly speaking, the PGD commit delay isn't a per-transaction delay. It's the mean value of commit delays over a stream of transactions for a particular client connection. This technique allows the commit delay and fine-grained adjustments of the value to escape the coarse granularity of OS schedulers, clock interrupts, and variation due to system load. It also allows the PGD runtime commit delay to settle within microseconds of the lowest duration possible to maintain a lag measure threshold.

> **PGD commit delay != Postgres commit delay**
>
> Don't conflate the PGD commit delay with the Postgres commit delay. They are unrelated and perform different functions. Don't substitute one for the other.

Requirements

To get started using Lag Control:

- Determine the maximum acceptable commit delay time `max_commit_delay` that all database applications can tolerate.
- Decide on the lag measure to use. Choose either lag size `max_lag_size` or lag time `max_lag_time`.
- Decide on the groups or subgroups involved and the minimum number of nodes in each collection required to satisfy confirmation. This information forms the basis for the definition of a commit scope rule.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Configuration

You specify Lag Control in a commit scope, which allows consistent and coordinated parameter settings across the nodes spanned by the commit scope rule. You can include a Lag Control specification in the default commit scope of a top group or as part of an origin group commit scope.

As in example, take a configuration with two datacenters, `left_dc` and `right_dc`, represented as subgroups:

```
SELECT bdr.create_node_group(
    node_group_name := 'left_dc',
    parent_group_name := 'top_group',
    join_node_group := false
);
SELECT bdr.create_node_group(
    node_group_name := 'right_dc',
    parent_group_name := 'top_group',
    join_node_group := false
);
```

The following code adds Lag Control rules for those two data centers, using individual rules for each subgroup:

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'left_dc',
    rule := 'ALL (left_dc) LAG CONTROL (max_commit_delay=500ms, max_lag_time=30s) AND ANY 1 (right_dc) LAG CONTROL
(max_commit_delay=500ms, max_lag_time=30s)',
    wait_for_ready :=
true
);
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'right_dc',
    rule := 'ANY 1 (left_dc) LAG CONTROL (max_commit_delay=0.250ms, max_lag_size=100MB) AND ALL (right_dc) LAG
CONTROL (max_commit_delay=0.250ms, max_lag_size=100MB)',
    wait_for_ready :=
true
);
```

You can add a Lag Control commit scope rule to existing commit scope rules that also include Group Commit and CAMO rule specifications.

The `max_commit_delay` is an interval, typically specified in milliseconds (1ms). Using fractional values for sub-millisecond precision is supported.

The `max_lag_size` is an integer that specifies the maximum allowed lag in terms of WAL bytes.

The `max_lag_time` is an interval, typically specified in seconds, that specifies the maximum allowed lag in terms of time.

The maximum commit delay (`max_commit_delay`) is a ceiling value representing a hard limit, which means that a commit delay never exceeds the configured value.

The maximum lag size and time (`max_lag_size` and `max_lag_time`) are soft limits that can be exceeded. When the maximum commit delay is reached, there's no additional back pressure on the lag measures to prevent their continued increase.

Confirmation

Confirmation level	Lag Control handling
`received`	Not applicable, only uses the default, `VISIBLE`.
`replicated`	Not applicable, only uses the default, `VISIBLE`.
`durable`	Not applicable, only uses the default, `VISIBLE`.
`visible` (default)	Not applicable, only uses the default, `VISIBLE`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Transaction application

The PGD commit delay is applied to all READ WRITE transactions that modify data for user applications. This behavior implies that any transaction that doesn't modify data, including declared READ WRITE transactions, is exempt from the commit delay.

Asynchronous transaction commit also executes a PGD commit delay. This might appear counterintuitive, but asynchronous commit, by virtue of its performance, can be one of the greatest sources of replication lag.

Postgres and PGD auxillary processes don't delay at transaction commit. Most notably, PGD writers don't execute a commit delay when applying remote transactions on the local node. This is by design, as PGD writers contribute nothing to outgoing replication lag and can reduce incoming replication lag the most by not having their transaction commits throttled by a delay.

Limitations

The maximum commit delay is a ceiling value representing a hard limit, which means that a commit delay never exceeds the configured value. Conversely, the maximum lag measures both by size and time and are soft limits that can be exceeded. When the maximum commit delay is reached, there's no additional back pressure on the lag measures to prevent their continued increase.

There's no way to exempt origin transactions that don't modify PGD replication sets from the commit delay. For these transactions, it can be useful to SET LOCAL the maximum transaction delay to 0.

Caveats

Application TPS is one of many factors that can affect replication lag. Other factors include the average size of transactions for which PGD commit delay can be less effective. In particular, bulk load operations can cause replication lag to rise, which can trigger a concomitant rise in the PGD runtime commit delay beyond the level reasonably expected by normal applications, although still under the maximum allowed delay.

Similarly, an application with a very high OLTP requirement and modest data changes can be unduly restrained by the acceptable PGD commit delay setting.

In these cases, it can be useful to use the `SET [SESSION|LOCAL]` command to custom configure Lag Control settings for those applications or modify those applications. For example, bulk load operations are sometimes split into multiple smaller transactions to limit transaction snapshot duration and WAL retention size or establish a restart point if the bulk load fails. In deference to Lag Control, those transaction commits can also schedule very long PGD commit delays to allow digestion of the lag contributed by the prior partial bulk load.

Meeting organizational objectives

In the example objectives listed earlier:

- RPO can be met by setting an appropriate maximum lag time.
- RCO can be met by setting an appropriate maximum lag size.
- GEO can be met by monitoring the PGD runtime commit delay and the PGD runtime lag measures,

As mentioned, when the maximum PGD runtime commit delay is pegged at the PGD-configured commit-delay limit, and the lag measures consistently exceed their PGD-configured maximum levels, this scenario can be a marker for PGD group expansion.

Lag Control and extensions

The PGD commit delay is a post-commit delay. It occurs after the transaction has committed and after all Postgres resources locked or acquired by the transaction are released. Therefore, the delay doesn't prevent concurrent active transactions from observing or modifying its values or acquiring its resources. The same guarantee can't be made for external resources managed by Postgres extensions. Regardless of extension dependencies, the same guarantee can be made if the PGD extension is listed before extension-based resource managers in postgresql.conf.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.12 Administering

When running a PGD cluster with Group Commit, you need to be aware of some things when administering the system, such as how to safely shut down and restart nodes.

Planned shutdown and restarts

When using Group Commit with receive confirmations, take care with planned shutdown or restart. By default, the apply queue is processed prior to shutting down. However, in the `immediate` shutdown mode, the queue is discarded at shutdown, leading to the stopped node "forgetting" transactions in the queue. A concurrent failure of the origin node can lead to loss of data, as if both nodes failed.

To ensure the apply queue gets flushed to disk, use either `smart` or `fast` shutdown for maintenance tasks. This approach maintains the required synchronization level and prevents loss of data.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.13 Legacy synchronous replication using PGD

> **Important**
>
> We highly recommend PGD Synchronous Commit instead of legacy synchronous replication.

Postgres provides physical streaming replication (PSR), which is unidirectional but offers a synchronous variant.

For backward compatibility, PGD still supports configuring synchronous replication with `synchronous_commit` and `synchronous_standby_names`. Consider using Group Commit or Synchronous Commit instead.

Unlike PGD replication options, PSR sync persists first, replicating after the WAL flush of commit record.

Usage

To enable synchronous replication using PGD, you need to add the application name of the relevant PGD peer nodes to `synchronous_standby_names`. The use of `FIRST x` or `ANY x` offers some flexibility if this doesn't conflict with the requirements of non-PGD standby nodes.

Once you've added it, you can configure the level of synchronization per transaction using `synchronous_commit`, which defaults to `on`. This setting means that adding the application name to `synchronous_standby_names` already enables synchronous replication. Setting `synchronous_commit` to `local` or `off` turns off synchronous replication.

Due to PGD applying the transaction before persisting it, the values `on` and `remote_apply` are equivalent for logical replication.

Comparison

The following table summarizes what a client can expect from a peer node replicated to after receiving a COMMIT confirmation from the origin node the transaction was issued to. The Mode column takes on different meaning depending on the variant. For PSR and legacy synchronous replication with PGD, it refers to the `synchronous_commit` setting.

Variant	Mode	Received	Visible	Durable
PSR Async	off (default)	no	no	no
PSR Sync	remote_write (2)	yes	no	no (3)
PSR Sync	on (2)	yes	no	yes
PSR Sync	remote_apply (2)	yes	yes	yes
PGD Legacy Sync (1)	remote_write (2)	yes	no	no
PGD Legacy Sync (1)	on (2)	yes	yes	yes
PGD Legacy Sync (1)	remote_apply (2)	yes	yes	yes

(1) Consider using Group Commit instead.

(2) Unless switched to local mode (if allowed) by setting `synchronous_replication_availability` to `async'`, otherwise the values for the asynchronous PGD default apply.

(3) Written to the OS, durable if the OS remains running and only Postgres crashes.

Postgres configuration parameters

The following table provides an overview of the configuration settings that you must set to a non-default value (req) and those that are optional (opt) but affect a specific variant.

Setting (GUC)	Group Commit	Lag Control	PSR	Legacy Sync
synchronous_standby_names	n/a	n/a	req	req
synchronous_commit	n/a	n/a	opt	opt

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Setting (GUC)	Group Commit	Lag Control	PSR	Legacy Sync
synchronous_replication_availability	n/a	n/a	opt	opt

Migration to commit scopes

You configure the Group Commit feature of PGD independent of `synchronous_commit` and `synchronous_standby_names`. Instead, the `bdr.commit_scope` GUC allows you to select the scope per transaction. And instead of configuring `synchronous_standby_names` on each node individually, Group Commit uses globally synchronized commit scopes.

> **Note**
>
> While the grammar for `synchronous_standby_names` and commit scopes looks similar, the former doesn't account for the origin node, but the latter does. Therefore, for example, `synchronous_standby_names = 'ANY 1 (..)'` is equivalent to a commit scope of `ANY 2 (...)`. This choice makes reasoning about majority easier and reflects that the origin node also contributes to the durability and visibility of the transaction.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.14 Limitations

The following limitations apply to the use of commit scopes and the various durability options they enable.

General limitations

- Legacy synchronous replication uses a mechanism for transaction confirmation different from the one used by CAMO, Eager, and Group Commit. The two aren't compatible, so don't use them together. Whenever you use Group Commit, CAMO, or Eager, make sure none of the PGD nodes are configured in `synchronous_standby_names`.
- Postgres two-phase commit (2PC) transactions (that is, `PREPARE TRANSACTION`) can't be used with CAMO, Group Commit, or Eager because those features use two-phase commit underneath.

Group Commit

Group Commit enables configurable synchronous commits over nodes in a group. If you use this feature, take the following limitations into account:

- Not all DDL can run when you use Group Commit. If you use unsupported DDL, a warning is logged, and the transactions commit scope is set to local. The only supported DDL operations are:
  - Nonconcurrent `CREATE INDEX`
  - Nonconcurrent `DROP INDEX`
  - Nonconcurrent `REINDEX` of an individual table or index
  - `CLUSTER` (of a single relation or index only)
  - `ANALYZE`
  - `TRUNCATE`
- Explicit two-phase commit isn't supported by Group Commit as it already uses two-phase commit.
- Combining different commit decision options in the same transaction or combining different conflict resolution options in the same transaction isn't supported.
- Currently, Raft commit decisions are extremely slow, producing very low TPS. We recommended using them only with the `eager` conflict resolution setting to get the Eager All-Node Replication behavior of PGD 4 and older.

Eager

Eager is available through Group Commit. It avoids conflicts by eagerly aborting transactions that might clash. It's subject to the same limitations as Group Commit.

Eager doesn't allow the `NOTIFY` SQL command or the `pg_notify()` function. It also doesn't allow `LISTEN` or `UNLISTEN`.

CAMO

Commit At Most Once (CAMO) is a feature that aims to prevent applications committing more than once. If you use this feature, take these limitations into account when planning:

- CAMO is designed to query the results of a recently failed COMMIT on the origin node. In case of disconnection, the application must request the transaction status from the CAMO partner. Ensure that you have as little delay as possible after the failure before requesting the status. Applications must not rely on CAMO decisions being stored for longer than 15 minutes.
- If the application forgets the global identifier assigned, for example, as a result of a restart, there's no easy way to recover it. Therefore, we recommend that applications wait for outstanding transactions to end before shutting down.
- For the client to apply proper checks, a transaction protected by CAMO can't be a single statement with implicit transaction control. You also can't use CAMO with a transaction-controlling procedure or in a `DO` block that tries to start or end transactions.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- CAMO resolves commit status but doesn't resolve pending notifications on commit. CAMO doesn't allow the `NOTIFY` SQL command or the `pg_notify()` function. They also don't allow `LISTEN` or `UNLISTEN`.

- When replaying changes, CAMO transactions might detect conflicts just the same as other transactions. If timestamp-conflict detection is used, the CAMO transaction uses the timestamp of the prepare-on-the-origin node, which is before the transaction becomes visible on the origin node itself.

- CAMO isn't currently compatible with transaction streaming. Be sure to disable transaction streaming when planning to use CAMO. You can configure this option globally or in the PGD node group. See Transaction streaming configuration.

- CAMO isn't currently compatible with decoding worker. Be sure to not enable decoding worker when planning to use CAMO. You can configure this option in the PGD node group. See Decoding worker disabling.

- Not all DDL can run when you use CAMO. If you use unsupported DDL, a warning is logged and the transactions commit scope is set to local only. The only supported DDL operations are:

    - Nonconcurrent `CREATE INDEX`
    - Nonconcurrent `DROP INDEX`
    - Nonconcurrent `REINDEX` of an individual table or index
    - `CLUSTER` (of a single relation or index only)
    - `ANALYZE`
    - `TRUNCATE`

- Explicit two-phase commit isn't supported by CAMO as it already uses two-phase commit.

- You can combine only CAMO transactions with the `DEGRADE TO` clause for switching to asynchronous operation in case of lowered availability.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

25.15 Internal timing of operations

For a better understanding of how the different modes work, it's helpful to know that legacy physical streaming replication (PSR) and PGD apply transactions in different ways.

With Legacy PSR, the order of operations is:

1. Origin flushes a commit record to WAL, making the transaction visible locally.
2. Peer node receives changes and issues a write.
3. Peer flushes the received changes to disk.
4. Peer applies changes, making the transaction visible on the peer.

Note that the change is written to the disk before applying the chnages.

With PGD, by default and with Lag Control, the order of operations is different. In these cases, the change becomes visible on the peer before the transaction is flushed to the peer's disk:

1. Origin flushes a commit record to WAL, making the transaction visible locally.
2. Peer node receives changes into its apply queue in memory.
3. Peer applies changes, making the transaction visible on the peer.
4. Peer persists the transaction by flushing to disk.

For PGD's Group Commit and CAMO, the origin node waits for a certain number of confirmations prior to making the transaction visible locally. The order of operations is:

1. Origin flushes a prepare or precommit record to WAL.
2. Peer node receives changes into its apply queue in memory.
3. Peer applies changes, making the transaction visible on the peer.
4. Peer persists the transaction by flushing to disk.
5. Origin commits and makes the transaction visible locally.

The following table summarizes the differences.

Variant	Order of apply vs persist	Replication before or after commit
PSR	persist first	after WAL flush of commit record
PGD Async	apply first	after WAL flush of commit record
PGD Lag Control	apply first	after WAL flush of commit record
PGD Group Commit	apply first	before COMMIT on origin
PGD CAMO	apply first	before COMMIT on origin

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26 Conflict Management

EDB Postgres Distributed is an active/active or multi-master DBMS. If used asynchronously, writes to the same or related rows from multiple different nodes can result in data conflicts when using standard data types.

Conflicts aren't errors. In most cases, they're events that PGD can detect and resolve as they occur. Resolution depends on the nature of the application and the meaning of the data, so it's important that PGD provides the application a range of choices as to how to resolve them.

By default, conflicts are resolved at the row level. When changes from two nodes conflict, either the local or remote tuple is picked and the other is discarded. For example, the commit timestamps might be compared for the two conflicting changes and the newer one kept. This approach ensures that all nodes converge to the same result and establishes commit-order-like semantics on the whole cluster.

Column-level conflict detection and resolution is available with PGD, described in CLCD.

If you want to avoid conflicts, you can use Group Commit with Eager conflict resolution or conflict-free data types (CRDTs), described in CRDT. You can also use PGD Proxy and route all writes to one write-leader, eliminating the chance for inter-nodal conflicts.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.1 Conflicts

EDB Postgres Distributed is an active/active or multi-master DBMS. If used asynchronously, writes to the same or related rows from multiple different nodes can result in data conflicts when using standard data types.

Conflicts aren't errors. In most cases, they are events that PGD can detect and resolve as they occur. This section introduces the PGD functionality that allows you to manage that detection and resolution.

- Overview introduces the idea of conflicts in PGD and explains how they can happen.
- Types of conflicts lists and discusses the various sorts of conflicts you might run across in PGD.
- Conflict detection introduces the mechanisms PGD provides for conflict detection.
- Conflict resolution explains how PGD resolves conflicts and how you can change the default behavior.
- Conflict logging points out where PGD keeps conflict logs and explains how you can perform conflict reporting.
- Data verification with LiveCompare explains how LiveCompare can help keep data consistent by pointing out conflicts as they arise.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.1.1 Overview

EDB Postgres Distributed is an active/active or multi-master DBMS. If used asynchronously, writes to the same or related rows from multiple different nodes can result in data conflicts when using standard data types.

Conflicts aren't errors. In most cases, they are events that PGD can detect and resolve as they occur. Resolving them depends on the nature of the application and the meaning of the data, so it's important for PGD to provide the application with a range of choices for how to resolve conflicts.

By default, conflicts are resolved at the row level. When changes from two nodes conflict, PGD picks either the local or remote tuple and the discards the other. For example, the commit timestamps might be compared for the two conflicting changes and the newer one kept. This approach ensures that all nodes converge to the same result and establishes commit-order-like semantics on the whole cluster.

Conflict handling is configurable, as described in Conflict resolution. PGD can detect conflicts and handle them differently for each table using conflict triggers, described in Stream triggers.

Column-level conflict detection and resolution is available with PGD, as described in CLCD.

By default, all conflicts are logged to `bdr.conflict_history`. If conflicts are possible, then table owners must monitor for them and analyze how to avoid them or make plans to handle them regularly as an application task. The LiveCompare tool is also available to scan regularly for divergence.

Some clustering systems use distributed lock mechanisms to prevent concurrent access to data. These can perform reasonably when servers are very close to each other but can't support geographically distributed applications where very low latency is critical for acceptable performance.

Distributed locking is essentially a pessimistic approach. PGD advocates an optimistic approach, which is to avoid conflicts where possible but allow some types of conflicts to occur and resolve them when they arise.

How conflicts happen

Inter-node conflicts arise as a result of sequences of events that can't happen if all the involved transactions happen concurrently on the same node. Because the nodes exchange changes only after the transactions commit, each transaction is individually valid on the node it committed on. It isn't valid if applied on another node that did other conflicting work at the same time.

Since PGD replication essentially replays the transaction on the other nodes, the replay operation can fail if there's a conflict between a transaction being applied and a transaction that was committed on the receiving node.

Most conflicts can't happen when all transactions run on a single node because Postgres has inter-transaction communication mechanisms to prevent it. Examples of these mechanisms are `UNIQUE` indexes, `SEQUENCE` operations, row and relation locking, and `SERIALIZABLE` dependency tracking. All of these mechanisms are ways to communicate between ongoing transactions to prevent undesirable concurrency issues.

PGD doesn't have a distributed transaction manager or lock manager. That's part of why it performs well with latency and network partitions. As a result, transactions on different nodes execute entirely independently from each other when using the default, which is lazy replication. Less independence between nodes can avoid conflicts altogether, which is why PGD also offers Eager Replication for when this is important.

Avoiding or tolerating conflicts

In most cases, you can design the application to avoid or tolerate conflicts.

Conflicts can happen only if things are happening at the same time on multiple nodes. The simplest way to avoid conflicts is to only ever write to one node or to only ever write to a specific row in a specific way from one specific node at a time.

This avoidance happens naturally in many applications. For example, many consumer applications allow only the owning user to change data, such as changing the default billing address on an account. Such data changes seldom have update conflicts.

You might make a change just before a node goes down, so the change seems to be lost. You might then make the same change again, leading to two updates on different nodes. When the down node comes back up, it tries to send the older change to other nodes. It's rejected because the last update of the data is kept.

For `INSERT` / `INSERT` conflicts, use global sequences to prevent this type of conflict.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

For applications that assign relationships between objects, such as a room-booking application, applying `update_if_newer` might not give an acceptable business outcome. That is, it isn't useful to confirm to two people separately that they have booked the same room. The simplest resolution is to use Eager Replication to ensure that only one booking succeeds. More complex ways might be possible depending on the application. For example, you can assign 100 seats to each node and allow those to be booked by a writer on that node. But if none are available locally, use a distributed locking scheme or Eager Replication after most seats are reserved.

Another technique for ensuring certain types of updates occur only from one specific node is to route different types of transactions through different nodes. For example:

- Receiving parcels on one node but delivering parcels using another node
- A service application where orders are input on one node and work is prepared on a second node and then served back to customers on another

Frequently, the best course is to allow conflicts to occur and design the application to work with PGD's conflict resolution mechanisms to cope with the conflict.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.1.2 Types of Conflict

PRIMARY KEY or UNIQUE conflicts

The most common conflicts are row conflicts, where two operations affect a row with the same key in ways they can't on a single node. PGD can detect most of those and applies the `update_if_newer` conflict resolver.

Row conflicts include:

- `INSERT` versus `INSERT`
- `UPDATE` versus `UPDATE`
- `UPDATE` versus `DELETE`
- `INSERT` versus `UPDATE`
- `INSERT` versus `DELETE`
- `DELETE` versus `DELETE`

The view `bdr.node_conflict_resolvers` provides information on how conflict resolution is currently configured for all known conflict types.

INSERT/INSERT conflicts

The most common conflict, `INSERT` / `INSERT`, arises where `INSERT` operations on two different nodes create a tuple with the same `PRIMARY KEY` values (or if no `PRIMARY KEY` exists, the same values for a single `UNIQUE` constraint).

PGD handles this situation by retaining the most recently inserted tuple of the two according to the originating node's timestamps. (A user-defined conflict handler can override this behavior.)

This conflict generates the `insert_exists` conflict type, which is by default resolved by choosing the newer row, based on commit time, and keeping only that one (`update_if_newer` resolver). You can configure other resolvers. See Conflict resolution for details.

To resolve this conflict type, you can also use column-level conflict resolution and user-defined conflict triggers.

You can effectively eliminate this type of conflict by using global sequences.

INSERT operations that violate UNIQUE or EXCLUDE constraints

An `INSERT` / `INSERT` conflict can violate more than one `UNIQUE` constraint, one of which might be the `PRIMARY KEY`. With the addition of `EXCLUDE` constraint support in PGD 5.6, an `INSERT` / `INSERT` conflict can also violate one or more `EXCLUDE` constraints.

In either of the following cases, applying the replication change produces a `multiple_unique_conflicts` conflict. Both of these cases result in a conflict against more than one other row.

- If a new row violates more than one `UNIQUE` constraint and that results in a conflict against more than one other row.
- If a new row violates more than one `EXCLUDE` constraint or a single `EXCLUDE` constraint.

In case of such a conflict, for replication to continue, you must remove some rows. Depending on the resolver setting for `multiple_unique_conflicts`, the apply process either exits with an error, skips the incoming row, or deletes some of the rows. The deletion tries to preserve the row with the correct `PRIMARY KEY` and delete the others.

> **Warning**
>
> In case of multiple rows conflicting this way, if the result of conflict resolution is to proceed with the insert operation, some of the data is always deleted.

You can also define a different behavior using a conflict trigger.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

UPDATE/UPDATE conflicts

Where two concurrent `UPDATE` operations on different nodes change the same tuple but not its `PRIMARY KEY`, an `UPDATE` / `UPDATE` conflict can occur on replay.

These can generate different conflict kinds based on the configuration and situation. If the table is configured with row version conflict detection, then the original (key) row is compared with the local row. If they're different, the `update_differing` conflict is generated. When using origin conflict detection, the origin of the row is checked. (The origin is the node that the current local row came from.) If that changed, the `update_origin_change` conflict is generated. In all other cases, the `UPDATE` is normally applied without generating a conflict.

Both of these conflicts are resolved the same way as `insert_exists`, described in INSERT/INSERT conflicts.

UPDATE conflicts on the PRIMARY KEY

PGD can't currently perform conflict resolution where the `PRIMARY KEY` is changed by an `UPDATE` operation. You can update the primary key, but you must ensure that no conflict with existing values is possible.

Conflicts on the update of the primary key are divergent conflicts and require manual intervention.

Updating a primary key is possible in Postgres, but there are issues in both Postgres and PGD.

To see how these updates behave, create a basic table with a primary key and insert an initial row:

```
CREATE TABLE pktest (pk integer primary key, val
integer);
INSERT INTO pktest VALUES
(1,1);
```

Updating a primary key column is technically possible. This command succeeds because the new value does not conflict with any existing data:

```
UPDATE pktest SET pk=2 WHERE
pk=1;
```

However, suppose the table has multiple rows:

```
INSERT INTO pktest VALUES
(3,3);
```

Some UPDATE operations succeed:

```
UPDATE pktest SET pk=4 WHERE
pk=3;
```

Confirm the changes to the table by selecting all rows. Notice that the primary key values have successfully shifted:

```
SELECT * FROM pktest;
 pk |
val
----+-----
  2 |
1
  4 |
3
(2 rows)
```

Other UPDATE operations fail with constraint errors:

```
UPDATE pktest SET pk=4 WHERE
pk=2;
```

Select all rows from the table and obvserve a standard constraint violation error:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
ERROR:  duplicate key value violates unique constraint
"pktest_pkey"
DETAIL:  Key (pk)=(4) already exists
```

Even without PGD, you must design your application to prevent these runtime errors, as Postgres strictly enforces primary key uniqueness.

Distributed environments like PGD increase the complexity of primary key updates. When multiple nodes attempt to modify keys simultaneously, the results depend on whether the changes overlap or conflict.

If two nodes update different rows to different new primary key values, PGD can replicate the changes successfully:

```
--node1:
UPDATE pktest SET pk=pk+1 WHERE pk =
2;

After replication, both nodes reflect the incremented values, maintaining a consistent state across the
cluster:

--node2:
UPDATE pktest SET pk=pk+1 WHERE pk =
4;
```

```
SELECT * FROM pktest;

 pk |
val
----+-----
  3 |
1
  5 |
3
(2 rows)
```

Executing these next two changes concurrently causes a divergent error, since both changes are accepted. Both nodes accept their own local change, but applying the changes on the other node results in `update_missing` conflicts.

```
--node1:
UPDATE pktest SET pk=1 WHERE pk =
3;
--node2:
UPDATE pktest SET pk=2 WHERE pk =
3;
```

This scenario leaves the data different on each node:

```
--node1:
SELECT * FROM pktest;
 pk |
val
----+-----
  1 |
1
  5 |
3
(2 rows)

--node2:
SELECT * FROM pktest;
 pk |
val
----+-----
  2 |
1
  5 |
3
(2 rows)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

You can identify and resolve this situation using LiveCompare.

Concurrent conflicts present problems. Executing these two changes concurrently isn't easy to resolve:

```
--node1:
UPDATE pktest SET pk=6, val=8 WHERE pk =
5;
--node2:
UPDATE pktest SET pk=6, val=9 WHERE pk =
5;
```

Both changes are applied locally, causing a divergence between the nodes. But the apply on the target fails on both nodes with a duplicate key-value violation error. This error causes the replication to halt and requires manual resolution.

You can avoid this duplicate key violation error, and replication doesn't break, if you set the conflict_type `update_pkey_exists` to `skip`, `update`, or `update_if_newer`. This approach can still lead to divergence depending on the nature of the update.

You can avoid divergence in cases where the same old key is being updated by the same new key concurrently by setting `update_pkey_exists` to `update_if_newer`. However, in certain situations, divergence occurs even with `update_if_newer`, namely when two different rows both are updated concurrently to the same new primary key.

As a result, we recommend strongly against allowing primary key UPDATE operations in your applications, especially with PGD. If parts of your application change primary keys, then to avoid concurrent changes, make those changes using Eager Replication.

> **Warning**
>
> In case the conflict resolution of `update_pkey_exists` conflict results in update, one of the rows is always deleted.

UPDATE operations that violate UNIQUE or EXCLUDE constraints

Like INSERT operations that violate multiple UNIQUE/EXCLUDE constraints, when an incoming `UPDATE` violates more than one `UNIQUE` / `EXCLUDE` index (including the `PRIMARY KEY`) or violates a single `EXCLUDE` index such that more than one row is in conflict, PGD raises a `multiple_unique_conflicts` conflict.

PGD supports deferred unique constraints. If a transaction can commit on the source, then it applies cleanly on target, unless it sees conflicts. However, you can't use a deferred primary key as a REPLICA IDENTITY, so the use cases are already limited by that and the warning about using multiple unique constraints.

UPDATE/DELETE conflicts

One node can update a row that another node deletes at the same time. In this case an `UPDATE` / `DELETE` conflict can occur on replay.

If the deleted row is still detectable (the deleted row wasn't removed by `VACUUM`), the `update_recently_deleted` conflict is generated. By default, the `UPDATE` is skipped, but you can configure the resolution for this. See Conflict resolution for details.

The database can clean up the deleted row by the time the `UPDATE` is received in case the local node is lagging behind in replication. In this case, PGD can't differentiate between `UPDATE` / `DELETE` conflicts and INSERT/UPDATE conflicts. It generates the `update_missing` conflict.

Another type of conflicting `DELETE` and `UPDATE` is a `DELETE` that comes after the row was updated locally. In this situation, the outcome depends on the type of conflict detection used. When using the default, origin conflict detection, no conflict is detected, leading to the `DELETE` being applied and the row removed. If you enable row version conflict detection, a `delete_recently_updated` conflict is generated. The default resolution for a `delete_recently_updated` conflict is to `skip` the deletion. However, you can configure the resolution or a conflict trigger can be configured to handle it.

INSERT/UPDATE conflicts

When using the default asynchronous mode of operation, a node might receive an `UPDATE` of a row before the original `INSERT` was received. This can happen only when three or more nodes are active (see Conflicts with three or more nodes).

When this happens, the `update_missing` conflict is generated. The default conflict resolver is `insert_or_skip`, though you can use `insert_or_error` or `skip` instead. Resolvers that do insert-or-action first try to `INSERT` a new row based on data from the `UPDATE` when possible (when the whole row was received). For reconstructing the row to be possible, the table either needs to have `REPLICA IDENTITY FULL` or the row must not contain any toasted data.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

See TOAST support details for more info about toasted data.

INSERT/DELETE conflicts

Similar to the `INSERT` / `UPDATE` conflict, the node might also receive a `DELETE` operation on a row for which it didn't yet receive an `INSERT`. This is again possible only with three or more nodes set up (see Conflicts with three or more nodes).

PGD can't currently detect this conflict type. The `INSERT` operation doesn't generate any conflict type, and the `INSERT` is applied.

The `DELETE` operation always generates a `delete_missing` conflict, which is by default resolved by skipping the operation.

DELETE/DELETE conflicts

A `DELETE` / `DELETE` conflict arises when two different nodes concurrently delete the same tuple.

This scenario always generates a `delete_missing` conflict, which is by default resolved by skipping the operation.

This conflict is harmless since both `DELETE` operations have the same effect. You can safely ignroe one of them.

Conflicts with three or more nodes

If one node inserts a row that's then replayed to a second node and updated there, a third node can receive the `UPDATE` from the second node before it receives the `INSERT` from the first node. This scenario is an `INSERT` / `UPDATE` conflict.

These conflicts are handled by discarding the `UPDATE`, which can lead to different data on different nodes. These are divergent conflicts.

This conflict type can happen only with three or more masters. At least two masters must be actively writing.

Also, the replication lag from node 1 to node 3 must be high enough to allow the following sequence of actions:

1. node 2 receives INSERT from node 1
2. node 2 performs UPDATE
3. node 3 receives UPDATE from node 2
4. node 3 receives INSERT from node 1

Using `insert_or_error` (or in some cases the `insert_or_skip` conflict resolver for the `update_missing` conflict type) is a viable mitigation strategy for these conflicts. However, enabling this option opens the door for `INSERT` / `DELETE` conflicts:

1. node 1 performs UPDATE
2. node 2 performs DELETE
3. node 3 receives DELETE from node 2
4. node 3 receives UPDATE from node 1, turning it into an INSERT

If these are problems, we recommend tuning freezing settings for a table or database so that they're correctly detected as `update_recently_deleted`.

Another alternative is to use Eager Replication to prevent these conflicts.

`INSERT` / `DELETE` conflicts can also occur with three or more nodes. Such a conflict is identical to `INSERT` / `UPDATE` except with the `UPDATE` replaced by a `DELETE`. This can result in a `delete_missing` conflict.

PGD could choose to make each `INSERT` into a check-for-recently deleted, as occurs with an `update_missing` conflict. However, the cost of doing this penalizes the majority of users, so at this time it instead logs `delete_missing`.

Future releases will automatically resolve `INSERT` / `DELETE` anomalies by way of rechecks using LiveCompare when `delete_missing` conflicts occur. Applications can perform these manually by checking the `bdr.conflict_history_summary` view.

These conflicts can occur in two main problem use cases:

- `INSERT` followed rapidly by a `DELETE`, as can be used in queuing applications
- Any case where the primary key identifier of a table is reused

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Neither of these cases is common. We recommend not replicating the affected tables if these problem use cases occur.

PGD has problems with the latter case because PGD relies on the uniqueness of identifiers to make replication work correctly.

Applications that insert, delete, and then later reuse the same unique identifiers can cause difficulties. This is known as the ABA problem. PGD has no way of knowing whether the rows are the current row, the last row, or much older rows.

Unique identifier reuse is also a business problem, since it prevents unique identification over time, which prevents auditing, traceability, and sensible data quality. Applications don't need to reuse unique identifiers.

Any identifier reuse that occurs in the time interval it takes for changes to pass across the system causes difficulties. Although that time might be short in normal operation, down nodes can extend that interval to hours or days.

We recommend that applications don't reuse unique identifiers. If they do, take steps to avoid reuse in less than a year.

This problem doesn't occur in applications that use sequences or UUIDs.

Foreign key constraint conflicts

Conflicts between a remote transaction being applied and existing local data can also occur for `FOREIGN KEY` (FK) constraints.

PGD applies changes with `session_replication_role = 'replica'`, so foreign keys aren't rechecked when applying changes. In an active/active environment, this situation can result in FK violations if deletes occur to the referenced table at the same time as inserts into the referencing table. This scenario is similar to an `INSERT` / `DELETE` conflict.

In single-master Postgres, any `INSERT` / `UPDATE` that refers to a value in the referenced table must wait for `DELETE` operations to finish before they can gain a row-level lock. If a `DELETE` removes a referenced value, then the `INSERT` / `UPDATE` fails the FK check.

In multi-master PGD. there are no inter-node row-level locks. An `INSERT` on the referencing table doesn't wait behind a `DELETE` on the referenced table, so both actions can occur concurrently. Thus an `INSERT` / `UPDATE` on one node on the referencing table can use a value at the same time as a `DELETE` on the referenced table on another node. The result, then, is a value in the referencing table that's no longer present in the referenced table.

In practice, this situation occurs if the `DELETE` operations occur on referenced tables in separate transactions from `DELETE` operations on referencing tables, which isn't a common operation.

In a parent-child relationship such as Orders -> OrderItems, it isn't typical to do this. It's more likely to mark an OrderItem as canceled than to remove it completely. For reference/lookup data, it's unusual to completely remove entries at the same time as using those same values for new fact data.

While dangling FKs are possible, the risk of this in general is very low. Thus PGD doesn't impose a generic solution to cover this case. Once you understand the situation in which this occurs, two solutions are possible.

The first solution is to restrict the use of FKs to closely related entities that are generally modified from only one node at a time, are infrequently modified, or where the modification's concurrency is application mediated. This approach avoids any FK violations at the application level.

The second solution is to add triggers to protect against this case using the PGD-provided functions `bdr.ri_fkey_trigger()` and `bdr.ri_fkey_on_del_trigger()`. When called as `BEFORE` triggers, these functions use `FOREIGN KEY` information to avoid FK anomalies by setting referencing columns to NULL, much as if you had a SET NULL constraint. This approach rechecks all FKs in one trigger, so you need to add only one trigger per table to prevent FK violation.

As an example, suppose you have two tables: Fact and RefData. Fact has an FK that references RefData. Fact is the referencing table, and RefData is the referenced table. You need to add one trigger to each table.

Add a trigger that sets columns to NULL in Fact if the referenced row in RefData was already deleted:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TRIGGER
bdr_replica_fk_iu_trg
    BEFORE INSERT OR UPDATE ON fact
    FOR EACH ROW
    EXECUTE PROCEDURE bdr.ri_fkey_trigger();

ALTER TABLE fact
    ENABLE REPLICA TRIGGER bdr_replica_fk_iu_trg;
```

Add a trigger that sets columns to NULL in Fact at the time a DELETE occurs on the RefData table:

```
CREATE TRIGGER bdr_replica_fk_d_trg
    BEFORE DELETE ON refdata
    FOR EACH ROW
    EXECUTE PROCEDURE
bdr.ri_fkey_on_del_trigger();

ALTER TABLE refdata
    ENABLE REPLICA TRIGGER
bdr_replica_fk_d_trg;
```

Adding both triggers avoids dangling foreign keys.

TRUNCATE conflicts

`TRUNCATE` behaves similarly to a `DELETE` of all rows but performs this action by physically removing the table data rather than row-by-row deletion. As a result, row-level conflict handling isn't available, so `TRUNCATE` commands don't generate conflicts with other DML actions, even when there's a clear conflict.

As a result, the ordering of replay can cause divergent changes if another DML is executed concurrently on other nodes to the `TRUNCATE`.

You can take one of the following actions:

- Ensure `TRUNCATE` isn't executed alongside other concurrent DML. Rely on LiveCompare to highlight any such inconsistency.
- Replace `TRUNCATE` with a `DELETE` statement with no `WHERE` clause. This approach is likely to have poor performance on larger tables.
- Set `bdr.truncate_locking = 'on'` to set the `TRUNCATE` command's locking behavior. This setting determines whether `TRUNCATE` obeys the `bdr.ddl_locking` setting. This isn't the default behavior for `TRUNCATE` since it requires all nodes to be up. This configuration might not be possible or wanted in all cases.

Data conflicts for roles and tablespace differences

Conflicts can also arise where nodes have global (Postgres-system-wide) data, like roles, that differ. This conflict can result in operations—mainly `DDL`—that can run successfully and commit on one node but then fail to apply to other nodes.

For example, node1 might have a user named fred, and that user wasn't created on node2. If fred on node1 creates a table, the table is replicated with its owner set to fred. When the DDL command is applied to node2, the DDL fails because there's no user named fred. This failure generates an error in the Postgres logs.

Administrator intervention is required to resolve this conflict by creating the user fred in the database where PGD is running. You can set `bdr.role_replication = on` to resolve this in future.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Lock conflicts and deadlock aborts

Because PGD writer processes operate much like normal user sessions, they're subject to the usual rules around row and table locking. This can sometimes lead to PGD writer processes waiting on locks held by user transactions or even by each other.

Relevant locking includes:

- Explicit table-level locking (`LOCK TABLE ...`) by user sessions
- Explicit row-level locking (`SELECT ... FOR UPDATE/FOR SHARE`) by user sessions
- Implicit locking because of row `UPDATE` , `INSERT` , or `DELETE` operations, either from local activity or from replication from other nodes

A PGD writer process can deadlock with a user transaction, where the user transaction is waiting on a lock held by the writer process and vice versa. Two writer processes can also deadlock with each other. Postgres's deadlock detector steps in and terminates one of the problem transactions. If the PGD writer process is terminated, it retries and generally succeeds.

All these issues are transient and generally require no administrator action. If a writer process is stuck for a long time behind a lock on an idle user session, the administrator can terminate the user session to get replication flowing again. However, this is no different from a user holding a long lock that impacts another user session.

Use of the log_lock_waits facility in Postgres can help identify locking related replay stalls.

Divergent conflicts

Divergent conflicts arise when data that should be the same on different nodes differs unexpectedly. Divergent conflicts shouldn't occur, but not all such conflicts can be reliably prevented at the time of writing.

Changing the `PRIMARY KEY` of a row can lead to a divergent conflict if another node changes the key of the same row before all nodes have replayed the change. Avoid changing primary keys, or change them only on one designated node.

Divergent conflicts involving row data generally require administrator action to manually adjust the data on one of the nodes to be consistent with the other one. Such conflicts don't arise so long as you use PGD as documented and avoid settings or functions marked as unsafe.

The administrator must manually resolve such conflicts. You might need to use the advanced options such as `bdr.ddl_replication` and `bdr.ddl_locking` depending on the nature of the conflict. However, careless use of these options can make things much worse and create a conflict that generic instructions can't address.

TOAST support details

Postgres uses out-of-line storage for larger columns called TOAST.

The TOAST values handling in logical decoding (which PGD is built on top of) and logical replication is different from inline data stored as part of the main row in the table.

The TOAST value is logged into the transaction log (WAL) only if the value changed. This can cause problems, especially when handling UPDATE conflicts, because an `UPDATE` statement that didn't change a value of a toasted column produces a row without that column. As mentioned in INSERT/UPDATE conflicts, PGD reports an error if an `update_missing` conflict is resolved using `insert_or_error` and there are missing TOAST columns.

However, more subtle issues than this one occur in case of concurrent workloads with asynchronous replication. (Eager transactions aren't affected.) Imagine, for example, the following workload on an EDB Postgres Distributed cluster with three nodes called A, B, and C:

1. On node A: txn A1 does an UPDATE SET col1 = 'toast data...' and commits first.
2. On node B: txn B1 does UPDATE SET other_column = 'anything else'; and commits after A1.
3. On node C: the connection to node A lags behind.
4. On node C: txn B1 is applied first, it misses the TOASTed column in col1, but gets applied without conflict.
5. On node C: txn A1 conflicts (on update_origin_change) and is skipped.
6. Node C misses the toasted data from A1 forever.

This scenario isn't usually a problem when using PGD. (It is when using either built-in logical replication or plain pglogical for multi-master.) PGD adds its own logging of TOAST columns when it detects a local `UPDATE` to a row that recently replicated a TOAST column modification and the local `UPDATE` isn't modifying the TOAST. Thus PGD prevents any inconsistency for toasted data across different nodes. This situation causes increased WAL logging when updates occur on multiple nodes, that is, when origin changes for a tuple. Additional WAL overhead is zero if all updates are made from a single node, as is normally the case with PGD AlwaysOn architecture.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Note**
>
> Running `VACUUM FULL` or `CLUSTER` on just the TOAST table without doing same on the main table removes metadata needed for the extra logging to work. This means that, for a short period after such a statement, the protection against these concurrency issues isn't present.

> **Warning**
>
> The additional WAL logging of TOAST is done using the `BEFORE UPDATE` trigger on standard Postgres. This trigger must be sorted alphabetically last based on trigger name among all `BEFORE UPDATE` triggers on the table. It's prefixed with `zzzz_bdr_` to make this easier, but make sure you don't create any trigger with a name that sorts after it. Otherwise you won't have the protection against the concurrency issues.

For the `insert_or_error` conflict resolution, the use of `REPLICA IDENTITY FULL` is still required.

None of these problems associated with toasted columns affect tables with `REPLICA IDENTITY FULL`. This setting always logs a toasted value as part of the key since the whole row is considered to be part of the key. PGD can reconstruct the new row, filling the missing data from the key row. As a result, using `REPLICA IDENTITY FULL` can increase WAL size significantly.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.1.3 Conflict detection

PGD provides these mechanisms for conflict detection:

- Origin conflict detection (default)
- Row version conflict detection
- Column-level conflict detection

Origin conflict detection

Origin conflict detection uses and relies on commit timestamps as recorded on the node the transaction originates from. This requires clocks to be in sync to work correctly or to be within a tolerance of the fastest message between two nodes. If this isn't the case, conflict resolution tends to favor the node that's further ahead. You can manage clock skew between nodes using the parameters `bdr.maximum_clock_skew` and `bdr.maximum_clock_skew_action`.

Row origins are available only if `track_commit_timestamp = on`.

Conflicts are first detected based on whether the replication origin changed, so conflict triggers are called in situations that might not turn out to be conflicts. Hence, this mechanism isn't precise, since it can generate false-positive conflicts.

Origin info is available only up to the point where a row is frozen. Updates arriving for a row after it was frozen don't raise a conflict so are applied in all cases. This is the normal case when adding a new node by `bdr_init_physical`, so raising conflicts causes many false-positive results in that case.

A node that was offline that reconnects and begins sending data changes can cause divergent errors if the newly arrived updates are older than the frozen rows that they update. Inserts and deletes aren't affected by this situation.

We suggest that you don't leave down nodes for extended outages, as discussed in Node restart and down node recovery.

On EDB Postgres Extended Server and EDB Postgres Advanced Server, PGD holds back the freezing of rows while a node is down. This mechanism handles this situation gracefully so you don't need to change parameter settings.

On other variants of Postgres, you might need to manage this situation with some care.

Freezing normally occurs when a row being vacuumed is older than `vacuum_freeze_min_age` xids from the current xid, which means that you need to configure suitably high values for these parameters:

- `vacuum_freeze_min_age`
- `vacuum_freeze_table_age`
- `autovacuum_freeze_max_age`

Choose values based on the transaction rate, giving a grace period of downtime before removing any conflict data from the database node. For example, when `vacuum_freeze_min_age` is set to 500 million, a node performing 1000 TPS can be down for just over 5.5 days before conflict data is removed. The CommitTS data structure takes on-disk space of 5 GB with that setting, so lower transaction rate systems can benefit from lower settings.

Initially, recommended settings are:

```
# 1 billion = 10GB
autovacuum_freeze_max_age = 1000000000

vacuum_freeze_min_age = 500000000

# 90% of autovacuum_freeze_max_age
vacuum_freeze_table_age = 900000000
```

Note that:

- You can set `autovacuum_freeze_max_age` only at node start.
- You can set `vacuum_freeze_min_age`, so using a low value freezes rows early and can result in conflicts being ignored. You can also set `autovacuum_freeze_min_age` and `toast.autovacuum_freeze_min_age` for individual tables.
- Running the `CLUSTER` or `VACUUM FREEZE` commands also freezes rows early and can result in conflicts being ignored.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Row version conflict detection

PGD provides the option to use row versioning and make conflict detection independent of the nodes' system clock.

Row version conflict detection requires that you enable three things. If any of these steps aren't performed correctly thenorigin conflict detection is used.

- Enable `REPLICA IDENTITY FULL` on all tables that use row version conflict detection.
- Enable row version tracking on the table by using `bdr.alter_table_conflict_detection`. This function adds a column with a name you specify and an `UPDATE` trigger that manages the new column value. The column is created as `INTEGER` type.

Although the counter is incremented only on `UPDATE`, this technique allows conflict detection for both `UPDATE` and `DELETE`.

This approach resembles Lamport timestamps and fully prevents the ABA problem for conflict detection.

> **Note**
>
> The row-level conflict resolution is still handled based on the conflict resolution configuration even with row versioning. The way the row version is generated is useful only for detecting conflicts. Don't rely on it as authoritative information about which version of row is newer.

To determine the current conflict detection strategy used for a specific table, refer to the column `conflict_detection` of the view `bdr.tables`.

To change the current conflict detection strategy, use bdr.alter_table_conflict_detection.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.1.4 Conflict resolution

Most conflicts can be resolved automatically. PGD defaults to a last-update-wins mechanism or, more accurately, the `update_if_newer` conflict resolver. This mechanism retains the most recently inserted or changed row of the two conflicting ones based on the same commit timestamps used for conflict detection. The behavior in certain corner-case scenarios depends on the settings used for `bdr.create_node_group` and alternatively for `bdr.alter_node_group`.

PGD lets you override the default behavior of conflict resolution by using bdr.alter_node_set_conflict_resolver.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.1.5 Conflict logging

To ease diagnosing and handling multi-master conflicts, PGD, by default, logs every conflict into the `bdr.conflict_history` table. You can change this behavior with more granularity using bdr.alter_node_set_log_config.

Conflict reporting

You can summarize conflicts logged to tables in reports. Reports allow application owners to identify, understand, and resolve conflicts and introduce application changes to prevent them.

```
SELECT nspname,
relname
, date_trunc('day', local_time) :: date AS
date
, count(*)
FROM bdr.conflict_history
WHERE local_time > date_trunc('day',
current_timestamp)
GROUP BY 1,2,3
ORDER BY 1,2;

```sql
 nspname | relname |    date    |
count
---------+---------+------------+-------
 my_app  | test    | 2019-04-05 |
1
(1 row)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.
```

26.1.6 Data verification with LiveCompare

LiveCompare is a utility program designed to compare any two databases to verify that they are identical.

LiveCompare is included as part of the PGD stack and can be aimed at any pair of PGD nodes. By default, it compares all replicated tables and reports differences. LiveCompare also works with non-PGD data sources such as Postgres and Oracle.

You can also use LiveCompare to continuously monitor incoming rows. You can stop and start it without losing context information, so you can run it at convenient times.

LiveCompare allows concurrent checking of multiple tables. You can configure it to allow checking of a few tables or just a section of rows in a table. Checks are performed by first comparing whole row hashes. If different, LiveCompare then compares whole rows. LiveCompare avoids overheads by comparing rows in useful-sized batches.

If differences are found, they can be rechecked over time, allowing for the delays of eventual consistency.

See the LiveCompare documentation for further details.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.2 Column-level conflict detection

By default, conflicts are resolved at row level. When changes from two nodes conflict, either the local or remote tuple is selected and the other is discarded. For example, commit timestamps for the two conflicting changes might be compared and the newer one kept. This approach ensures that all nodes converge to the same result and establishes commit-order-like semantics on the whole cluster.

However, it might sometimes be appropriate to resolve conflicts at the column level rather than the row level, at least in some cases.

- Overview introduces column-level conflict resolution in contrast to row-level conflict resolution, suggesting where it might be a better fit than row-level conflict resolution.
- Enabling and disabling provides an example of enabling column-level conflict resolution and explains how to list tables with column-level conflict resolution enabled.
- Timestamps explicates the difference between using `column_modify_timestamp` and `column_commit_timestamp` and shows how the timestamps associated with column-level conflict resolution can be selected and inspected.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.2.1 Overview

By default, conflicts are resolved at row level. When changes from two nodes conflict, either the local or remote tuple is selected and the other is discarded. For example, commit timestamps for the two conflicting changes might be compared and the newer one kept. This approach ensures that all nodes converge to the same result and establishes commit-order-like semantics on the whole cluster.

However, it might sometimes be appropriate to resolve conflicts at the column level rather than the row level, at least in some cases.

When to resolve at the column level

Consider a simple example in which table t has two integer columns, a and b, and a single row `(1,1)`. On one node execute:

```
UPDATE t SET a =
100
```

On another node, before receiving the preceding `UPDATE`, concurrently execute:

```
UPDATE t SET b =
100
```

> **Note**
>
> The attributes modified by an `UPDATE` are determined by comparing the old and new row in a trigger. This means that if the attribute doesn't change a value, it isn't detected as modified even if it's explicitly set. For example, `UPDATE t SET a = a` doesn't mark `a` as modified for any row. Similarly, `UPDATE t SET a = 1` doesn't mark `a` as modified for rows that are already set to `1`.

This sequence results in an `UPDATE-UPDATE` conflict. With the `update_if_newer` conflict resolution, the commit timestamps are compared, and the new row version is kept. Assuming the second node committed last, the result is `(1,100)`, which effectively discards the change to column a.

For many use cases, this behavior is desired and expected. However, for some use cases, this might be an issue. Consider, for example, a multi-node cluster where each part of the application is connected to a different node, updating a dedicated subset of columns in a shared table. In that case, the different components might conflict and overwrite changes.

For such use cases, it might be more appropriate to resolve conflicts on a given table at the column level. To achieve that, PGD tracks the timestamp of the last change for each column separately and uses that to pick the most recent value, essentially performing `update_if_newer`.

Applied to the previous example, the result is `(100,100)` on both nodes, despite neither of the nodes ever seeing such a row.

When thinking about column-level conflict resolution, it can be useful to see tables as vertically partitioned, so that each update affects data in only one slice. This approach eliminates conflicts between changes to different subsets of columns. In fact, vertical partitioning can even be a practical alternative to column-level conflict resolution.

Column-level conflict resolution requires the table to have `REPLICA IDENTITY FULL`. The bdr.alter_table_conflict_detection() function checks that and fails with an error if this setting is missing.

Special problems for column-level conflict resolution

By treating the columns independently, it's easy to violate constraints in a way that isn't possible when all changes happen on the same node. Consider, for example, a table like this:

```
CREATE TABLE t (id INT PRIMARY KEY, a INT, b INT, CHECK (a >
b));
INSERT INTO t VALUES (1, 1000,
1);
```

Assume one node does:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
UPDATE t SET a =
100;
```

Another node concurrently does:

```
UPDATE t SET b =
500;
```

Each of those updates is valid when executed on the initial row and so passes on each node. But when replicating to the other node, the resulting row violates the `CHECK (a > b)` constraint, and the replication stops until the issue is resolved manually.

Handling column-level conflicts using CRDT data types

By default, column-level conflict resolution picks the value with a higher timestamp and discards the other one. You can, however, reconcile the conflict in different, more elaborate ways. For example, you can use CRDT types that allow merging the conflicting values without discarding any information.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.2.2 Enabling and disabling column-level conflict resolution

> **Permissions required**
>
> Column-level conflict detection uses the `column_timestamps` type. This type requires any user needing to detect column-level conflicts to have at least the bdr_application role assigned.

The bdr.alter_table_conflict_detection() function manages column-level conflict resolution.

Using bdr.alter_table_conflict_detection to enable column-level conflict resolution

The bdr.alter_table_conflict_detection function takes a table name and column name as its arguments. The column is added to the table as a `column_modify_timestamp` column. The function also adds two triggers (BEFORE INSERT and BEFORE UPDATE) that are responsible for maintaining timestamps in the new column before each change.

```
db=# CREATE TABLE my_app.test_table (id SERIAL PRIMARY KEY, val
INT);
CREATE TABLE

db=# ALTER TABLE my_app.test_table REPLICA IDENTITY
FULL;
ALTER TABLE

db=# SELECT bdr.alter_table_conflict_detection(
db(# 'my_app.test_table'::regclass,
db(# 'column_modify_timestamp', 'cts');
 alter_table_conflict_detection
--------------------------------

t

db=# \d my_app.test_table
                                      Table "my_app.test_table"
 Column |         Type          | Collation | Nullable |
Default
--------+-----------------------+-----------+----------+-----------------------------------------------------
 id     | integer               |           | not null |
nextval('my_app.test_table_id_seq'::regclass)
 val    | integer               |           |
|
 cts    | bdr.column_timestamps |           | not null | 's 1 775297963454602 0
0'::bdr.column_timestamps
Indexes:
    "test_table_pkey" PRIMARY KEY, btree
(id)
Triggers:
    bdr_clcd_before_insert BEFORE INSERT ON my_app.test_table FOR EACH ROW EXECUTE FUNCTION
bdr.column_timestamps_current_insert()
    bdr_clcd_before_update BEFORE UPDATE ON my_app.test_table FOR EACH ROW EXECUTE FUNCTION
bdr.column_timestamps_current_update()
```

The new column specifies `NOT NULL` with a default value, which means that `ALTER TABLE ... ADD COLUMN` doesn't perform a table rewrite.

> **Note**
>
> Avoid using columns with the `bdr.column_timestamps` data type for other purposes, as doing so can have negative effects. For example, it switches the table to column-level conflict resolution, which doesn't work correctly without the triggers.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Listing tables with column-level conflict resolution

You can list tables having column-level conflict resolution enabled with the following query.

```
SELECT nc.nspname,
c.relname
FROM pg_attribute
a
JOIN (pg_class c JOIN pg_namespace nc ON c.relnamespace =
nc.oid)
  ON a.attrelid = c.oid
JOIN (pg_type t  JOIN pg_namespace nt ON t.typnamespace =
nt.oid)
  ON a.atttypid = t.oid
WHERE NOT pg_is_other_temp_schema(nc.oid)
  AND nt.nspname = 'bdr'
  AND t.typname = 'column_timestamps'
  AND NOT
a.attisdropped
  AND c.relkind IN ('r', 'v', 'f',
'p');
```

This query detects the presence of a column of type `bdr.column_timestamp`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.2.3 Timestamps in column-level conflict resolution

Column-level conflict resolution depends on a timestamp column being included in the table.

Comparing `column_modify_timestamp` and `column_commit_timestamp`

When you select one of the two column-level conflict detection methods, a column is added to the table that contains a mapping of modified columns and timestamps.

The column that stores timestamp mapping is managed automatically. Don't specify or override the value in your queries, as the results can be unpredictable. When possible, user attempts to override the value are ignored.

When enabling or disabling column timestamps on a table, the code uses DDL locking to ensure that there are no pending changes from before the switch. This approach ensures only conflicts with timestamps in both tuples or in neither of them are seen. Otherwise, the code might unexpectedly see timestamps in the local tuple and NULL in the remote one. It also ensures that the changes are resolved the same way (column-level or row-level) on all nodes.

`column_modify_timestamp`

When `column_modify_timestamp` is selected as the conflict detection method, the timestamp assigned to the modified columns is the current timestamp, similar to the value you might get running `select_clock_timestamp()`.

This approach is simple and, for many cases, it's correct, for example, when the conflicting rows modify non-overlapping subsets of columns. Its simplicity can, though, lead to unexpected effects.

For example, if an `UPDATE` affects multiple rows, the clock continues ticking while the `UPDATE` runs. So each row gets a slightly different timestamp, even if they're being modified concurrently by the one `UPDATE`. This behavior, in turn, means that the effects of concurrent changes might get "mixed" in various ways, depending on how the changes performed on different nodes interleaves.

Another possible issue is clock skew. When the clocks on different nodes drift, the timestamps generated by those nodes also drift. This clock skew can induce unexpected behavior such as newer changes being discarded because the timestamps are apparently switched around. However, you can manage clock skew between nodes using the parameters bdr.maximum_clock_skew and bdr.maximum_clock_skew_action.

As the current timestamp is unrelated to the commit timestamp, using it to resolve conflicts means that the result isn't equivalent to the commit order, which means it probably can't be serialized.

When using current timestamps to order changes or commits, the conflicting changes might have exactly the same timestamp because two or more nodes happened to generate the same timestamp. This risk isn't unique to column-level conflict resolution, as it can happen even for regular row-level conflict resolution. The node id is used as the tiebreaker in this situation. The higher node id wins. This approach ensures that the same changes are applied on all nodes.

`column_commit_timestamp`

You can also use the actual commit timestamp specified with `column_commit_timestamp` as the conflict detection method. This approach has the advantage of using the commit time, which is the same for all changes made in an `UPDATE`.

> **Note**
>
> Statement transactions might be added in the future, which will address issues with mixing effects of concurrent statements or transactions. Still, neither of these options can ever produce results equivalent to commit order.

Inspecting column timestamps

The column storing timestamps for modified columns is maintained by triggers. Don't modify it directly. It can be useful to inspect the current timestamp's value, for example, while investigating how a conflict was resolved.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Note**
>
> The timestamp mapping is maintained by triggers, and the order in which triggers execute matters. If your custom triggers modify tuples and are executed after the pgl_clcd_ triggers, the modified columns aren't detected correctly. This can lead to incorrect conflict resolution. If you need to modify tuples in your triggers, make sure they're executed before the pgl_clcd_ triggers.

The following functions are useful for inspecting timestamps.

`bdr.column_timestamps_to_text(bdr.column_timestamps)`

This function returns a human-readable representation of the timestamp mapping and is used when casting the value to text:

```
db=# select cts::text from
test_table;

cts
-----------------------------------------------------------------------------------------------------
 {source: current, default: 2018-09-23 19:24:52.118583+02, map: [2 : 2018-09-23
19:25:02.590677+02]}
(1 row)
```

`bdr.column_timestamps_to_jsonb(bdr.column_timestamps)`

This function turns a JSONB representation of the timestamps mapping and is used when casting the value to jsonb:

```
db=# select jsonb_pretty(cts::jsonb) from
test_table;
                   jsonb_pretty
-------------------------------------------------
 {
+
     "map": {
+
         "2": "2018-09-23T19:24:52.118583+02:00"  +
     },                                           +
     "source": "current",                         +
     "default": "2018-09-23T19:24:52.118583+02:00"+

}
(1 row)
```

`bdr.column_timestamps_resolve(bdr.column_timestamps, xid)`

This function updates the mapping with the commit timestamp for the attributes modified by the most recent transaction if it already committed. This matters only when using the commit timestamp. For example, in this case, the last transaction updated the second attribute (with attnum = 2):

```
test=# select cts::jsonb from
test_table;

cts
-----------------------------------------------------------------------------------------------------------------------------
-------------
 {"map": {"2": "2018-09-23T19:29:55.581823+02:00"}, "source": "commit", "default": "2018-09-23T19:29:55.581823+02:00",
"modified": [2]}
(1 row)

db=# select bdr.column_timestamps_resolve(cts, xmin)::jsonb from
test_table;
                                          column_timestamps_resolve
-----------------------------------------------------------------------------------------------------------------------------
 {"map": {"2": "2018-09-23T19:29:55.581823+02:00"}, "source": "commit", "default": "2018-09-
23T19:29:55.581823+02:00"}
(1 row)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3 Conflict-free replicated data types

Conflict-free replicated data types (CRDTs) support merging values from concurrently modified rows instead of discarding one of the rows as the traditional resolution does.

- Overview provides an introduction to CRDTs, including how to use CRDTs in tables, configuration options, and examples of CRDTs.
- Using CRDTs investigates how to use CRDTs in tables, reviews some configuration options, and reviews some examples of CRDTs and how they work.
- Operation-based and state-based CRDTs reviews the differences between operation-based and state-based CRDTs.
- Disk-space requirements covers disk-size considerations for CRDTs, especially state-based CRDTs.
- CRDTs vs conflict handling/reporting explains how conflict handling and reporting works with CRDTs.
- Resetting CRDT values discusses the challenges of resetting CRDT values and provides some guidance on doing so successfully.
- Implemented CRDTs details each of the 6 available CRDTs available in PGD, with implementation examples.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3.1 CRDTs Overview

Introduction to CRDTs

Conflict-free replicated data types (CRDTs) support merging values from concurrently modified rows instead of discarding one of the rows as the traditional resolution does.

Each CRDT type is implemented as a separate PostgreSQL data type with an extra callback added to the `bdr.crdt_handlers` catalog. The merge process happens inside the PGD writer on the apply side without any user action needed.

CRDTs require the table to have column-level conflict resolution enabled, as described inColumn-level conflict resolution.

CRDTs in PostgreSQL

The CRDTs are installed as part of `bdr` into the `bdr` schema. For convenience, the basic operators (`+` , `#` and `!`) and a number of common aggregate functions (`min` , `max` , `sum` , and `avg`) are created in `pg_catalog` . Thus they are available without having to tweak `search_path` .

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3.2 Using CRDTs

Using CRDTs in tables

> **Permissions required**
>
> PGD CRDTs requires usage access to CRDT types. Therefore, any user needing to access CRDT types must have at least the bdr_application role assigned to them.

To use CRDTs, you need to use a particular data type in CREATE/ALTER TABLE rather than standard built-in data types such as `integer`. For example, consider the following table with one regular integer counter and a single row:

Non-CRDT example

```
CREATE TABLE non_crdt_example
(
    id      integer             PRIMARY KEY,
    counter integer             NOT NULL DEFAULT 0
);

INSERT INTO non_crdt_example (id) VALUES
(1);
```

Suppose you issue the following SQL on two different nodes at same time:

```
UPDATE
non_crdt_example
   SET counter = counter + 1    -- "reflexive"
update
 WHERE id = 1;
```

After both updates are applied, you can see the resulting values using this query:

```
SELECT * FROM non_crdt_example WHERE id =
1;
   id |
counter
 -----+-----------
    1 |
1
(1 row)
```

This code shows that you lost one of the increments due to the `update_if_newer` conflict resolver.

CRDT example

To use a CRDT counter data type instead, you would follow these steps:

Create the table but with a CRDT (`bdr.crdt_gcounter`) as the counters data type.

```
CREATE TABLE crdt_example
(
    id      integer             PRIMARY KEY,
    counter bdr.crdt_gcounter   NOT NULL DEFAULT 0
);
```

Configure the table for column-level conflict resolution:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
ALTER TABLE crdt_example REPLICA IDENTITY
FULL;

SELECT bdr.alter_table_conflict_detection('crdt_example',
            'column_modify_timestamp', 'cts');
```

And then insert a row with a value for this example.

```
INSERT INTO crdt_example (id) VALUES (1);
```

If you now issue, as before, the same SQL on two nodes at same time.

```
UPDATE crdt_example
   SET counter = counter + 1    -- "reflexive"
update
 WHERE id = 1;
```

Once the changes are applied, you find that the counter has managed to concurrenct updates.

```
SELECT id, counter FROM crdt_example WHERE id = 1;
   id |
counter
 -----+-----------
    1 |
2
(1 row)
```

This example shows that the CRDT correctly allows the accumulator columns to work, even in the face of asynchronous concurrent updates that otherwise conflict.

Configuration options

The `bdr.crdt_raw_value` configuration option determines whether queries return the current value or the full internal state of the CRDT type. By default, only the current numeric value is returned. When set to `true`, queries return representation of the full state. You can use the special hash operator (`#`) to request only the current numeric value without using the special operator (the default behavior). If the full state is dumped using `bdr.crdt_raw_value = on`, then the value can reload only with `bdr.crdt_raw_value = on`.

> **Note**
>
> The `bdr.crdt_raw_value` applies formatting only of data returned to clients, that is, simple column references in the select list. Any column references in other parts of the query (such as `WHERE` clause or even expressions in the select list) might still require use of the `#` operator.

Different types of CRDTs

The `crdt_gcounter` type is an example of state-based CRDT types that work only with reflexive UPDATE SQL, such as `x = x + 1`, as the example shows.

Another class of CRDTs are *delta CRDT* types. These are a special subclass of operation-based CRDT.

With delta CRDTs, any update to a value is compared to the previous value on the same node. Then a change is applied as a delta on all other nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE crdt_delta_example
(
    id       integer            PRIMARY KEY,
    counter  bdr.crdt_delta_counter NOT NULL DEFAULT 0
);

ALTER TABLE crdt_delta_example REPLICA IDENTITY
FULL;

SELECT bdr.alter_table_conflict_detection('crdt_delta_example',
            'column_modify_timestamp', 'cts');

INSERT INTO crdt_delta_example (id) VALUES
(1);
```

Suppose you issue the following SQL on two nodes at same time:

```
UPDATE crdt_delta_example
   SET counter = 2          -- notice NOT counter = counter +
2
 WHERE id = 1;
```

After both updates are applied, you can see the resulting values using this query:

```
SELECT id, counter FROM crdt_delta_example WHERE id = 1;
   id |
counter
 -----+---------
    1 |
4
(1 row)
```

With a regular `integer` column, the result is `2`. But when you update the row with a delta CRDT counter, you start with the OLD row version, make a NEW row version, and send both to the remote node. There, compare them with the version found there (e.g., the LOCAL version). Standard CRDTs merge the NEW and the LOCAL version, while delta CRDTs compare the OLD and NEW versions and apply the delta to the LOCAL version.

Query planning and optimization

An important question is how query planning and optimization works with these new data types. CRDT types are handled transparently. Both `ANALYZE` and the optimizer work, so estimation and query planning works fine without having to do anything else.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3.3 Operation-based and state-based CRDTs

Operation-based CRDT types (CmCRDT)

The implementation of operation-based types is trivial because the operation isn't transferred explicitly but computed from the old and new row received from the remote node.

Currently, these operation-based CRDTs are implemented:

- `crdt_delta_counter` — `bigint` counter (increments/decrements)
- `crdt_delta_sum` — `numeric` sum (increments/decrements)

These types leverage existing data types with a little bit of code to compute the delta. For example, `crdt_delta_counter` is a domain on a `bigint`.

This approach is possible only for types for which the method for computing the delta is known, but the result is simple and cheap (both in terms of space and CPU) and has a couple of added benefits. For example, it can leverage operators/syntax for the underlying data type.

The main disadvantage is that you can't reset this value reliably in an asynchronous and concurrent environment.

> **Note**
>
> Implementing more complicated operation-based types by creating custom data types is possible, storing the state and the last operation. (Every change is decoded and transferred, so multiple operations aren't needed). But at that point, the main benefits (simplicity, reuse of existing data types) are lost without gaining any advantage compared to state-based types (for example, still no capability to reset) except for the space requirements. (A per-node state isn't needed.)

State-based CRDT types (CvCRDT)

State-based types require a more complex internal state and so can't use the regular data types directly the way operation-based types do.

Currently, four state-based CRDTs are implemented:

- `crdt_gcounter` — `bigint` counter (increment-only)
- `crdt_gsum` — `numeric` sum/counter (increment-only)
- `crdt_pncounter` — `bigint` counter (increments/decrements)
- `crdt_pnsum` — `numeric` sum/counter (increments/decrements)

The internal state typically includes per-node information, increasing the on-disk size but allowing added benefits. The need to implement custom data types implies more code (in/out functions and operators).

The advantage is the ability to reliably reset the values, a somewhat self-healing nature in the presence of lost changes (which doesn't happen in a cluster that operates properly), and the ability to receive changes from other than source nodes.

Consider, for example, that a value is modified on node A, and the change gets replicated to B but not C due to network issue between A and C. If B modifies the value and this change gets replicated to C, it includes even the original change from A. With operation-based CRDTs, node C doesn't receive the change until the A-C network connection starts working again.

The main disadvantages of CvCRDTs are higher costs in terms of disk space and CPU usage. A bit of information for each node is needed, including nodes that were already removed from the cluster. The complex nature of the state (serialized into varlena types) means increased CPU use.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3.4 CRDT Disk-space requirements

An important consideration is the overhead associated with CRDT types, particularly the on-disk size.

Operation-based CRDT disk-space reqs

For operation-based types, this is trivial because the types are merely domains on top of other types. They have the same disk space requirements no matter how many nodes are there:

- `crdt_delta_counter` — Same as `bigint` (8 bytes)
- `crdt_delta_sum` — Same as `numeric` (variable, depending on precision and scale)

There's no dependency on the number of nodes because operation-based CRDT types don't store any per-node information.

State-based CRDT disk-space reqs

For state-based types, the situation is more complicated. All the types are variable length (stored essentially as a `bytea` column) and consist of a header and a certain amount of per-node information for each node that modified the value.

For the `bigint` variants, formulas computing approximate size are:

- `crdt_gcounter` — `32B (header) + N * 12B (per-node)`
- `crdt_pncounter` -— `48B (header) + N * 20B (per-node)`

  `N` denotes the number of nodes that modified this value.

For the `numeric` variants, there's no exact formula because both the header and per-node parts include `numeric` variable-length values. To give you an idea of how many such values you need to keep:

- `crdt_gsum`
  - fixed: `20B (header) + N * 4B (per-node)`
  - variable: `(2 + N)` `numeric` values
- `crdt_pnsum`
  - fixed: `20B (header) + N * 4B (per-node)`
  - variable: `(4 + 2 * N)` `numeric` values

> **Note**
>
> It doesn't matter how many nodes are in the cluster if the values are never updated on multiple nodes. It also doesn't matter whether the updates were concurrent (causing a conflict).
>
> In addition, it doesn't matter how many of those nodes were already removed from the cluster. There's no way to compact the state yet.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3.5 CRDTs vs conflict handling/reporting

CRDT types versus conflicts handling

As tables can contain both CRDT and non-CRDT columns (most columns are expected to be non-CRDT), you need to do both the regular conflict resolution and CRDT merge.

The conflict resolution happens first and is responsible for deciding the tuple to keep (applytuple) and the one to discard. The merge phase happens next, merging data for CRDT columns from the discarded tuple into the applytuple.

> **Note**
>
> This handling makes CRDT types somewhat more expensive compared to plain conflict resolution because the merge needs to happen every time. This is the case even when the conflict resolution can use one of the fast paths (such as those modified in the current transaction).

CRDT types versus conflict reporting

By default, detected conflicts are individually reported. Without CRDT types, this makes sense because the conflict resolution essentially throws away half of the available information (local or remote row, depending on configuration). This presents a data loss.

CRDT types allow both parts of the information to be combined without throwing anything away, eliminating the data loss issue. This approach makes the conflict reporting unnecessary.

For this reason, conflict reporting is skipped when the conflict can be fully resolved by CRDT merge. Each column must meet at least one of these two conditions:

- The values in local and remote tuple are the same (NULL or equal).
- It uses a CRDT data type and so can be merged.

> **Note**
>
> Conflict reporting is also skipped when there are no CRDT columns but all values in local/remote tuples are equal.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3.6 Resetting CRDT values

Resetting CRDT values is possible but requires special handling. The asynchronous nature of the cluster means that different nodes might see the reset operation at different places in the change stream no matter how it's implemented. Different nodes might also initiate a reset concurrently, that is, before observing the reset from the other node.

In other words, to make the reset operation behave correctly, it needs to be commutative with respect to the regular operations. Many naive ways to reset a value that might work well on a single-node fail for this reason.

Challenges when resetting CRDT values

For example, the simplest approach to resetting a value might be:

```
UPDATE crdt_table SET cnt = 0 WHERE id = 1;
```

With state-based CRDTs this doesn't work. It throws away the state for the other nodes but only locally. It's added back by merge functions on remote nodes, causing diverging values and eventually receiving it back due to changes on the other nodes.

With operation-based CRDTs, this might seem to work because the update is interpreted as a subtraction of `-cnt`. But it works only in the absence of concurrent resets. Once two nodes attempt to do a reset at the same time, the delta is applied twice, getting a negative value (which isn't expected from a reset).

It might also seem that you can use `DELETE + INSERT` as a reset, but this approach has a couple of weaknesses, too. If the row is reinserted with the same key, it's not guaranteed that all nodes see it at the same position in the stream of operations with respect to changes from other nodes. PGD specifically discourages reusing the same primary key value since it can lead to data anomalies in concurrent cases.

How to reliably handle resetting CRDT values

State-based CRDT types can reliably handle resets using a special `!` operator like this:

```
UPDATE tab SET counter = !counter WHERE ...;
```

"Reliably" means the values don't have the two issues of multiple concurrent resets and divergence.

Operation-based CRDT types can be reset reliably only usingEager Replication, since this avoids multiple concurrent resets. You can also use Eager Replication to set either kind of CRDT to a specific value.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

26.3.7 Implemented CRDTs

Currently, six CRDT data types are implemented:

- Grow-only counter and sum
- Positive-negative counter and sum
- Delta counter and sum

The counters and sums behave mostly the same, except that the counter types are integer based (`bigint`), while the sum types are decimal-based (`numeric`).

You can list the currently implemented CRDT data types with the following query:

```
SELECT n.nspname, t.typname
FROM bdr.crdt_handlers
c
JOIN (pg_type t JOIN pg_namespace n ON t.typnamespace =
n.oid)
  ON t.oid = c.crdt_type_id;
```

Grow-only counter (`crdt_gcounter`)

- Supports only increments with nonnegative values (`value + int` and `counter + bigint` operators).
- You can obtain the current value of the counter either using `#` operator or by casting it to `bigint` .
- Isn't compatible with simple assignments like `counter = value` (which is common pattern when the new value is computed somewhere in the application).
- Allows simple reset of the counter using the `!` operator (`counter = !counter`).
- You can inspect the internal state using `crdt_gcounter_to_text` .

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE crdt_test
(
    id       INT PRIMARY KEY,
    cnt      bdr.crdt_gcounter NOT NULL DEFAULT
0
);

INSERT INTO crdt_test VALUES (1, 0);      -- initialized to
0
INSERT INTO crdt_test VALUES (2, 129824); -- initialized to
129824
INSERT INTO crdt_test VALUES (3, -4531);  -- error: negative
value

-- enable CLCD on the
table
ALTER TABLE crdt_test REPLICA IDENTITY
FULL;
SELECT bdr.alter_table_conflict_detection('crdt_test', 'column_modify_timestamp', 'cts');

-- increment
counters
UPDATE crdt_test SET cnt = cnt + 1 WHERE id =
1;
UPDATE crdt_test SET cnt = cnt + 120 WHERE id =
2;

-- error: minus operator not
defined
UPDATE crdt_test SET cnt = cnt - 1 WHERE id =
1;

-- error: increment has to be non-
negative
UPDATE crdt_test SET cnt = cnt + (-1) WHERE id =
1;

-- reset counter
UPDATE crdt_test SET cnt = !cnt WHERE id =
1;

-- get current counter
value
SELECT id, cnt::bigint, cnt FROM
crdt_test;

-- show internal structure of
counters
SELECT id, bdr.crdt_gcounter_to_text(cnt) FROM crdt_test;
```

Grow-only sum (`crdt_gsum`)

- Supports only increments with nonnegative values (`sum + numeric`).
- You can obtain the current value of the sum either by using the `#` operator or by casting it to `numeric` .
- Isn't compatible with simple assignments like `sum = value` , which is the common pattern when the new value is computed somewhere in the application.
- Allows simple reset of the sum using the `!` operator (`sum = !sum`).
- Can inspect internal state using `crdt_gsum_to_text` .

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE crdt_test
(
    id       INT PRIMARY KEY,
    gsum     bdr.crdt_gsum NOT NULL DEFAULT 0.0
);

INSERT INTO crdt_test VALUES (1, 0.0);      -- initialized to
0
INSERT INTO crdt_test VALUES (2, 1298.24); -- initialized to
1298.24
INSERT INTO crdt_test VALUES (3, -45.31);  -- error: negative
value

-- enable CLCD on the
table
ALTER TABLE crdt_test REPLICA IDENTITY
FULL;
SELECT bdr.alter_table_conflict_detection('crdt_test', 'column_modify_timestamp', 'cts');

-- increment
sum
UPDATE crdt_test SET gsum = gsum + 11.5 WHERE id = 1;
UPDATE crdt_test SET gsum = gsum + 120.33 WHERE id = 2;

-- error: minus operator not
defined
UPDATE crdt_test SET gsum = gsum - 15.2 WHERE id = 1;

-- error: increment has to be non-
negative
UPDATE crdt_test SET gsum = gsum + (-1.56) WHERE id =
1;

-- reset
sum
UPDATE crdt_test SET gsum = !gsum WHERE id = 1;

-- get current sum
value
SELECT id, gsum::numeric, gsum FROM crdt_test;

-- show internal structure of
sums
SELECT id, bdr.crdt_gsum_to_text(gsum) FROM crdt_test;
```

Positive-negative counter (`crdt_pncounter`)

- Supports increments with both positive and negative values (through `counter + int` and `counter + bigint` operators).
- You can obtain the current value of the counter either by using the `#` operator or by casting to `bigint` .
- Isn't compatible with simple assignments like `counter = value` , which is the common pattern when the new value is computed somewhere in the application.
- Allows simple reset of the counter using the `!` operator (`counter = !counter`).
- You can inspect the internal state using `crdt_pncounter_to_text` .

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE crdt_test
(
    id       INT PRIMARY KEY,
    cnt      bdr.crdt_pncounter NOT NULL DEFAULT
0
);

INSERT INTO crdt_test VALUES (1, 0);      -- initialized to
0
INSERT INTO crdt_test VALUES (2, 129824); -- initialized to
129824
INSERT INTO crdt_test VALUES (3, -4531);  -- initialized to -
4531

-- enable CLCD on the
table
ALTER TABLE crdt_test REPLICA IDENTITY
FULL;
SELECT bdr.alter_table_conflict_detection('crdt_test', 'column_modify_timestamp', 'cts');

-- increment
counters
UPDATE crdt_test SET cnt = cnt + 1      WHERE id =
1;
UPDATE crdt_test SET cnt = cnt + 120    WHERE id =
2;
UPDATE crdt_test SET cnt = cnt + (-244) WHERE id =
3;

-- decrement
counters
UPDATE crdt_test SET cnt = cnt - 73    WHERE id =
1;
UPDATE crdt_test SET cnt = cnt - 19283 WHERE id =
2;
UPDATE crdt_test SET cnt = cnt - (-12) WHERE id =
3;

-- get current counter
value
SELECT id, cnt::bigint, cnt FROM
crdt_test;

-- show internal structure of
counters
SELECT id, bdr.crdt_pncounter_to_text(cnt) FROM
crdt_test;

-- reset counter
UPDATE crdt_test SET cnt = !cnt WHERE id =
1;

-- get current counter value after the
reset
SELECT id, cnt::bigint, cnt FROM
crdt_test;
```

Positive-negative sum (`crdt_pnsum`)

- Supports increments with both positive and negative values through `sum + numeric` .
- You can obtain the current value of the sum either by using then `#` operator or by casting to `numeric` .
- Isn't compatible with simple assignments like `sum = value` , which is the common pattern when the new value is computed somewhere in the application.
- Allows simple reset of the sum using the `!` operator (`sum = !sum`).
- You can inspect the internal state using `crdt_pnsum_to_text` .

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE crdt_test
(
    id       INT PRIMARY KEY,
    pnsum    bdr.crdt_pnsum NOT NULL DEFAULT
0
);

INSERT INTO crdt_test VALUES (1, 0);       -- initialized to
0
INSERT INTO crdt_test VALUES (2, 1298.24); -- initialized to
1298.24
INSERT INTO crdt_test VALUES (3, -45.31);  -- initialized to -
45.31

-- enable CLCD on the
table
ALTER TABLE crdt_test REPLICA IDENTITY
FULL;
SELECT bdr.alter_table_conflict_detection('crdt_test', 'column_modify_timestamp', 'cts');

-- increment sums
UPDATE crdt_test SET pnsum = pnsum + 1.44     WHERE id = 1;
UPDATE crdt_test SET pnsum = pnsum + 12.20    WHERE id = 2;
UPDATE crdt_test SET pnsum = pnsum + (-24.34) WHERE id =
3;

-- decrement sums
UPDATE crdt_test SET pnsum = pnsum - 7.3      WHERE id = 1;
UPDATE crdt_test SET pnsum = pnsum - 192.83   WHERE id = 2;
UPDATE crdt_test SET pnsum = pnsum - (-12.22) WHERE id =
3;

-- get current sum
value
SELECT id, pnsum::numeric, pnsum FROM
crdt_test;

-- show internal structure of
sum
SELECT id, bdr.crdt_pnsum_to_text(pnsum) FROM
crdt_test;

-- reset
sum
UPDATE crdt_test SET pnsum = !pnsum WHERE id =
1;

-- get current sum value after the
reset
SELECT id, pnsum::numeric, pnsum FROM
crdt_test;
```

Delta counter (`crdt_delta_counter`)

- Is defined a `bigint` domain, so works exactly like a `bigint` column.
- Supports increments with both positive and negative values.
- Is compatible with simple assignments like `counter = value`, which is common when the new value is computed somewhere in the application.
- There's no simple way to reset the value reliably.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE crdt_test
(
    id       INT PRIMARY KEY,
    cnt      bdr.crdt_delta_counter NOT NULL DEFAULT
0
);

INSERT INTO crdt_test VALUES (1, 0);      -- initialized to
0
INSERT INTO crdt_test VALUES (2, 129824); -- initialized to
129824
INSERT INTO crdt_test VALUES (3, -4531);  -- initialized to -
4531

-- enable CLCD on the
table
ALTER TABLE crdt_test REPLICA IDENTITY
FULL;
SELECT bdr.alter_table_conflict_detection('crdt_test', 'column_modify_timestamp', 'cts');

-- increment
counters
UPDATE crdt_test SET cnt = cnt + 1      WHERE id =
1;
UPDATE crdt_test SET cnt = cnt + 120    WHERE id =
2;
UPDATE crdt_test SET cnt = cnt + (-244) WHERE id =
3;

-- decrement
counters
UPDATE crdt_test SET cnt = cnt - 73    WHERE id =
1;
UPDATE crdt_test SET cnt = cnt - 19283 WHERE id =
2;
UPDATE crdt_test SET cnt = cnt - (-12) WHERE id =
3;

-- get current counter
value
SELECT id, cnt FROM
crdt_test;
```

Delta sum (`crdt_delta_sum`)

- Is defined as a `numeric` domain so works exactly like a `numeric` column.
- Supports increments with both positive and negative values.
- Is compatible with simple assignments like `sum = value`, which is common when the new value is computed somewhere in the application.
- There's no simple way to reset the value reliably.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE crdt_test
(
    id       INT PRIMARY KEY,
    dsum     bdr.crdt_delta_sum NOT NULL DEFAULT 0
);

INSERT INTO crdt_test VALUES (1, 0);       -- initialized to
0
INSERT INTO crdt_test VALUES (2, 129.824); -- initialized to
129824
INSERT INTO crdt_test VALUES (3, -4.531);  -- initialized to -
4531

-- enable CLCD on the
table
ALTER TABLE crdt_test REPLICA IDENTITY
FULL;
SELECT bdr.alter_table_conflict_detection('crdt_test', 'column_modify_timestamp', 'cts');

-- increment
counters
UPDATE crdt_test SET dsum = dsum + 1.32   WHERE id = 1;
UPDATE crdt_test SET dsum = dsum + 12.01  WHERE id = 2;
UPDATE crdt_test SET dsum = dsum + (-2.4) WHERE id =
3;

-- decrement
counters
UPDATE crdt_test SET dsum = dsum - 7.33   WHERE id = 1;
UPDATE crdt_test SET dsum = dsum - 19.83  WHERE id = 2;
UPDATE crdt_test SET dsum = dsum - (-1.2) WHERE id =
3;

-- get current counter
value
SELECT id, cnt FROM
crdt_test;
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

27 Parallel Apply

What is Parallel Apply?

Parallel Apply is a feature of PGD that allows a PGD node to use multiple writers per subscription. This behavior generally increases the throughput of a subscription and improves replication performance.

Configuring Parallel Apply

Two variables control Parallel Apply in PGD 5: `bdr.max_writers_per_subscription` (defaults to 8) and `bdr.writers_per_subscription` (defaults to 2).

```
bdr.max_writers_per_subscription = 8
bdr.writers_per_subscription = 2
```

This configuration gives each subscription two writers. However, in some circumstances, the system might allocate up to eight writers for a subscription.

Changing `bdr.max_writers_per_subscription` requires a server restart to take effect.

You can change `bdr.writers_per_subscription` for a specific subscription without a restart by:

1. Halting the subscription using `bdr.alter_subscription_disable`.
2. Setting the new value.
3. Resuming the subscription using `bdr.alter_subscription_enable`.

First though, establish the name of the subscription using `select * from bdr.subscription`. For this example, the subscription name is `bdr_bdrdb_bdrgroup_node2_node1`.

```
SELECT bdr.alter_subscription_disable
('bdr_bdrdb_bdrgroup_node2_node1');

UPDATE
bdr.subscription
SET num_writers =
4
WHERE sub_name =
'bdr_bdrdb_bdrgroup_node2_node1';

SELECT bdr.alter_subscription_enable
('bdr_bdrdb_bdrgroup_node2_node1');
```

When to use Parallel Apply

Parallel Apply is always on by default and, for most operations, we recommend leaving it on.

Monitoring Parallel Apply

To support Parallel Apply's deadlock mitigation, PGD 5.2 adds columns to `bdr.stat_subscription`. The new columns are `nprovisional_waits`, `ntuple_waits`, and `ncommmit_waits`. These are metrics that indicate how well Parallel Apply is managing what previously would have been deadlocks. They don't reflect overall system performance.

The `nprovisional_waits` value reflects the number of operations on the same tuples being performed by concurrent apply transactions. These are provisional waits that aren't actually waiting yet but could start waiting.

If a tuple's write needs to wait until it can be safely applied, it's counted in `ntuple_waits`. Fully applied transactions that waited before being committed are counted in `ncommit_waits`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Disabling Parallel Apply

To disable Parallel Apply, set `bdr.writers_per_subscription` to `1`.

Deadlock mitigation

When Parallel Apply is operating, the transactional changes from the subscription are written by multiple writers. However, each writer ensures that the final commit of its transaction doesn't violate the commit order as executed on the origin node. If there's a violation, an error is generated and the transaction can be rolled back.

This mechanism previously meant that when the following are all true, the resulting error could manifest as a deadlock:

- A transaction is pending commit and modifies a row that another transaction needs to change.
- That other transaction executed on the origin node before the pending transaction did.
- The pending transaction took out a lock request.

Additionally, handling the error could increase replication lag due to a combination of the time taken:

- To detect the deadlock
- For the client to roll back its transaction
- For indirect garbage collection of the changes that were already applied
- To redo the work

This is where Parallel Apply's deadlock mitigation, introduced in PGD 5.2, can help. For any transaction, Parallel Apply looks at transactions already scheduled for any row (tuple) that the current transaction wants to write. If it finds one, the row is marked as needing to wait until the other transaction is committed before applying its change to the row. This approach ensures that rows are written in the correct order.

Parallel Apply support

Up to and including PGD 5.1, don't use Parallel Apply with Group Commit, CAMO, and Eager Replication. Disable Parallel Apply in these scenarios. If, using PGD 5.1 or earlier, you're experiencing a large number of deadlocks, you might also want to disable Parallel Apply or consider upgrading.

From PGD 5.2, Parallel Apply works with CAMO. It isn't compatible with Group Commit or Eager Replication, so disable it if Group Commit or Eager Replication are in use.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

28 Replication sets

A replication set is a group of tables that a PGD node can subscribe to. You can use replication sets to create more complex replication topologies than regular symmetric multi-master topologies where each node is an exact copy of the other nodes.

Every PGD group creates a replication set with the same name as the group. This replication set is the default replication set, which is used for all user tables and DDL replication. All nodes are subscribed to it. In other words, by default, all user tables are replicated between all nodes.

Using replication sets

You can create replication sets using `bdr.create_replication_set`, specifying whether to include insert, update, delete, or truncate actions. One option lets you add existing tables to the set, and a second option defines whether to add tables when they're created.

You can also manually define the tables to add or remove from a replication set.

Tables included in the replication set are maintained when the node joins the cluster and afterwards.

Once the node is joined, you can still remove tables from the replication set, but you must add new tables using a resync operation.

By default, a newly defined replication set doesn't replicate DDL or PGD administration function calls. Use `bdr.replication_set_add_ddl_filter` to define the commands to replicate.

PGD creates replication set definitions on all nodes. Each node can then be defined to publish or subscribe to each replication set using `bdr.alter_node_replication_sets`.

You can use functions to alter these definitions later or to drop the replication set.

> **Note**
>
> Don't use the default replication set for selective replication. Don't drop or modify the default replication set on any of the PGD nodes in the cluster, as it's also used by default for DDL replication and administration function calls.

Behavior of partitioned tables

PGD supports partitioned tables transparently, meaning that you can add a partitioned table to a replication set.

Changes that involve any of the partitions are replicated downstream.

> **Note**
>
> When partitions are replicated through a partitioned table, the statements executed directly on a partition are replicated as they were executed on the parent table. The exception is the `TRUNCATE` command, which always replicates with the list of affected tables or partitions.

You can add individual partitions to the replication set, in which case they're replicated like regular tables, that is, to the table of the same name as the partition on the downstream. This behavior has some performance advantages if the partitioning definition is the same on both provider and subscriber, as the partitioning logic doesn't have to be executed.

> **Note**
>
> If a root partitioned table is part of any replication set, memberships of individual partitions are ignored. Only the membership of that root table is taken into account.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Behavior with foreign keys

A foreign-key constraint ensures that each row in the referencing table matches a row in the referenced table. Therefore, if the referencing table is a member of a replication set, the referenced table must also be a member of the same replication set.

The current version of PGD doesn't check for or enforce this condition. When adding a table to a replication set, the database administrator must make sure that all the tables referenced by foreign keys are also added.

You can use the following query to list all the foreign keys and replication sets that don't satisfy this requirement. The referencing table is a member of the replication set, while the referenced table isn't.

```
SELECT
t1.relname,

t1.nspname,

fk.conname,

t1.set_name
  FROM bdr.tables AS t1
  JOIN pg_catalog.pg_constraint AS
fk
    ON fk.conrelid =
t1.relid
   AND fk.contype = 'f'
 WHERE NOT EXISTS
(
  SELECT *
    FROM bdr.tables AS t2
   WHERE t2.relid =
fk.confrelid
     AND t2.set_name =
t1.set_name
);
```

The output of this query looks like this:

```
 relname | nspname |  conname  |
set_name
---------+---------+-----------+----------
 t2      | public  | t2_x_fkey |
s2
(1 row)
```

This output means that table `t2` is a member of replication set `s2`, but the table referenced by the foreign key `t2_x_fkey` isn't.

The `TRUNCATE CASCADE` command takes into account the replication set membership before replicating the command. For example:

```
TRUNCATE table1
CASCADE;
```

This becomes a `TRUNCATE` without cascade on all the tables that are part of the replication set only:

```
TRUNCATE table1, referencing_table1, referencing_table2
...
```

Replication set membership

You can add tables to or remove them from one or more replication sets. Doing so affects replication only of changes (DML) in those tables. Schema changes (DDL) are handled by DDL replication set filters (see DDL replication filtering).

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

The replication uses the table membership in replication sets with the node replication sets configuration to determine the actions to replicate and the node to replicate them to. The decision is done using the union of all the memberships and replication set options. Suppose that a table is a member of replication set A that replicates only INSERT actions and replication set B that replicates only UPDATE actions. Both INSERT and UPDATE actions are replicated if the target node is also subscribed to both replication set A and B.

You can control membership using `bdr.replication_set_add_table` and `bdr.replication_set_remove_table`.

Listing replication sets

You can list existing replication sets with the following query:

```
SELECT
set_name
FROM
bdr.replication_sets;
```

You can use this query to list all the tables in a given replication set:

```
SELECT nspname,
relname
FROM bdr.tables
WHERE set_name =
'myrepset';
```

Behavior with foreign keys shows a query that lists all the foreign keys whose referenced table isn't included in the same replication set as the referencing table.

Use the following SQL to show those replication sets that the current node publishes and subscribes from:

```
 SELECT
node_id,
        node_name,
        pub_repsets,

sub_repsets
   FROM bdr.local_node_summary;
```

This code produces output like this:

```
  node_id   | node_name |    pub_repsets     |
sub_repsets
------------+-----------+------------------------------------
 1834550102 | s01db01   | {bdrglobal,bdrs01} |
{bdrglobal,bdrs01}
(1 row)
```

To execute the same query against all nodes in the cluster, you can use the following query. This approach gets the replication sets associated with all nodes at the same time.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
WITH node_repsets AS
(
  SELECT
jsonb_array_elements(
    bdr.run_on_all_nodes($$
        SELECT

node_id,
          node_name,
          pub_repsets,

sub_repsets
        FROM bdr.local_node_summary;
    $$)::jsonb
  ) AS
j
)
SELECT j->'response'->'command_tuples'->0->>'node_id' AS
node_id,
       j->'response'->'command_tuples'->0->>'node_name' AS
node_name,
       j->'response'->'command_tuples'->0->>'pub_repsets' AS
pub_repsets,
       j->'response'->'command_tuples'->0->>'sub_repsets' AS
sub_repsets
FROM node_repsets;
```

This shows, for example:

```
  node_id   | node_name |    pub_repsets     |
sub_repsets
------------+-----------+--------------------------------------
 933864801  | s02db01   | {bdrglobal,bdrs02} |
{bdrglobal,bdrs02}
 1834550102 | s01db01   | {bdrglobal,bdrs01} |
{bdrglobal,bdrs01}
 3898940082 | s01db02   | {bdrglobal,bdrs01} |
{bdrglobal,bdrs01}
 1102086297 | s02db02   | {bdrglobal,bdrs02} |
{bdrglobal,bdrs02}
(4 rows)
```

DDL replication filtering

By default, the replication of all supported DDL happens by way of the default PGD group replication set. This replication is achieved using a DDL filter with the same name as the PGD group. This filter is added to the default PGD group replication set when the PGD group is created.

You can adjust this behavior by changing the DDL replication filters for all existing replication sets. These filters are independent of table membership in the replication sets. Just like data changes, each DDL statement is replicated only once, even if it's matched by multiple filters on multiple replication sets.

You can list existing DDL filters with the following query, which shows, for each filter, the regular expression applied to the command tag and to the role name:

```
SELECT * FROM bdr.ddl_replication;
```

You can use `bdr.replication_set_add_ddl_filter` and `bdr.replication_set_remove_ddl_filter` to manipulate DDL filters. They're considered to be `DDL` and are therefore subject to DDL replication and global locking.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Selective replication example


This example configures EDB Postgres Distributed to selectively replicate tables to particular groups of nodes.

Cluster configuration

This example assumes you have a cluster of six data nodes, `data-a1` to `data-a3` and `data-b1` to `data-b3` in two locations. The two locations they're members of are represented as `region_a` and `region_b` groups.

There's also, as we recommend, a witness node named `witness` in `region-c` that isn't mentioned in this example. The cluster is called `sere`.

This configuration looks like this:



This is the standard Always-on Multi-region configuration discussed in Choosing your architecture.

Application requirements

This example works with an application that records the opinions of people who attended performances of musical works. There's a table for attendees, a table for the works, and an opinion table. The opinion table records each work each attendee saw, where and when they saw it, and how they scored the work. Because of data regulation, the example assumes that opinion data must stay only in the region where the opinion was recorded.

Creating tables

The first step is to create appropriate tables:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE TABLE attendee
(
   id bigserial PRIMARY KEY,
   email text NOT NULL
);

CREATE TABLE work
(
    id int PRIMARY KEY,
    title text NOT NULL,
    author text NOT
NULL
);

CREATE TABLE opinion
(
    id bigserial PRIMARY KEY,
    work_id int NOT NULL REFERENCES work(id),
    attendee_id bigint NOT NULL REFERENCES
attendee(id),
    country text NOT NULL,
    day date NOT NULL,
    score int NOT NULL
);
```

Viewing groups and replication sets

By default, EDB Postgres Distributed is configured to replicate each table in its entirety to each and every node. This is managed through replication sets.

To view the initial configuration's default replication sets, run:

```
SELECT node_group_name, default_repset,
parent_group_name
FROM bdr.node_group_summary;
```

```
 node_group_name | default_repset | parent_group_name
-----------------+----------------+-------------------
 sere            | sere           |
 region_a        | region_a       | sere
 region_b        | region_b       | sere
 region_c        | region_c       | sere
```

In the output, you can see there's the top-level group, `sere`, with a default replication set named `sere`. Each of the three subgroups has a replication set with the same name as the subgroup. The `region_a` group has a `region_a` default replication set.

By default, all existing tables and new tables become members of the replication set of the top-level group.

Adding tables to replication sets

The next step is to add tables to the replication sets belonging to the groups that represent the regions. As previously mentioned, all new tables are automatically added to the `sere` replication set. You can confirm that by running:

```
SELECT relname, set_name FROM bdr.tables ORDER BY relname,
set_name;
```

```
 relname  | set_name
----------+----------
 attendee | sere
 opinion  | sere
 work     | sere
(3 rows)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

You want the `opinion` table to be replicated only in `region_a` and, separately, only in `region_b`. To do that, you add the table to the replica sets of each region:

```
SELECT bdr.replication_set_add_table('opinion', 'region_a');
SELECT bdr.replication_set_add_table('opinion', 'region_b');
```

But you're not done, because `opinion` is still a member of the `sere` replication set. When a table is a member of multiple replication sets, it's replicated in each. This doesn't affect performance, though, as each row is replicated only once on each target node. You don't want `opinion` replicated across all nodes, so you need to remove it from the top-level group's replication set:

```
SELECT bdr.replication_set_remove_table('opinion', 'sere');
```

You can now review these changes:

```
SELECT relname, set_name FROM bdr.tables ORDER BY relname,
set_name;
```

```
 relname  | set_name
----------+-------------------
 attendee | sere
 opinion  | region_a
 opinion  | region_b
 work     | sere
(4 rows)
```

This process should provide the selective replication you wanted. To verify whether it did, use the next step to test it.

Testing selective replication

First create some test data: two works and an attendee. Connect directly to `data-a1` to run this next code:

```
INSERT INTO work VALUES (1, 'Aida',
'Verdi');
INSERT INTO work VALUES (2, 'Lohengrin',
'Wagner');
INSERT INTO attendee (email) VALUES
('gv@example.com');
```

Now that there's some data in these tables, you can insert into the `opinion` table without violating foreign key constraints:

```
INSERT INTO opinion (work_id, attendee_id, country, day,
score)
SELECT work.id, attendee.id, 'Italy', '1871-11-19', 3
  FROM work,
attendee
 WHERE work.title = 'Lohengrin'
   AND attendee.email =
'gv@example.com';
```

Once you've done the insert, you can validate the contents of the database on the same node:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
SELECT a.email
, o.country
, o.day
, w.title
,
w.author
, o.score
FROM opinion
o
JOIN work w ON w.id =
o.work_id
JOIN attendee a ON a.id =
o.attendee_id;
```

```
    email       | country |    day     |   title   | author | score
----------------+---------+------------+-----------+--------+-------
 gv@example.com | Italy   | 1871-11-19 | Lohengrin | Wagner |     3
(1 row)
```

If you now connect to nodes `data-a2` and `data-a3` and run the same query, you get the same result. The data is being replicated in `region_a`. If you connect to `data-b1`, `data-b2`, or `data-b3`, the query returns no rows. That's because, although the `attendee` and `work` tables are populated, there's no `opinion` row to select. That, in turn, is because the replication of `opinion` on `region_a` happens only in that region.

Now connect to `data-b1` and insert an opinion there:

```
INSERT INTO attendee (email) VALUES
('fb@example.com');

INSERT INTO opinion (work_id, attendee_id, country, day,
score)
SELECT work.id, attendee.id, 'Germany', '1850-08-27', 9
  FROM work,
attendee
 WHERE work.title = 'Lohengrin'
   AND attendee.email =
'fb@example.com';
```

This opinion is replicated only on `region_b`. On `data-b1`, `data-b2`, and `data-b3`, you can run:

```
SELECT a.email
, o.country
, o.day
, w.title
,
w.author
, o.score
FROM opinion
o
JOIN work w ON w.id =
o.work_id
JOIN attendee a ON a.id =
o.attendee_id;
```

```
    email       | country |    day     |   title   | author | score
----------------+---------+------------+-----------+--------+-------
 fb@example.com | Germany | 1850-08-27 | Lohengrin | Wagner |     9
(1 row)
```

You see the same result on each of the `region_b` data nodes. Run the query on `region_a` nodes, and you don't see this particular entry.

Finally, notice that the `attendee` table is shared identically across all nodes. On any node, run the query:

```
SELECT * FROM attendee;
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
         id         |    email
--------------------+----------------
 904252679641903104 | gv@example.com
 904261037006536704 | fb@example.com
(2 rows)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

29 Stream triggers

PGD introduces new types of triggers that you can use for additional data processing on the downstream/target node:

- Conflict triggers
- Transform triggers

Together, these types of triggers are known as *stream triggers*.

> **Permissions required**
>
> Stream triggers are a PGD feature that requires permission. Any user wanting to create or drop triggers must have at least the bdr_application role assigned to them.

Stream triggers are designed to be trigger-like in syntax. They leverage the PostgreSQL BEFORE trigger architecture and are likely to have similar performance characteristics as PostgreSQL BEFORE triggers.

Multiple trigger definitions can use one trigger function, just as with normal PostgreSQL triggers. A trigger function is a program defined in this form: `CREATE FUNCTION ... RETURNS TRIGGER`. Creating the trigger doesn't require use of the `CREATE TRIGGER` command. Instead, create stream triggers using the special PGD functions `bdr.create_conflict_trigger()` and `bdr.create_transform_trigger()`.

Once created, the trigger is visible in the catalog table `pg_trigger`. The stream triggers are marked as `tgisinternal = true` and `tgenabled = 'D'` and have the name suffix '_bdrc' or '_bdrt'. The view `bdr.triggers` provides information on the triggers in relation to the table, the name of the procedure that's being executed, the event that triggers it, and the trigger type.

Stream triggers aren't enabled for normal SQL processing. Because of this, the `ALTER TABLE ... ENABLE TRIGGER` is blocked for stream triggers in both its specific name variant and the ALL variant. This mechanism prevents the trigger from executing as a normal SQL trigger.

These triggers execute on the downstream or target node. There's no option for them to execute on the origin node. However, you might want to consider the use of `row_filter` expressions on the origin.

Also, any DML that's applied while executing a stream trigger isn't replicated to other PGD nodes and doesn't trigger the execution of standard local triggers. This is intentional. You can use it, for example, to log changes or conflicts captured by a stream trigger into a table that's crash-safe and specific to that node. See Stream triggers examples for a working example.

Trigger execution during apply

Transform triggers execute first—once for each incoming change in the triggering table. These triggers fire before we attempt to locate a matching target row, allowing a very wide range of transforms to be applied efficiently and consistently.

Next, for UPDATE and DELETE changes, we locate the target row. If there's no target row, then no further processing occurs for those change types.

We then execute any normal triggers that previously were explicitly enabled as replica triggers at table level:

```
ALTER TABLE tablename
ENABLE REPLICA TRIGGER trigger_name;
```

We then decide whether a potential conflict exists. If so, we then call any conflict trigger that exists for that table.

Missing-column conflict resolution

Before transform triggers are executed, PostgreSQL tries to match the incoming tuple against the row-type of the target table.

Any column that exists on the input row but not on the target table triggers a conflict of type `target_column_missing`. Conversely, a column existing on the target table but not in the incoming row triggers a `source_column_missing` conflict. The default resolutions for those two conflict types are respectively `ignore_if_null` and `use_default_value`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

This is relevant in the context of rolling schema upgrades, for example, if the new version of the schema introduces a new column. When replicating from an old version of the schema to a new one, the source column is missing, and the `use_default_value` strategy is appropriate, as it populates the newly introduced column with the default value.

However, when replicating from a node having the new schema version to a node having the old one, the column is missing from the target table. The `ignore_if_null` resolver isn't appropriate for a rolling upgrade because it breaks replication as soon as a user inserts a tuple with a non-NULL value in the new column in any of the upgraded nodes.

In view of this example, the appropriate setting for rolling schema upgrades is to configure each node to apply the `ignore` resolver in case of a `target_column_missing` conflict.

You can do this with the following query, which you must execute separately on each node. Replace `node1` with the actual node name.

```
SELECT
bdr.alter_node_set_conflict_resolver('node1',
    'target_column_missing', 'ignore');
```

Data loss and divergence risk

Setting the conflict resolver to `ignore` can lead to data loss and cluster divergence.

Consider the following example: table `t` exists on nodes 1 and 2, but its column `col` exists only on node 1.

If the conflict resolver is set to `ignore`, then there can be rows on node 1 where `c` isn't null, for example, `(pk=1, col=100)`. That row is replicated to node 2, and the value in column `c` is discarded, for example, `(pk=1)`.

If column `c` is then added to the table on node 2, it's at first set to NULL on all existing rows, and the row considered above becomes `(pk=1, col=NULL)`. The row having `pk=1` is no longer identical on all nodes, and the cluster is therefore divergent.

The default `ignore_if_null` resolver isn't affected by this risk because any row replicated to node 2 has `col=NULL`.

Based on this example, we recommend running LiveCompare against the whole cluster at the end of a rolling schema upgrade where the `ignore` resolver was used. This practice helps to ensure that you detect and fix any divergence.

Terminology of row-types

PGD uses these row-types:

- `SOURCE_OLD` is the row before update, that is, the key.
- `SOURCE_NEW` is the new row coming from another node.
- `TARGET` is the row that exists on the node already, that is, the conflicting row.

Conflict triggers

Conflict triggers execute when a conflict is detected by PGD. They decide what happens when the conflict occurs.

- If the trigger function returns a row, the action is applied to the target.
- If the trigger function returns a NULL row, the action is skipped.

For example, if the trigger is called for a `DELETE`, the trigger returns NULL if it wants to skip the `DELETE`. If you want the `DELETE` to proceed, then return a row value: either `SOURCE_OLD` or `TARGET` works. When the conflicting operation is either `INSERT` or `UPDATE`, and the chosen resolution is to delete the conflicting row, the trigger must explicitly perform the deletion and return NULL. The trigger function can perform other SQL actions as it chooses, but those actions are only applied locally, not replicated.

When a real data conflict occurs between two or more nodes, two or more concurrent changes are occurring. When the changes are applied, the conflict resolution occurs independently on each node. This means the conflict resolution occurs once on each node and can occur with a significant time difference between them. As a result, communication between the multiple executions of the conflict trigger isn't possible. It's the responsibility of the author of the conflict trigger to ensure that the trigger gives exactly the same result for all related events. Otherwise, data divergence occurs.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Warning**
>
> - You can specify multiple conflict triggers on a single table, but they must match a distinct event. That is, each conflict must match only a single conflict trigger.
> - We don't recommend multiple triggers matching the same event on the same table. They might result in inconsistent behavior and will not be allowed in a future release.

If the same conflict trigger matches more than one event, you can use the `TG_OP` variable in the trigger to identify the operation that produced the conflict.

By default, PGD detects conflicts by observing a change of replication origin for a row. Hence, you can call a conflict trigger even when only one change is occurring. Since, in this case, there's no real conflict, this conflict detection mechanism can generate false-positive conflicts. The conflict trigger must handle all of those identically.

In some cases, timestamp conflict detection doesn't detect a conflict at all. For example, in a concurrent `UPDATE` / `DELETE` where the `DELETE` occurs just after the `UPDATE`, any nodes that see first the `UPDATE` and then the `DELETE` don't see any conflict. If no conflict is seen, the conflict trigger is never called. In the same situation but using row-version conflict detection, a conflict is seen, which a conflict trigger can then handle.

The trigger function has access to additional state information as well as the data row involved in the conflict, depending on the operation type:

- On `INSERT`, conflict triggers can access the `SOURCE_NEW` row from the source and `TARGET` row.
- On `UPDATE`, conflict triggers can access the `SOURCE_OLD` and `SOURCE_NEW` row from the source and `TARGET` row.
- On `DELETE`, conflict triggers can access the `SOURCE_OLD` row from the source and `TARGET` row.

You can use the function `bdr.trigger_get_row()` to retrieve `SOURCE_OLD`, `SOURCE_NEW`, or `TARGET` rows, if a value exists for that operation.

Changes to conflict triggers happen transactionally and are protected by global DML locks during replication of the configuration change. This behavior is similar to how some variants of `ALTER TABLE` are handled.

If primary keys are updated inside a conflict trigger, it can sometimes lead to unique constraint violations errors due to a difference in timing of execution. Hence, avoid updating primary keys in conflict triggers.

Transform triggers

These triggers are similar to conflict triggers, except they're executed for every row on the data stream against the specific table. The behavior of return values and the exposed variables is similar, but transform triggers execute before a target row is identified, so there's no `TARGET` row.

You can specify multiple transform triggers on each table in PGD. Transform triggers execute in alphabetical order.

A transform trigger can filter away rows, and it can do additional operations as needed. It can alter the values of any column or set them to `NULL`. The return value decides the next action taken:

- If the trigger function returns a row, it's applied to the target.
- If the trigger function returns a `NULL` row, there's no further action to perform. Unexecuted triggers never execute.
- The trigger function can perform other actions as it chooses.

The trigger function has access to additional state information as well as rows involved in the conflict:

- On `INSERT`, transform triggers can access the `SOURCE_NEW` row from the source.
- On `UPDATE`, transform triggers can access the `SOURCE_OLD` and `SOURCE_NEW` row from the source.
- On `DELETE`, transform triggers can access the `SOURCE_OLD` row from the source.

You can use the function `bdr.trigger_get_row()` to retrieve `SOURCE_OLD` or `SOURCE_NEW` rows. `TARGET` row isn't available, since this type of trigger executes before such a target row is identified, if any.

Transform triggers look very similar to normal BEFORE row triggers but have these important differences:

- A transform trigger gets called for every incoming change. BEFORE triggers aren't called at all for `UPDATE` and `DELETE` changes if a matching row in a table isn't found.

- Transform triggers are called before partition-table routing occurs.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- Transform triggers have access to the lookup key via `SOURCE_OLD`, which isn't available to normal SQL triggers.

Row contents

The `SOURCE_NEW`, `SOURCE_OLD`, and `TARGET` contents depend on the operation, REPLICA IDENTITY setting of a table, and the contents of the target table.

The TARGET row is available only in conflict triggers. The TARGET row contains data only if a row was found when applying `UPDATE` or `DELETE` in the target table. If the row isn't found, the TARGET is `NULL`.

Execution order

Execution order for triggers:

- Transform triggers — Execute once for each incoming row on the target.
- Normal triggers — Execute once per row.
- Conflict triggers — Execute once per row where a conflict exists.

Stream triggers examples

A conflict trigger that provides similar behavior as the `update_if_newer` conflict resolver:

```
CREATE OR REPLACE FUNCTION update_if_newer_trig_func
RETURNS TRIGGER
LANGUAGE plpgsql
AS $$
BEGIN
    IF (bdr.trigger_get_committs('TARGET')
>
        bdr.trigger_get_committs('SOURCE_NEW')) THEN
    RETURN TARGET;
    ELSIF
        RETURN SOURCE;
    END IF;
END;
$$;
```

A conflict trigger that applies a delta change on a counter column and uses SOURCE_NEW for all other columns:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE OR REPLACE FUNCTION delta_count_trg_func
RETURNS TRIGGER
LANGUAGE plpgsql
AS $$
DECLARE
    DELTA bigint;
    SOURCE_OLD record;
    SOURCE_NEW record;
    TARGET
record;
BEGIN
    SOURCE_OLD := bdr.trigger_get_row('SOURCE_OLD');
    SOURCE_NEW := bdr.trigger_get_row('SOURCE_NEW');
    TARGET :=
bdr.trigger_get_row('TARGET');

    DELTA := SOURCE_NEW.counter -
SOURCE_OLD.counter;
    SOURCE_NEW.counter = TARGET.counter +
DELTA;

    RETURN
SOURCE_NEW;
END;
$$;
```

A transform trigger that logs all changes to a log table instead of applying them:

```
CREATE OR REPLACE FUNCTION log_change
RETURNS TRIGGER
LANGUAGE plpgsql
AS $$
DECLARE
    SOURCE_NEW record;
    SOURCE_OLD record;
    COMMITTS
timestamptz;
BEGIN
    SOURCE_NEW := bdr.trigger_get_row('SOURCE_NEW');
    SOURCE_OLD := bdr.trigger_get_row('SOURCE_OLD');
    COMMITTS :=
bdr.trigger_get_committs('SOURCE_NEW');

    IF (TG_OP = 'INSERT')
THEN
        INSERT INTO log SELECT 'I', COMMITTS,
row_to_json(SOURCE_NEW);
    ELSIF (TG_OP = 'UPDATE')
THEN
        INSERT INTO log SELECT 'U', COMMITTS,
row_to_json(SOURCE_NEW);
    ELSIF (TG_OP = 'DELETE')
THEN
        INSERT INTO log SELECT 'D', COMMITTS,
row_to_json(SOURCE_OLD);
    END IF;

    RETURN NULL; -- do not apply the
change
END;
$$;
```

This example shows a conflict trigger that implements trusted-source conflict detection, also known as trusted site, preferred node, or Always Wins resolution. It uses the `bdr.trigger_get_origin_node_id()` function to provide a solution that works with three or more nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
CREATE OR REPLACE FUNCTION test_conflict_trigger()
RETURNS TRIGGER
LANGUAGE plpgsql
AS $$
DECLARE
    SOURCE  record;
    TARGET
record;

    TRUSTED_NODE    bigint;
    SOURCE_NODE
bigint;
    TARGET_NODE
bigint;
BEGIN
    TARGET :=
bdr.trigger_get_row('TARGET');
    IF (TG_OP =
'DELETE')
        SOURCE := bdr.trigger_get_row('SOURCE_OLD');
    ELSE
        SOURCE := bdr.trigger_get_row('SOURCE_NEW');
    END IF;

    TRUSTED_NODE :=
current_setting('customer.trusted_node_id');

    SOURCE_NODE :=
bdr.trigger_get_origin_node_id('SOURCE_NEW');
    TARGET_NODE :=
bdr.trigger_get_origin_node_id('TARGET');

    IF (TRUSTED_NODE = SOURCE_NODE) THEN
        RETURN SOURCE;
    ELSIF (TRUSTED_NODE = TARGET_NODE) THEN
        RETURN TARGET;
    ELSE
        RETURN NULL; -- do not apply the
change
    END IF;
END;
$$;
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

30 PGD AutoPartition

PGD AutoPartition allows you to split tables into several partitions. It lets tables grow easily to large sizes using automatic partitioning management. This capability uses features of PGD, such as low-conflict locking of creating and dropping partitions.

You can create new partitions regularly and then drop them when the data retention period expires.

You perform PGD management primarily by using functions that can be called by SQL. All functions in PGD are exposed in the `bdr` schema. Unless you put it into your search_path, you need to schema qualify the name of each function.

Auto creation of partitions

PGD AutoPartition uses the `bdr.autopartition()` function to create or alter the definition of automatic range partitioning for a table. If no definition exists, it's created. Otherwise, later executions will alter the definition.

PGD AutoPartition in PGD 5.5 and later leverages underlying Postgres features that allow a partition to be attached or detached/dropped without locking the rest of the table. Versions of PGD earlier than 5.5 don't support this feature and lock the tables.

An error is raised if the table isn't RANGE partitioned or a multi-column partition key is used.

By default, AutoPartition manages partitions globally. In other words, when a partition is created on one node, the same partition is created on all other nodes in the cluster. Using the default makes all partitions consistent and guaranteed to be available. For this capability, AutoPartition makes use of Raft.

You can change this behavior by setting `managed_locally` to `true`. In that case, all partitions are managed locally on each node. Managing partitions locally is useful when the partitioned table isn't a replicated table. In that case, you might not need or want to have all partitions on all nodes. For example, the built-in `bdr.conflict_history` table isn't a replicated table. It's managed by AutoPartition locally. Each node creates partitions for this table locally and drops them once they're old enough.

Also consider:

- You can't later change tables marked as `managed_locally` to be managed globally and vice versa.
- Activities are performed only when the entry is marked `enabled = on`.
- We recommend that you don't manually create or drop partitions for tables managed by AutoPartition. Doing so can make the AutoPartition metadata inconsistent and might cause it to fail.

AutoPartition examples

Daily partitions, keep data for one month:

```
CREATE TABLE measurement
(
logdate date not null,
peaktemp int,
unitsales int
) PARTITION BY RANGE (logdate);

bdr.autopartition('measurement', '1 day', data_retention_period := '30
days');
```

Create five advance partitions when there are only two more partitions remaining. Each partition can hold 1 billion orders.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
bdr.autopartition('Orders', '1000000000',
        partition_initial_lowerbound := '0',
        minimum_advance_partitions :=
2,
        maximum_advance_partitions :=
5
    );
```

RANGE-partitioned tables

A new partition is added for every `partition_increment` range of values. Lower and upper bound are `partition_increment` apart. For tables with a partition key of type `timestamp` or `date`, the `partition_increment` must be a valid constant of type `interval`. For example, specifying `1 Day` causes a new partition to be added each day, with partition bounds that are one day apart.

If the partition column is connected to a `snowflakeid`, `timeshard`, or `ksuuid` sequence, you must specify the `partition_increment` as type `interval`. Otherwise, if the partition key is integer or numeric, then the `partition_increment` must be a valid constant of the same datatype. For example, specifying `1000000` causes new partitions to be added every 1 million values.

If the table has no existing partition, then the specified `partition_initial_lowerbound` is used as the lower bound for the first partition. If you don't specify `partition_initial_lowerbound`, then the system tries to derive its value from the partition column type and the specified `partition_increment`. For example, if `partition_increment` is specified as `1 Day`, then `partition_initial_lowerbound` is set to CURRENT DATE. If `partition_increment` is specified as `1 Hour`, then `partition_initial_lowerbound` is set to the current hour of the current date. The bounds for the subsequent partitions are set using the `partition_increment` value.

The system always tries to have a certain minimum number of advance partitions. To decide whether to create new partitions, it uses the specified `partition_autocreate_expression`. This can be an expression that can be evaluated by SQL that's evaluated every time a check is performed. For example, for a partitioned table on column type `date`, suppose `partition_autocreate_expression` is specified as `DATE_TRUNC('day',CURRENT_DATE)`, `partition_increment` is specified as `1 Day`, and `minimum_advance_partitions` is specified as `2`. New partitions are then created until the upper bound of the last partition is less than `DATE_TRUNC('day', CURRENT_DATE) + '2 Days'::interval`.

The expression is evaluated each time the system checks for new partitions.

For a partitioned table on column type `integer`, you can specify the `partition_autocreate_expression` as `SELECT max(partcol) FROM schema.partitioned_table`. The system then regularly checks if the maximum value of the partitioned column is within the distance of `minimum_advance_partitions * partition_increment` of the last partition's upper bound. Create an index on the `partcol` so that the query runs efficiently. If you don't specify the `partition_autocreate_expression` for a partition table on column type `integer`, `smallint`, or `bigint`, then the system sets it to `max(partcol)`.

If the `data_retention_period` is set, partitions are dropped after this period. To minimize locking, partitions are dropped at the same time as new partitions are added. If you don't set this value, you must drop the partitions manually.

The `data_retention_period` parameter is supported only for timestamp-based (and related) partitions. The period is calculated by considering the upper bound of the partition. The partition is dropped if the given period expires, relative to the upper bound.

Stopping automatic creation of partitions

Use `bdr.drop_autopartition()` to drop the autopartitioning rule for the given relation. All pending work items for the relation are deleted, and no new work items are created.

Waiting for partition creation

Partition creation is an asynchronous process. AutoPartition provides a set of functions to wait for the partition to be created, locally or on all nodes.

Use `bdr.autopartition_wait_for_partitions()` to wait for the creation of partitions on the local node. The function takes the partitioned table name and a partition key column value and waits until the partition that holds that value is created.

The function waits only for the partitions to be created locally. It doesn't guarantee that the partitions also exist on the remote nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

To wait for the partition to be created on all PGD nodes, use the `bdr.autopartition_wait_for_partitions_on_all_nodes()` function. This function internally checks local as well as all remote nodes and waits until the partition is created everywhere.

Finding a partition

Use the `bdr.autopartition_find_partition()` function to find the partition for the given partition key value. If a partition to hold that value doesn't exist, then the function returns NULL. Otherwise it returns the Oid of the partition.

Enabling or disabling autopartitioning

Use `bdr.autopartition_enable()` to enable autopartitioning on the given table. If autopartitioning is already enabled, then no action occurs. Similarly, use `bdr.autopartition_disable()` to disable autopartitioning on the given table.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

31 Explicit two-phase commit (2PC)

> **Note**
>
> Two-phase commit isn't available with Group Commit or CAMO. See Commit scope limitations.

An application can explicitly opt to use two-phase commit with PGD. See Distributed Transaction Processing: The XA Specification.

The X/Open Distributed Transaction Processing (DTP) model envisions three software components:

- An application program (AP) that defines transaction boundaries and specifies actions that constitute a transaction
- Resource managers (RMs), such as databases or file-access systems, that provide access to shared resources
- A separate component called a transaction manager (TM) that assigns identifiers to transactions, monitors their progress, and takes responsibility for transaction completion and for failure recovery

PGD supports explicit external 2PC using the `PREPARE TRANSACTION` and `COMMIT PREPARED` / `ROLLBACK PREPARED` commands. Externally, an EDB Postgres Distributed cluster appears to be a single resource manager to the transaction manager for a single session.

When `bdr.commit_scope` is `local`, the transaction is prepared only on the local node. Once committed, changes are replicated, and PGD then applies post-commit conflict resolution.

Using `bdr.commit_scope` set to `local` might not seem to make sense with explicit two-phase commit. However, the option is offered to allow you to control the tradeoff between transaction latency and robustness.

Explicit two-phase commit doesn't work with either CAMO or the global commit scope. Future releases might enable this combination.

Use

Two-phase commits with a local commit scope work exactly like standard PostgreSQL. Use the local commit scope and disable CAMO:

```
BEGIN;

SET LOCAL bdr.enable_camo = 'off';
SET LOCAL bdr.commit_scope =
'local';

... other commands
possible...
```

To start the first phase of the commit, the client must assign a global transaction id, which can be any unique string identifying the transaction:

```
PREPARE TRANSACTION 'some-global-id';
```

After a successful first phase, all nodes have applied the changes and are prepared for committing the transaction. The client must then invoke the second phase from the same node:

```
COMMIT PREPARED 'some-global-
id';
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

32 Decoding worker

PGD provides an option to enable a decoding worker process that performs decoding once, no matter how many nodes are sent data. This option introduces a new process, the WAL decoder, on each PGD node. One WAL sender process still exists for each connection, but these processes now just perform the task of sending and receiving data. Taken together, these changes reduce the CPU overhead of larger PGD groups and also allow higher replication throughput since the WAL sender process now spends more time on communication.

Enabling

`enable_wal_decoder` is an option for each PGD group, which is currently disabled by default. You can use `bdr.alter_node_group_option()` to enable or disable the decoding worker for a PGD group.

When the decoding worker is enabled, PGD stores logical change record (LCR) files to allow buffering of changes between decoding and when all subscribing nodes received data. LCR files are stored under the `pg_logical` directory in each local node's data directory. The number and size of the LCR files varies as replication lag increases, so this process also needs monitoring. The LCRs that aren't required by any of the PGD nodes are cleaned periodically. The interval between two consecutive cleanups is controlled by `bdr.lcr_cleanup_interval`, which defaults to 3 minutes. The cleanup is disabled when `bdr.lcr_cleanup_interval` is 0.

Disabling

When disabled, logical decoding is performed by the WAL sender process for each node subscribing to each node. In this case, no LCR files are written.

Even though the decoding worker is enabled for a PGD group, following GUCs control the production and use of LCR per node. By default these are `false`. For production and use of LCRs, enable the decoding worker for the PGD group and set these GUCs to `true` on each of the nodes in the PGD group.

- `bdr.enable_wal_decoder` — When `false`, all WAL senders using LCRs restart to use WAL directly. When `true` along with the PGD group config, a decoding worker process is started to produce LCR and WAL senders that use LCR.
- `bdr.receive_lcr` — When `true` on the subscribing node, it requests WAL sender on the publisher node to use LCRs if available.

> **Notes**
>
> As of now, a decoding worker decodes changes corresponding to the node where it's running. A logical standby is sent changes from all the nodes in the PGD group through a single source. Hence a WAL sender serving a logical standby currently can't use LCRs.
>
> A subscriber-only node receives changes from respective nodes directly. Hence a WAL sender serving a subscriber-only node can use LCRs.
>
> Even though LCRs are produced, the corresponding WALs are still retained similar to the case when a decoding worker isn't enabled. In the future, it might be possible to remove WAL corresponding the LCRs, if they aren't otherwise required.

LCR file names

For reference, the first 24 characters of an LCR file name are similar to those in a WAL file name. The first 8 characters of the name are currently all '0'. In the future, they're expected to represent the TimeLineId similar to the first 8 characters of a WAL segment file name. The following sequence of 16 characters of the name is similar to the WAL segment number, which is used to track LCR changes against the WAL stream.

However, logical changes are reordered according to the commit order of the transactions they belong to. Hence their placement in the LCR segments doesn't match the placement of corresponding WAL in the WAL segments.

The set of the last 16 characters represents the subsegment number in an LCR segment. Each LCR file corresponds to a subsegment. LCR files are binary and variable sized. You can control the maximum size of an LCR file by adjusting `bdr.max_lcr_segment_file_size`, which defaults to 1 GB.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Using with transaction streaming

It's possible to enable transaction streaming and the decoding worker at the same time. Transaction streaming means that the WAL sender can send a partial transaction before it commits, reducing replication lag. The WAL decoder now supports the decoding of partial transactions, so the decoding worker can decode the partial transaction and store it in an LCR file. The LCR file is then used to apply the transaction on the subscriber node. This in turn reduces CPU usage, by reducing the lag, and reduces disk space usages, since ".spill" files are not generated.

The WAL decoder always streams the transactions to LCRs but based on downstream request the WAL sender either stream transaction or just mimics a normal `BEGIN..COMMIT` scenario.

To support this feature, the system creates additional streaming files. These files have names in that begin with `STR_TXN_<file-name-format>` and `CAS_TXN_<file-name-format>` and each streamed transaction creates their own pair.

To enable transaction streaming with the WAL decoder, set the PGD group's `bdr.streaming_mode` set to 'default' using `bdr.alter_node_group_option`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

33 Transaction streaming

With logical replication, transactions are decoded concurrently on the publisher but aren't sent to subscribers until the transaction is committed. If the changes exceed `logical_decoding_work_mem` (PostgreSQL 13 and later), they're spilled to disk. This means that, particularly with large transactions, there's some delay before they reach subscribers and might entail additional I/O on the publisher.

Beginning with PostgreSQL 14, transactions can optionally be decoded and sent to subscribers before they're committed on the publisher. The subscribers save the incoming changes to a staging file (or set of files) and apply them when the transaction commits (or discard them if the transaction aborts). This makes it possible to apply transactions on subscribers as soon as the transaction commits.

PGD enhancements

PostgreSQL's built-in transaction streaming has the following limitations:

- While you no longer need to spill changes to disk on the publisher, you must write changes to disk on each subscriber.
- If the transaction aborts, the work (changes received by each subscriber and the associated storage I/O) is wasted.

However, starting with version 3.7, PGD supports Parallel Apply, enabling multiple writer processes on each subscriber. This capability is leveraged to provide the following enhancements:

- Decoded transactions can be streamed directly to a writer on the subscriber.
- Decoded transactions don't need to be stored on disk on subscribers.
- You don't need to wait for the transaction to commit before starting to apply the transaction on the subscriber.

Caveats

- You must enable Parallel Apply.
- Workloads consisting of many small and conflicting transactions can lead to frequent deadlocks between writers.

> **Note**
>
> Direct streaming to writer is still an experimental feature. Use it with caution. Specifically, it might not work well with conflict resolutions since the commit timestamp of the streaming might not be available. (The transaction might not yet have committed on the origin.)

Configuration

Configure transaction streaming in two locations:

- At node level, using the GUC `bdr.default_streaming_mode`
- At group level, using the function `bdr.alter_node_group_option()`

Node configuration using bdr.default_streaming_mode

Permitted values are:

- `off`
- `writer`
- `file`
- `auto`

Default value is `auto`.

Changing this setting requires a restart of the pglogical receiver process for each subscription for the setting to take effect. You can achieve this with a server restart.

If `bdr.default_streaming_mode` is set to any value other than `off`, the subscriber requests transaction streaming from the publisher. How this is provided can also depend on the group configuration setting. See Node configuration using bdr.default_streaming_mode for details.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Group configuration using bdr.alter_node_group_option()

You can use the parameter `streaming_mode` in the function `bdr.alter_node_group_option()` to set the group transaction streaming configuration.

Permitted values are:

- `off`
- `writer`
- `file`
- `auto`
- `default`

The default value is `default`.

The value of the current setting is contained in the column `node_group_streaming_mode` from the view `bdr.node_group`. The value returned is a single char type, and the possible values are `D` (`default`), `W` (`writer`), `F` (`file`), `A` (`auto`), and `O` (`off`).

Configuration setting effects

Transaction streaming is controlled at the subscriber level by the GUC `bdr.default_streaming_mode`. Unless set to `off`, which disables transaction streaming, the subscriber requests transaction streaming.

If the publisher can provide transaction streaming, it streams transactions whenever the transaction size exceeds the threshold set in `logical_decoding_work_mem`. The publisher usually has no control over whether the transactions are streamed to a file or to a writer. Except for some situations (such as COPY), it might hint for the subscriber to stream the transaction to a writer (if possible).

The subscriber can stream transactions received from the publisher to either a writer or a file. The decision is based on several factors:

- If Parallel Apply is off (`num_writers = 1`), then it's streamed to a file. (writer 0 is always reserved for non-streamed transactions.)
- If Parallel Apply is on but all writers are already busy handling streamed transactions, then the new transaction is streamed to a file. See Monitoring PGD writers to check PGD writer status.

If streaming to a writer is possible (that is, a free writer is available), then the decision whether to stream the transaction to a writer or a file is based on the combination of group and node settings as per the following table.

Group	Node	Streamed to
off	(any)	(none)
(any)	off	(none)
writer	file	file
file	writer	file
default	writer	writer
default	file	file
default	auto	writer
auto	(any)	writer

If the group configuration is set to `auto`, or the group configuration is `default` and the node configuration is `auto`, then the transaction is streamed to a writer only if the publisher hinted to do this.

Currently the publisher hints for the subscriber to stream to the writer for the following transaction types. These are known to be conflict free and can be safely handled by the writer.

- `COPY`
- `CREATE INDEX CONCURRENTLY`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Monitoring

You can monitor the use of transaction streaming using the `bdr.stat_subscription` function on the subscriber node.

- `nstream_writer` — Number of transactions streamed to a writer.
- `nstream_file` — Number of transactions streamed to file.
- `nstream_commit` — Number of committed streamed transactions.
- `nstream_abort` — Number of aborted streamed transactions.
- `nstream_start` — Number of streamed transactions that were started.
- `nstream_stop` — Number of streamed transactions that were fully received.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

34 Timestamp-based snapshots

The timestamp-based snapshots allow reading data in a consistent manner by using a user-specified timestamp rather than the usual MVCC snapshot. You can use this feature to access data on different PGD nodes at a common point in time. For example, you can compare data on multiple nodes for data-quality checking.

This feature doesn't currently work with write transactions.

Enable the use of timestamp-based snapshots using the `snapshot_timestamp` parameter. This parameter accepts either a timestamp value or a special value, `'current'`, which represents the current timestamp (now). If `snapshot_timestamp` is set, queries use that timestamp to determine visibility of rows rather than the usual MVCC semantics.

For example, the following query returns the state of the `customers` table at 2018-12-08 02:28:30 GMT:

```
SET snapshot_timestamp = '2018-12-08 02:28:30
GMT';
SELECT count(*) FROM customers;
```

Without PGD, this query works only with future timestamps or the special `'current'` value, so you can't use it for historical queries.

PGD works with and improves on that feature in a multi-node environment. First, PGD makes sure that all connections to other nodes replicate any outstanding data that was added to the database before the specified timestamp. This ensures that the timestamp-based snapshot is consistent across the whole multi-master group. Second, PGD adds a parameter called `bdr.timestamp_snapshot_keep`. This parameter specifies a window of time when you can execute queries against the recent history on that node.

You can specify any interval, but be aware that VACUUM (including autovacuum) doesn't clean dead rows that are newer than up to twice the specified interval. This also means that transaction ids aren't freed for the same amount of time. As a result, using this can leave more bloat in user tables. Initially, we recommend 10 seconds as a typical setting, although you can change that as needed.

Once the query is accepted for execution, the query might run for longer than `bdr.timestamp_snapshot_keep` without problem, just as normal.

Also, information about how far the snapshots were kept doesn't survive server restart. The oldest usable timestamp for the timestamp-based snapshot is the time of last restart of the PostgreSQL instance.

You can combine the use of `bdr.timestamp_snapshot_keep` with the `postgres_fdw` extension to get a consistent read across multiple nodes in a PGD group. You can use this combination to run parallel queries across nodes, when used with foreign tables.

There are no limits on the number of nodes in a multi-node query when using this feature.

Use of timestamp-based snapshots doesn't increase inter-node traffic or bandwidth. Only the timestamp value is passed in addition to query data.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

35 CDC Failover support

> **Availability**
>
> This is a PGD 5.7 and later feature. It is not supported on earlier versions of PGD.

Background

Earlier versions of PGD have allowed the creation of logical replication slots on nodes that can provide a feed of the logical changes happening to the data in the database. These logical replication slots have been local to the node and not replicated. Apart from only replicating changes on the particular node, this behavior has presented challenges when faced with node failover in the cluster. In that scenario, a consumer of the logical replication off a node that fails has no replica of the slot on another node to continue consuming from.

While solutions to this can be engineered using a subscriber-only node as an intermediary, it significantly raises the cost of logical replication.

CDC Failover support

To address this need, PGD 5.7 introduces CDC Failover support. This is an optionally enabled feature that activates automatic logical slot replication across the cluster. This, in turn, allows a consumer of a logical slot's replication to receive change data from any node when a failure occurs.

How CDC Failover works

When a logical slot is created on a node with CDC Failover support enabled, the slot is replicated across the cluster. This means that the slot is available for consumption on any node in the cluster. When a node fails, the slot can be consumed from another node in the cluster. This allows for continuing the logical replication stream without interruption.

If, though, the consumer of the slot connects to a different node in the cluster, the previous connection the consumer had will be closed by PGD. This behavior is to ensure that the slot isn't being consumed from multiple nodes at the same time. In the background, PGD is using its Raft consensus protocol to ensure that the slot is being consumed from only one node at a time. This means that the guarantee of only one slot being consumed at a time doesn't hold in split-brain scenarios.

Currently CDC Failover support is a global option that's controlled by a top-group option. The `failover_slot_scope` top-group option can currently be set to (and defaults to) `local`, which disables replication of logical slots, or `global`. The `global` setting enables the replication of all non-temporary logical slots created in the PGD database.

Temporary logical slots aren't replicated, as they have a lifetime scoped to the session that created them and will go away when that session ends.

At-least-once delivery guarantees

CDC Failover support takes steps to ensure that the consumer receives all changes at least once. This is done by holding back slots until delivery has been confirmed, at which point the slot is then advanced on all nodes in an asynchronous manner. In the case of a failure on the node where the slot was being consumed, the slot is held until the consumer connects to a node in the cluster. This then allows the slot to progress.

> **Important**
>
> If a consuming application disconnects and doesn't reconnect, the slot will remain held back on every node in the cluster. As this consumes disk and memory, it's essential to avoid this situation. Applications that consume slots must return to consuming as soon as possible.

Exactly-once delivery

Currently, there's no way to ensure exactly-once delivery, and we expect consuming applications to manage the discarding of previously completed transactions.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Enabling CDC Failover support

To enable CDC Failover support run the SQL command and call the `bdr.alter_node_group_option` function with the following parameters:

```
select bdr.alter_node_group_option(<top-level group name>,
     'failover_slot_scope',
     'global');
```

Replace `<top-level group name>` with the name of your cluster's top-level group. If you don't know the name, it's the group with a node_group_parent_id equal to 0 in `bdr.node_group`.

If you do not know the name, it is the group with a node_group_parent_id equal to 0 in `bdr.node_group`. You can also use:

```
SELECT bdr.alter_node_group_option(

node_group_name,
     'failover_slot_scope',
     'global')
    from bdr.node_group
    where node_group_parent_id=0;
```

This command ensures you're setting the correct top-level group's option.

Once CDC Failover is enabled, to create a new globally replicated slot, you can use:

```
SELECT pg_create_logical_replication_slot('myslot',
                                          'test_decoding');
```

Logical replication slots created before the option was set to `global` aren't replicated. Only new slots are replicated.

Failover slots can also be created with the `CREATE_REPLICATION_SLOT` command on a replication connection.

The status of failover slots is tracked in the `bdr.failover_replication_slots` table.

CDC Failover support with Postgres 17+

For Postgres 17 and later, support for failover was added to allow standbys to be resumed. Use an option in `pg_create_logical_replication_slot` named `failover` for this purpose. This new setting requires that, no matter what the setting of `failover_slot_scope`, you must also set `failover` to `true`.

```
SELECT pg_create_logical_replication_slot('myslot',
                                          'test_decoding',

failover=>true);
```

Obtaining Initial Consistent Snapshot

When a logical replication slot is created, a consistent snapshot is exported by Postgres. This snapshot can be used to obtain a consistent initial copy of the data. PGD's failover slot mechanism also follows the same procedure. But the consumer must obtain the snapshot from the same node where the slot was originally created. In addition, it must also start the initial replication from the same node. Once the consumer has received enough changes over the replication stream, the failover slot is marked as `failover_safe`. Once the slot is marked as `failover_safe`, then the consumer can safely failover to some other node in the PGD cluster (other considerations apply though, see below).

To check if the slot is `failover_safe` or not, the user can query the `bdr.failover_replication_slots` catalog and check for the value of `failover_safe` column of the given slot.

If the consumer connects to some other PGD node and attempts to start replication before the slot is marked `failover_safe`, an appropriate error will be raised by PGD.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Failing Over to Newly Joined Nodes

When a new node joins the PGD cluster, it may not be immediately ready to serve as a decoding target for a CDC failover slot. The newly joined node may not have all the WAL files to decode the changes that the consumer has not yet consumed. Consuming from such a node may result in data loss. PGD detects and prevents such situations by internally tracking the replication progress and preventing a new node from being a failover target, until it's safe to do so. If the consumer tries to connect to a node that is not yet ready to serve as a decoding target, an appropriate error will be raised.

Tracking Per-Origin Progress

Transactions can originate from any node in the PGD cluster. When a consumer connects to a PGD node and starts decoding transactions, it may receive changes for the transactions originated on that node as well as transactions replicated from other nodes in the cluster. The consumer is expected to track replication progress across all such PGD nodes or origins and ensure that duplicate transactions are handled correctly. To facilitate this, the `test_decoding` plugin in Postgres-Extended and EnterpriseDB Advance Server has been enhanced to include the origin information of the transactions. Consumers can opt to receive origin information by setting `include-origin` option to `on` while starting the logical replication.

A sample output of `test_decoding` plugin with the origin information is produced below.

```
BEGIN 1723654 (origin 2) (origin_name bdr_bdrdemo_bdrgroup_node2) (origin_lsn 0/1D948910)
table public.pgbench_accounts: UPDATE: old-key: aid[integer]:39958 bid[integer]:1 abalance[integer]:0
filler[character]:'                                                                  ' new-tuple:
aid[integer]:39958 bid[integer]:1 abalance[integer]:-1783 filler[character]:'
'
table public.pgbench_tellers: UPDATE: old-key: tid[integer]:6 bid[integer]:1 tbalance[integer]:0 new-tuple:
tid[integer]:6 bid[integer]:1 tbalance[integer]:-1783 filler[character]:null
table public.pgbench_branches: UPDATE: old-key: bid[integer]:1 bbalance[integer]:0 new-tuple: bid[integer]:1
bbalance[integer]:-1783 filler[character]:null
table public.pgbench_history: INSERT: tid[integer]:6 bid[integer]:1 aid[integer]:39958 delta[integer]:-1783
mtime[timestamp without time zone]:'2025-01-31 16:51:21.511571' filler[character]:null
COMMIT 1723654 (origin 2) (origin_name bdr_bdrdemo_bdrgroup_node2) (origin_lsn 0/1D948910)
```

Consumers can make use of this information to track per-origin progress.

PGD also records replication progress across all nodes in the `bdr.logical_checkpoints` catalog and the consumer can receive decoded changes for the catalog and use that information to know the replication progress.

```
BEGIN 65720
id[name]:'370098259-0-6056978' origin_node[oid]:370098259 origin_lsn[pg_lsn]:'0/6056978' local_node[oid]:370098259
local_lsn[pg_lsn]:'0/6056978' peer_count[integer]:2 peer_nodes[oid[]]:'{2228531844,4052927809}'
peer_lsns[pg_lsn[]]:'{0/4836758,0/67F0AF8}'
COMMIT 65720
```

In this example, the node 370098259 is reporting the replication progress. When the consumer receives this change record, it can be sure of having received everything up to 0/4836758 and 0/67F0AF8 respectively from nodes 2228531844 and 4052927809.

> **Important**
>
> Currently PGD reports node information as OIDs stored in `bdr.node` catalog. But this will change in the near future and the information will be replaced by UUID.

Limitations

The CDC Failover Slot support comes with certain limitations:

- CDC Failover slot support requires the latest versions of EDB Postgres Distributed (PGD) 5.7+ and the latest minor releases of Postgres Extended or EDB Postgres Advanced Server (available Feb 2025).
- CDC Failover support is a global option and can't be set on a per-slot basis. Because changing the enabled status of CDC Failover doesn't affect previously provisioned slots, it's possible to enable it (set to `global`), create a replicated slot, then disable it (set to `local`) to create a singular replicated slot.
- CDC Failover support isn't supported on temporary slots.
- CDC Failover support isn't supported on slots created with the `failover` option set to `false`.
- CDC Failover support works with EDB Postgres Advanced Server and EDB Postgres Extended Server only. It isn't supported on community Postgres installations.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- Existing slots aren't converted into failover slots when the option is enabled.
- While Postgres's built-in functions such as `pg_logical_slot_get_changes()` can be used, they won't ensure that the slot isn't being decoded anywhere else and can't update replication progress accurately across the cluster. Therefore, we recommend that you don't rely on the function to receive decoded changes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36 PGD reference

The reference section is a definitive listing of all functions, views, and commands available in EDB Postgres Distributed.

User visible catalogs and views

- bdr.camo_decision_journal
- bdr.commit_decisions
- bdr.commit_scopes
- bdr.conflict_history
- bdr.conflict_history_summary
- bdr.consensus_kv_data
- bdr.crdt_handlers
- bdr.ddl_replication
- bdr.depend
- bdr.failover_replication_slots
- bdr.global_consensus_journal
- bdr.global_consensus_journal_details
- bdr.global_consensus_response_journal
- bdr.global_lock
- bdr.global_locks
- bdr.group_camo_details
- bdr.group_raft_details
- bdr.group_replslots_details
- bdr.group_subscription_summary
- bdr.group_versions_details
- bdr.leader
- bdr.local_consensus_snapshot
- bdr.local_consensus_state
- bdr.local_node
- bdr.local_node_summary
- bdr.local_sync_status
- bdr.node
- bdr.node_catchup_info
- bdr.node_catchup_info_details
- bdr.node_conflict_resolvers
- bdr.node_group
- bdr.node_group_replication_sets
- bdr.node_group_summary
- bdr.node_local_info
- bdr.node_log_config
- bdr.node_peer_progress
- bdr.node_replication_rates
- bdr.node_slots
- bdr.node_summary
- bdr.queue
- bdr.raft_instances
- bdr.replication_set
- bdr.replication_set_table
- bdr.replication_set_ddl
- bdr.replication_sets
- bdr.replication_status
- bdr.schema_changes
- bdr.sequence_alloc
- bdr.sequences
- bdr.stat_activity
- bdr.stat_commit_scope
- bdr.stat_commit_scope_state
- bdr.stat_raft_followers_state
- bdr.stat_raft_state
- bdr.stat_receiver
- bdr.stat_relation
- bdr.stat_routing_candidate_state
- bdr.stat_routing_state

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- bdr.stat_subscription
- bdr.stat_worker
- bdr.stat_writer
- bdr.subscription
- bdr.subscription_summary
- bdr.tables
- bdr.taskmgr_work_queue
- bdr.taskmgr_workitem_status
- bdr.taskmgr_local_work_queue
- bdr.taskmgr_local_workitem_status
- bdr.trigger
- bdr.triggers
- bdr.workers
- bdr.writers
- bdr.worker_tasks
- bdr.xid_peer_progress

System functions

Version information functions

- bdr.bdr_version
- bdr.bdr_version_num

System information functions

- bdr.get_relation_stats
- bdr.get_subscription_stats

System and progress information parameters

- bdr.local_node_id
- bdr.last_committed_lsn
- transaction_id
- bdr.is_node_connected
- bdr.is_node_ready

Consensus function

- bdr.consensus_disable
- bdr.consensus_enable
- bdr.consensus_proto_version
- bdr.consensus_snapshot_export
- bdr.consensus_snapshot_import
- bdr.consensus_snapshot_verify
- bdr.get_consensus_status
- bdr.get_raft_status
- bdr.raft_leadership_transfer

Utility functions

- bdr.wait_slot_confirm_lsn
- bdr.wait_node_confirm_lsn
- bdr.wait_for_apply_queue
- bdr.get_node_sub_receive_lsn
- bdr.get_node_sub_apply_lsn
- bdr.replicate_ddl_command
- bdr.run_on_all_nodes

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- `bdr.run_on_nodes`
- `bdr.run_on_group`
- `bdr.global_lock_table`
- `bdr.wait_for_xid_progress`
- `bdr.local_group_slot_name`
- `bdr.node_group_type`
- `bdr.alter_node_kind`
- `bdr.alter_subscription_skip_changes_upto`
- `bdr.connection_manager_refresh_pools`

Global advisory locks

- `bdr.global_advisory_lock`
- `bdr.global_advisory_unlock`

Monitoring functions

- `bdr.monitor_group_versions`
- `bdr.monitor_group_raft`
- `bdr.monitor_local_replslots`
- `bdr.wal_sender_stats`
- `bdr.get_decoding_worker_stat`
- `bdr.lag_control`

CAMO functions

- `bdr.is_camo_partner_connected`
- `bdr.is_camo_partner_ready`
- `bdr.get_configured_camo_partner`
- `bdr.wait_for_camo_partner_queue`
- `bdr.camo_transactions_resolved`
- `bdr.logical_transaction_status`

Commit Scope functions

- `bdr.add_commit_scope`
- `bdr.create_commit_scope`
- `bdr.alter_commit_scope`
- `bdr.drop_commit_scope`
- `bdr.remove_commit_scope`

PGD settings

Conflict handling

- `bdr.default_conflict_detection`

Global sequence parameters

- `bdr.default_sequence_kind`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

DDL handling

- `bdr.default_replica_identity`
- `bdr.ddl_replication`
- `bdr.role_replication`
- `bdr.ddl_locking`
- `bdr.truncate_locking`

Global locking

- `bdr.global_lock_max_locks`
- `bdr.global_lock_timeout`
- `bdr.global_lock_statement_timeout`
- `bdr.global_lock_idle_timeout`
- `bdr.lock_table_locking`
- `bdr.predictive_checks`

Node management

- `bdr.replay_progress_frequency`

Generic replication

- `bdr.writers_per_subscription`
- `bdr.max_writers_per_subscription`
- `bdr.xact_replication`
- `bdr.permit_unsafe_commands`
- `bdr.batch_inserts`
- `bdr.maximum_clock_skew`
- `bdr.maximum_clock_skew_action`
- `bdr.accept_connections`
- `bdr.standby_slot_names`
- `bdr.standby_slots_min_confirmed`
- `bdr.writer_input_queue_size`
- `bdr.writer_output_queue_size`
- `bdr.min_worker_backoff_delay`

CRDTs

- `bdr.crdt_raw_value`

Commit scope

- `bdr.commit_scope`

Commit At Most Once

- `bdr.camo_local_mode_delay`
- `bdr.camo_enable_client_warnings`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Transaction streaming

- `bdr.default_streaming_mode`

Lag Control

- `bdr.lag_control_min_conforming_nodes`
- `bdr.lag_control_commit_delay_adjust`
- `bdr.lag_control_sample_interval`
- `bdr.lag_control_commit_delay_start`

Timestamp-based snapshots

- `bdr.timestamp_snapshot_keep`

Monitoring and logging

- `bdr.debug_level`
- `bdr.trace_level`
- `bdr.track_subscription_apply`
- `bdr.track_relation_apply`
- `bdr.track_apply_lock_timing`

Decoding worker

- `bdr.enable_wal_decoder`
- `bdr.receive_lcr`
- `bdr.lcr_cleanup_interval`

Connectivity settings

- `bdr.global_connection_timeout`
- `bdr.global_keepalives`
- `bdr.global_keepalives_idle`
- `bdr.global_keepalives_interval`
- `bdr.global_keepalives_count`
- `bdr.global_tcp_user_timeout`

Topology settings

- `bdr.force_full_mesh`

Internal settings - Raft timeouts

- `bdr.raft_global_election_timeout`
- `bdr.raft_group_election_timeout`
- `bdr.raft_response_timeout`

Internal settings - Other Raft values

- `bdr.raft_keep_min_entries`
- `bdr.raft_log_min_apply_duration`
- `bdr.raft_log_min_message_duration`
- `bdr.raft_group_max_connections`
- `bdr.raft_vacuum_interval`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- `bdr.raft_vacuum_full_interval`

Internal settings - Other values

- `bdr.backwards_compatibility`
- `bdr.track_replication_estimates`
- `bdr.lag_tracker_apply_rate_weight`
- `bdr.enable_auto_sync_reconcile`

Node management

- List of node states
- Node-management commands
  - `bdr_init_physical`
  - `bdr_config`

Node management interfaces

- `bdr.alter_node_group_option`
- `bdr.alter_node_interface`
- `bdr.alter_node_option`
- `bdr.alter_subscription_enable`
- `bdr.alter_subscription_disable`
- `bdr.create_node`
- `bdr.create_node_group`
- `bdr.drop_node_group`
- `bdr.join_node_group`
- `bdr.part_node`
- `bdr.promote_node`
- `bdr.switch_node_group`
- `bdr.wait_for_join_completion`
- `bdr.alter_node_group_config`

Routing functions

- `bdr.create_proxy`
- `bdr.alter_proxy_option`
- `bdr.drop_proxy`
- `bdr.routing_leadership_transfer`

Commit scopes

- Commit scope syntax
  - commit_scope_degrade_operation

- Commit scope targets
  - ORIGIN_GROUP

- Commit scope groups
  - ANY
  - ANY NOT
  - MAJORITY
  - MAJORITY NOT
  - ALL
  - ALL NOT

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- Confirmation level
  - ON received
  - ON replicated
  - ON durable
  - ON visible
- Commit Scope kinds
- SYNCHRONOUS COMMIT
  - DEGRADE ON parameters
  - commit_scope_degrade_operation
- GROUP COMMIT
  - GROUP COMMIT parameters
  - ABORT ON parameters
  - DEGRADE ON parameters
  - transaction_tracking settings
  - conflict_resolution settings
  - commit_decision settings
  - commit_scope_degrade_operation settings
- CAMO
  - DEGRADE ON parameters
- LAG CONTROL
  - LAG CONTROL parameters

Conflicts

- Conflict detection
  - List of conflict types
- Conflict resolution
  - List of conflict resolvers
  - Default conflict resolvers
  - List of conflict resolutions
- Conflict logging

Conflict functions

- `bdr.alter_table_conflict_detection`
- `bdr.alter_node_set_conflict_resolver`
- `bdr.alter_node_set_log_config`

Replication set management

- `bdr.create_replication_set`
- `bdr.alter_replication_set`
- `bdr.drop_replication_set`
- `bdr.alter_node_replication_sets`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Replication set membership

- `bdr.replication_set_add_table`
- `bdr.replication_set_remove_table`

DDL replication filtering

- `bdr.replication_set_add_ddl_filter`
- `bdr.replication_set_remove_ddl_filter`

Testing and tuning commands

- `pgd_bench`

Global sequence management interfaces

Sequence functions

- `bdr.alter_sequence_set_kind`
- `bdr.extract_timestamp_from_snowflakeid`
- `bdr.extract_nodeid_from_snowflakeid`
- `bdr.extract_localseqid_from_snowflakeid`
- `bdr.timestamp_to_snowflakeid`
- `bdr.extract_timestamp_from_timeshard`
- `bdr.extract_nodeid_from_timeshard`
- `bdr.extract_localseqid_from_timeshard`
- `bdr.timestamp_to_timeshard`
- `bdr.galloc_chunk_info`

KSUUID v2 functions

- `bdr.gen_ksuuid_v2`
- `bdr.ksuuid_v2_cmp`
- `bdr.extract_timestamp_from_ksuuid_v2`

KSUUID v1 functions

- `bdr.gen_ksuuid`
- `bdr.uuid_v1_cmp`
- `bdr.extract_timestamp_from_ksuuid`

Autopartition

- `bdr.autopartition`
- `bdr.drop_autopartition`
- `bdr.autopartition_wait_for_partitions`
- `bdr.autopartition_wait_for_partitions_on_all_nodes`
- `bdr.autopartition_find_partition`
- `bdr.autopartition_enable`
- `bdr.autopartition_disable`
- Internal functions
- `bdr.autopartition_create_partition`
- `bdr.autopartition_drop_partition`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Stream triggers reference

Stream triggers manipulation interfaces

- `bdr.create_conflict_trigger`
- `bdr.create_transform_trigger`
- `bdr.drop_trigger`

Stream triggers row functions

- `bdr.trigger_get_row`
- `bdr.trigger_get_committs`
- `bdr.trigger_get_xid`
- `bdr.trigger_get_type`
- `bdr.trigger_get_conflict_type`
- `bdr.trigger_get_origin_node_id`
- `bdr.ri_fkey_on_del_trigger`

Stream triggers row variables

- `TG_NAME`
- `TG_WHEN`
- `TG_LEVEL`
- `TG_OP`
- `TG_RELID`
- `TG_TABLE_NAME`
- `TG_TABLE_SCHEMA`
- `TG_NARGS`
- `TG_ARGV[]`

Internal catalogs and views

- `bdr.autopartition_partitions`
- `bdr.autopartition_rules`
- `bdr.ddl_epoch`
- `bdr.event_history`
- `bdr.event_summary`
- `bdr.local_leader_change`
- `bdr.node_config`
- `bdr.node_config_summary`
- `bdr.node_group_config`
- `bdr.node_group_routing_config_summary`
- `bdr.node_group_routing_info`
- `bdr.node_group_routing_summary`
- `bdr.node_peer_progress_mapping`
- `bdr.node_routing_config_summary`
- `bdr.proxy_config`
- `bdr.proxy_config_summary`
- `bdr.sequence_kind`
- `bdr.sync_node_requests`
- `bdr.sync_node_requests_summary`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Internal system functions

General internal functions

- bdr.bdr_get_commit_decisions
- bdr.bdr_track_commit_decision
- bdr.consensus_kv_fetch
- bdr.consensus_kv_store
- bdr.decode_message_payload
- bdr.decode_message_response_payload
- bdr.difference_fix_origin_create
- bdr.difference_fix_session_reset
- bdr.difference_fix_session_setup
- bdr.difference_fix_xact_set_avoid_conflict
- bdr.drop_node
- bdr.get_global_locks
- bdr.get_node_conflict_resolvers
- bdr.get_slot_flush_timestamp
- bdr.internal_alter_sequence_set_kind
- bdr.internal_replication_set_add_table
- bdr.internal_replication_set_remove_table
- bdr.internal_submit_join_request
- bdr.isolation_test_session_is_blocked
- bdr.local_node_info
- bdr.msgb_connect
- bdr.msgb_deliver_message
- bdr.node_catchup_state_name
- bdr.node_kind_name
- bdr.peer_state_name
- bdr.pg_xact_origin
- bdr.request_replay_progress_update
- bdr.reset_relation_stats
- bdr.reset_subscription_stats
- bdr.resynchronize_table_from_node
- bdr.seq_currval
- bdr.seq_lastval
- bdr.seq_nextval
- bdr.show_subscription_status
- bdr.show_workers
- bdr.show_writers
- bdr.sync_status_name

Task manager functions

- bdr.taskmgr_set_leader
- bdr.taskmgr_get_last_completed_workitem
- bdr.taskmgr_work_queue_check_status
- bdr.pglogical_proto_version_ranges
- bdr.get_min_required_replication_slots
- bdr.get_min_required_worker_processes
- bdr.stat_get_activity
- bdr.worker_role_id_name
- bdr.lag_history
- bdr.get_raft_instance_by_nodegroup
- bdr.monitor_camo_on_all_nodes
- bdr.monitor_raft_details_on_all_nodes
- bdr.monitor_replslots_details_on_all_nodes
- bdr.monitor_subscription_details_on_all_nodes
- bdr.monitor_version_details_on_all_nodes
- bdr.node_group_member_info

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Conflict functions

- `bdr.alter_table_conflict_detection`
- `bdr.alter_node_set_conflict_resolver`
- `bdr.alter_node_set_log_config`

Column-level conflict functions

- `bdr.column_timestamps_create`

Conflicts

- Conflict detection
  - List of conflict types
- Conflict resolution
  - List of conflict resolvers
  - Default conflict resolvers
  - List of conflict resolutions
- Conflict logging

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.1 User visible catalogs and views

Catalogs and views are listed here in alphabetical order.

`bdr.camo_decision_journal`

A persistent journal of decisions resolved by a CAMO partner node after a failover, in case `bdr.logical_transaction_status` was invoked. Unlike `bdr.commit_decisions`, this doesn't cover transactions processed under normal operational conditions (that is, both nodes of a CAMO pair are running and connected). Entries in this journal aren't ever cleaned up automatically. This is a diagnostic tool that the system doesn't depend on.

`bdr.camo_decision_journal` columns

Name	Type	Description
origin_node_id	oid	OID of the node where the transaction executed
origin_xid	oid	Transaction ID on the remote origin node
decision	char	'c' for commit, 'a' for abort
decision_ts	timestamptz	Decision time

`bdr.commit_decisions`

A view used internally on nodes configured as Commit At Most Once (CAMO) partners. Shows the decisions a CAMO partner took on transactions in the last 15 minutes.

`bdr.commit_decisions` columns

Name	Type	Description
origin_node_id	oid	OID of the node where the transaction executed
origin_xid	xid	Transaction ID on the remote origin node
decision	char	Decision taken; can be `c` (commit), or `a` (abort).
local_xid	xid	Transaction ID on the local node
commit_ts	timestamptz	Commit timestamp of the transaction
decision_ts	timestamptz	Decision time

`bdr.commit_scopes`

Catalog storing all possible commit scopes that you can use for `bdr.commit_scope` to enable Group Commit.

`bdr.commit_scopes` columns

Name	Type	Description
commit_scope_id	oid	ID of the scope to be referenced
commit_scope_name	name	Name of the scope to be referenced
commit_scope_origin_node_group	oid	Node group for which the rule applies, referenced by ID
sync_scope_rule	text	Definition of the scope

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.conflict_history`

This table is the default table where conflicts are logged. The table is RANGE partitioned on column `local_time` and is managed by Autopartition. The default data retention period is 30 days.

Access to this table is possible by any table owner, who can see all conflicts for the tables they own, restricted by row-level security.

For details, see Logging conflicts to a table.

`bdr.conflict_history` columns

Name	Type	Description
sub_id	oid	Subscription that produced this conflict; can be joined to `bdr.subscription` table
origin_node_id	oid	OID (as seen in the pg_replication_origin catalog) of the node that produced the conflicting change
local_xid	xid	Local transaction of the replication process at the time of conflict
local_lsn	pg_lsn	Local LSN at the time of conflict
local_time	timestamp with time zone	Local time of the conflict
remote_xid	xid	Transaction that produced the conflicting change on the remote node (an origin)
remote_change_nr	oid	Index of the change within its transaction
remote_commit_lsn	pg_lsn	Commit LSN of the transaction which produced the conflicting change on the remote node (an origin)
remote_commit_time	timestamp with time zone	Commit timestamp of the transaction that produced the conflicting change on the remote node (an origin)
conflict_type	text	Detected type of the conflict
conflict_resolution	text	Conflict resolution chosen
conflict_index	regclass	Conflicting index (valid only if the index wasn't dropped since)
reloid	oid	Conflicting relation (valid only if the index wasn't dropped since)
nspname	text	Name of the schema for the relation on which the conflict has occurred at the time of conflict (doesn't follow renames)
relname	text	Name of the relation on which the conflict has occurred at the time of conflict (does not follow renames)
key_tuple	json	Json representation of the key used for matching the row
remote_tuple	json	Json representation of an incoming conflicting row
local_tuple	json	Json representation of the local conflicting row
apply_tuple	json	Json representation of the resulting (the one that has been applied) row
local_tuple_xmin	xid	Transaction that produced the local conflicting row (if `local_tuple` is set and the row isn't frozen)
local_tuple_node_id	oid	Node that produced the local conflicting row (if `local_tuple` is set and the row isn't frozen)
local_tuple_commit_time	timestamp with time zone	Last-known-change timestamp of the local conflicting row (if `local_tuple` is set and the row isn't frozen)

`bdr.conflict_history_summary`

A view containing user-readable details on row conflict.

`bdr.conflict_history_summary` columns

Name	Type	Description
nspname	text	Name of the schema
relname	text	Name of the table
origin_node_id	oid	OID (as seen in the pg_replication_origin catalog) of the node that produced the conflicting change
remote_commit_lsn	pg_lsn	Commit LSN of the transaction which produced the conflicting change on the remote node (an origin)
remote_change_nr	oid	Index of the change within its transaction

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
local_time	timestamp with time zone	Local time of the conflict
local_tuple_commit_time	timestamp with time zone	Time of local commit
remote_commit_time	timestamp with time zone	Time of remote commit
conflict_type	text	Type of conflict
conflict_resolution	text	Resolution adopted

`bdr.consensus_kv_data`

A persistent storage for the internal Raft-based KV store used by `bdr.consensus_kv_store()` and `bdr.consensus_kv_fetch()` interfaces.

`bdr.consensus_kv_data` Columns

Name	Type	Description
kv_key	text	Unique key
kv_val	json	Arbitrary value in json format
kv_create_ts	timestamptz	Last write timestamp
kv_ttl	int	Time to live for the value in milliseconds
kv_expire_ts	timestamptz	Expiration timestamp (`kv_create_ts` + `kv_ttl`)

`bdr.crdt_handlers`

This table lists merge ("handlers") functions for all CRDT data types.

`bdr.crdt_handlers` Columns

Name	Type	Description
crdt_type_id	regtype	CRDT data type ID
crdt_merge_id	regproc	Merge function for this data type

`bdr.ddl_replication`

This view lists DDL replication configuration as set up by current DDL filters.

`bdr.ddl_replication` columns

Name	Type	Description
set_ddl_name	name	Name of DDL filter
set_ddl_tag	text	Command tags it applies on (regular expression)
set_ddl_role	text	Roles it applies to (regular expression)
set_name	name	Name of the replication set for which this filter is defined

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.depend`

This table tracks internal object dependencies inside PGD catalogs.

`bdr.failover_replication_slots`

This table tracks the status of logical replication slots that are being used with failover support. For more information on failover replication slots, see CDC Failover support.

`bdr.failover_replication_slots` columns

Name	Type	Description
slot_name	name	Name of the replication slot
slot_id	oid	ID of the replication slot
node_group_id	oid	ID of the node group
plugin	name	Name of the plugin
twophase	boolean	Is the slot used for two-phase commit
active_node	oid	ID of the active node
active_pid	int	PID of the process currently decoding the slot
prev_node	oid	ID of the previous node

`bdr.global_consensus_journal`

This catalog table logs all the Raft messages that were sent while managing global consensus.

As for the `bdr.global_consensus_response_journal` catalog, the payload is stored in a binary encoded format, which can be decoded with the `bdr.decode_message_payload()` function. See the `bdr.global_consensus_journal_details` view for more details.

`bdr.global_consensus_journal` columns

Name	Type	Description
log_index	int8	ID of the journal entry
term	int8	Raft term
origin	oid	ID of node where the request originated
req_id	int8	ID for the request
req_payload	bytea	Payload for the request
trace_context	bytea	Trace context for the request

`bdr.global_consensus_journal_details`

This view presents Raft messages that were sent and the corresponding responses, using the `bdr.decode_message_payload()` function to decode their payloads.

`bdr.global_consensus_journal_details` columns

Name	Type	Description
node_group_name	name	Name of the node group
log_index	int8	ID of the journal entry
term	int8	Raft term

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
request_id	int8	ID of the request
origin_id	oid	ID of the node where the request originated
req_payload	bytea	Payload of the request
origin_node_name	name	Name of the node where the request originated
message_type_no	oid	ID of the PGD message type for the request
message_type	text	Name of the PGD message type for the request
message_payload	text	PGD message payload for the request
response_message_type_no	oid	ID of the PGD message type for the response
response_message_type	text	Name of the PGD message type for the response
response_payload	text	PGD message payload for the response
response_errcode_no	text	SQLSTATE for the response
response_errcode	text	Error code for the response
response_message	text	Error message for the response

`bdr.global_consensus_response_journal`

This catalog table collects all the responses to the Raft messages that were received while managing global consensus.

As for the `bdr.global_consensus_journal` catalog, the payload is stored in a binary-encoded format, which can be decoded with the `bdr.decode_message_payload()` function. See the `bdr.global_consensus_journal_details` view for more details.

`bdr.global_consensus_response_journal` columns

Name	Type	Description
log_index	int8	ID of the journal entry
res_status	oid	Status code for the response
res_payload	bytea	Payload for the response
trace_context	bytea	Trace context for the response

`bdr.global_lock`

This catalog table stores the information needed for recovering the global lock state on server restart.

For monitoring usage, the `bdr.global_locks` view is preferable because the visible rows in `bdr.global_lock` don't necessarily reflect all global locking activity.

Don't modify the contents of this table. It is an important PGD catalog.

`bdr.global_lock` columns

Name	Type	Description
ddl_epoch	int8	DDL epoch for the lock
origin_node_id	oid	OID of the node where the global lock has originated
lock_type	oid	Type of the lock (DDL or DML)
nspname	name	Schema name for the locked relation
relname	name	Relation name for the locked relation
groupid	oid	OID of the top level group (for Advisory locks)
key1	integer	First 32-bit key or lower order 32-bits of 64-bit key (for advisory locks)

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
key2	integer	Second 32-bit key or higher order 32-bits of 64-bit key (for advisory locks)
key_is_bigint	boolean	True if 64-bit integer key is used (for advisory locks)

`bdr.global_locks`

A view containing active global locks on this node. The `bdr.global_locks` view exposes PGD's shared-memory lock state tracking, giving administrators greater insight into PGD's global locking activity and progress.

See Monitoring global locks for more information about global locking.

`bdr.global_locks` columns

Name	Type	Description
origin_node_id	oid	OID of the node where the global lock has originated
origin_node_name	name	Name of the node where the global lock has originated
lock_type	text	Type of the lock (DDL or DML)
relation	text	Locked relation name (for DML locks) or keys (for advisory locks)
pid	int4	PID of the process holding the lock
acquire_stage	text	Internal state of the lock acquisition process
waiters	int4	List of backends waiting for the same global lock
global_lock_request_time	timestamptz	Time this global lock acquire was initiated by origin node
local_lock_request_time	timestamptz	Time the local node started trying to acquire the local lock
last_state_change_time	timestamptz	Time `acquire_stage` last changed

Column details:

- `relation`: For DML locks, `relation` shows the relation on which the DML lock is acquired. For global advisory locks, `relation` column actually shows the two 32-bit integers or one 64-bit integer on which the lock is acquired.
- `origin_node_id` and `origin_node_name`: If these are the same as the local node's ID and name, then the local node is the initiator of the global DDL lock, that is, it is the node running the acquiring transaction. If these fields specify a different node, then the local node is instead trying to acquire its local DDL lock to satisfy a global DDL lock request from a remote node.
- `pid`: The process ID of the process that requested the global DDL lock, if the local node is the requesting node. Null on other nodes. Query the origin node to determine the locker pid.
- `global_lock_request_time`: The timestamp at which the global-lock request initiator started the process of acquiring a global lock. Can be null if unknown on the current node. This time is stamped at the beginning of the DDL lock request and includes the time taken for DDL epoch management and any required flushes of pending-replication queues. Currently only known on origin node.
- `local_lock_request_time`: The timestamp at which the local node started trying to acquire the local lock for this global lock. This includes the time taken for the heavyweight session lock acquire but doesn't include any time taken on DDL epochs or queue flushing. If the lock is reacquired after local node restart, it becomes the node restart time.
- `last_state_change_time`: The timestamp at which the `bdr.global_locks.acquire_stage` field last changed for this global lock entry.

`bdr.group_camo_details`

Uses `bdr.run_on_all_nodes` to gather CAMO-related information from all nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.group_camo_details` columns

Name	Type	Description
node_id	text	Internal node ID
node_name	text	Name of the node
camo_partner	text	Node name of the camo partner
is_camo_partner_connected	text	Connection status
is_camo_partner_ready	text	Readiness status
camo_transactions_resolved	text	Are there any pending and unresolved CAMO transactions
apply_lsn	text	Latest position reported as replayed (visible)
receive_lsn	text	Latest LSN of any change or message received (can go backwards in case of restarts)
apply_queue_size	text	Bytes difference between apply_lsn and receive_lsn

`bdr.group_raft_details`

Uses `bdr.run_on_all_nodes` to gather Raft Consensus status from all nodes.

`bdr.group_raft_details` columns

Name	Type	Description
node_id	oid	Internal node ID
node_name	name	Name of the node
node_group_name	name	Name of the group is part of
state	text	Raft worker state on the node
leader_id	oid	Node id of the RAFT_LEADER
current_term	int	Raft election internal ID
commit_index	int	Raft snapshot internal ID
nodes	int	Number of nodes accessible
voting_nodes	int	Number of nodes voting
protocol_version	int	Protocol version for this node

`bdr.group_replslots_details`

Uses `bdr.run_on_all_nodes` to gather PGD slot information from all nodes.

`bdr.group_replslots_details` columns

Name	Type	Description
node_group_name	text	Name of the PGD group
origin_name	text	Name of the origin node
target_name	text	Name of the target node
slot_name	text	Slot name on the origin node used by this subscription
active	text	Is the slot active (does it have a connection attached to it)
state	text	State of the replication (catchup, streaming, ...) or 'disconnected' if offline
write_lag	interval	Approximate lag time for reported write
flush_lag	interval	Approximate lag time for reported flush
replay_lag	interval	Approximate lag time for reported replay
sent_lag_bytes	int8	Bytes difference between sent_lsn and current WAL write position
write_lag_bytes	int8	Bytes difference between write_lsn and current WAL write position

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
flush_lag_bytes	int8	Bytes difference between flush_lsn and current WAL write position
replay_lag_byte	int8	Bytes difference between replay_lsn and current WAL write position

`bdr.group_subscription_summary`

Uses `bdr.run_on_all_nodes` to gather subscription status from all nodes.

`bdr.group_subscription_summary` columns

Name	Type	Description
origin_node_name	text	Name of the origin of the subscription
target_node_name	text	Name of the target of the subscription
last_xact_replay_timestamp	text	Timestamp of the last replayed transaction
sub_lag_seconds	text	Lag between now and last_xact_replay_timestamp
subscription_status	text	Status of the subscription. Possible values are: `initializing`, `replicating`, `down`, `disabled` and `unknown`

`bdr.group_versions_details`

Uses `bdr.run_on_all_nodes` to gather PGD information from all nodes.

`bdr.group_versions_details` columns

Name	Type	Description
node_id	oid	Internal node ID
node_name	name	Name of the node
postgres_version	text	PostgreSQL version on the node
bdr_version	text	PGD version on the node

`bdr.leader`

Tracks leader nodes across subgroups in the cluster. Shows the status of all write leaders and subscriber-only group leaders (when optimized topology is enabled) in the cluster.

`bdr.leader` columns

Name	Type	Description
node_group_id	oid	ID of the node group.
leader_node_id	oid	ID of the leader node.
generation	int	Generation of the leader node. Leader_kind sets semantics.
leader_kind	"char"	Kind of the leader node.

Leader_kind values can be:

Value	Description
W	Write leader, as per proxy routing. In this case leader is maintained by subgroup Raft instance. `generation` corresponds to `write_leader_version` of respective `bdr.node_group_routing_info` record.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Value	Description
S	Subscriber-only group leader. This designated member of a SO group subscribes to upstream data nodes and is tasked with publishing upstream changes to remaining SO group members. Leader is maintained by top-level Raft instance. `generation` is updated sequentially upon leader change.

`bdr.local_consensus_snapshot`

This catalog table contains consensus snapshots created or received by the local node.

`bdr.local_consensus_snapshot` columns

Name	Type	Description
log_index	int8	ID of the journal entry
log_term	int8	Raft term
snapshot	bytea	Raft snapshot data

`bdr.local_consensus_state`

This catalog table stores the current state of Raft on the local node.

`bdr.local_consensus_state` columns

Name	Type	Description
node_id	oid	ID of the node
current_term	int8	Raft term
apply_index	int8	Raft apply index
voted_for	oid	Vote cast by this node in this term
last_known_leader	oid	node_id of last known Raft leader

`bdr.local_node`

This table identifies the local node in the current database of the current Postgres instance.

`bdr.local_node` columns

Name	Type	Description
node_id	oid	ID of the node
pub_repsets	text[]	Published replication sets
sub_repsets	text[]	Subscribed replication sets
node_uuid	uuid	Globally unique identifier for each BDR node

`bdr.local_node_summary`

A view containing the same information as `bdr.node_summary` (plus `pub_repsets` and `sub_repsets`), but only for the local node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.local_sync_status`

Information about status of either subscription or table synchronization process.

`bdr.local_sync_status` columns

Name	Type	Description
sync_kind	char	Kind of synchronization done
sync_subid	oid	ID of subscription doing the synchronization
sync_nspname	name	Schema name of the synchronized table (if any)
sync_relname	name	Name of the synchronized table (if any)
sync_status	char	Current state of the synchronization
sync_remote_relid	oid	ID of the synchronized table (if any) on the upstream
sync_end_lsn	pg_lsn	Position at which the synchronization state last changed

`bdr.node`

This table lists all the PGD nodes in the cluster.

The view `bdr.node_summary` provides a human-readable version of most of the columns from `bdr.node`.

`bdr.node` columns

Name	Type	Description
node_id	oid	ID of the node
node_name	name	Name of the node
node_group_id	oid	ID of the node group
source_node_id	oid	ID of the source node
synchronize_structure	"char"	Schema synchronization done during the join
node_state	oid	Consistent state of the node
target_state	oid	State that the node is trying to reach (during join or promotion)
seq_id	int4	Sequence identifier of the node used for generating unique sequence numbers
dbname	name	Database name of the node
node_dsn	char	Connection string for the node
proto_version_ranges	int[]	Supported protocol version ranges by the node
generation	smallint	Counter incremented when a node joins with the same name as a previous node
node_kind	oid	ID of the node kind
node_join_finished	boolean	Check if the join is finished
node_uuid	uuid	Globally unique identifier for each BDR node

`bdr.node_catchup_info`

This catalog table records relevant catchup information on each node, either if it is related to the join or part procedure.

`bdr.node_catchup_info` columns

Name	Type	Description
node_id	oid	ID of the node
node_source_id	oid	ID of the node used as source for the data

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
slot_name	name	Slot used for this source
min_node_lsn	pg_lsn	Minimum LSN at which the node can switch to direct replay from a peer node
catchup_state	oid	Status code of the catchup state
origin_node_id	oid	ID of the node from which we want transactions

If a node(node_id) needs missing data from a parting node(origin_node_id), it can get it from a node that already has it(node_source_id) by forwarding. The records in this table persists until the node(node_id) is a member of the EDB Postgres Distributed cluster.

`bdr.node_catchup_info_details`

A view of `bdr.node_catchup_info` catalog which shows info in more friendly way

`bdr.node_conflict_resolvers`

Currently configured conflict resolution for all known conflict types.

`bdr.node_conflict_resolvers` columns

Name	Type	Description
conflict_type	text	Type of the conflict
conflict_resolver	text	Resolver used for this conflict type

`bdr.node_group`

This catalog table lists all the PGD node groups. See also `bdr.node_group_summary` for a view containing user-readable details.

`bdr.node_group` columns

Name	Type	Description
node_group_id	oid	ID of the node group
node_group_name	name	Name of the node group
node_group_default_repset	oid	Default replication set for this node group
node_group_default_repset_ext	oid	Default replication set for this node group
node_group_parent_id	oid	ID of parent group (0 if this is a root group)
node_group_flags	int	Group flags
node_group_uuid	uuid	The uuid of the group
node_group_apply_delay	interval	How long a subscriber waits before applying changes from the provider
node_group_check_constraints	bool	Whether the apply process checks constraints when applying data
node_group_num_writers	int	Number of writers to use for subscriptions backing this node group
node_group_enable_wal_decoder	bool	Whether the group has enable_wal_decoder set
node_group_streaming_mode	char	Transaction streaming setting: 'O' - off, 'F' - file, 'W' - writer, 'A' - auto, 'D' - default
node_group_default_commit_scope	oid	ID of the node group's default commit scope
node_group_location	char	Name of the location associated with the node group
node_group_enable_proxy_routing	char	Whether the node group allows routing from `pgd-proxy`
node_group_enable_raft	bool	Whether the node group allows Raft Consensus

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.node_group_replication_sets`

A view showing default replication sets create for PGD groups. See also `bdr.replication_sets`.

`bdr.node_group_replication_sets` columns

Name	Type	Description
node_group_name	name	Name of the PGD group
def_repset	name	Name of the default repset
def_repset_ops	text[]	Actions replicated by the default repset
def_repset_ext	name	Name of the default "external" repset (usually same as def_repset)
def_repset_ext_ops	text[]	Actions replicated by the default "external" repset (usually same as def_repset_ops)

`bdr.node_group_summary`

A view containing user-readable details about node groups. See also `bdr.node_group`.

`bdr.node_group_summary` columns

Name	Type	Description
node_group_name	name	Name of the node group
default_repset	name	Default replication set for this node group
parent_group_name	name	Name of parent group (NULL if this is a root group)
node_group_type	text	Type of the node group (one of "global", "data", "shard" or "subscriber-only")
apply_delay	interval	How long a subscriber waits before applying changes from the provider
check_constraints	boolean	Whether the apply process checks constraints when applying data
num_writers	integer	Number of writers to use for subscriptions backing this node group
enable_wal_decoder	boolean	Whether the group has enable_wal_decoder set
streaming_mode	text	Transaction streaming setting: "off", "file", "writer", "auto" or "default"
default_commit_scope	name	Name of the node group's default commit scope
location	name	Name of the location associated with the node group
enable_proxy_routing	boolean	Whether the node group allows routing from `pgd-proxy`
enable_raft	boolean	Whether the node group allows Raft Consensus
route_writer_max_lag	bigint	Maximum write lag accepted
route_reader_max_lag	bigint	Maximum read lag accepted
route_writer_wait_flush	boolean	Switch if we need to wait for the flush

`bdr.node_local_info`

A catalog table used to store per-node configuration that's specific to the local node (as opposed to global view of per-node configuration).

`bdr.node_local_info` columns

Name	Type	Description
node_id	oid	The OID of the node (including the local node)
applied_state	oid	Internal ID of the node state
ddl_epoch	int8	Last epoch number processed by the node

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
slot_name	name	Name of the slot used to connect to that node (NULL for the local node)
origin_name	name	Name of the replication origin for that node. It will be NULL for the local node or for nodes that are not data nodes such as subscriber-only nodes or standbys.

`bdr.node_log_config`

A catalog view that stores information on the conflict logging configurations.

`bdr.node_log_config` columns

Name	Description
log_name	Name of the logging configuration
log_to_file	Whether it logs to the server log file
log_to_table	Whether it logs to a table, and which table is the target
log_conflict_type	Which conflict types it logs, if NULL means all
log_conflict_res	Which conflict resolutions it logs, if NULL means all

`bdr.node_peer_progress`

Catalog used to keep track of every node's progress in the replication stream. Every node in the cluster regularly broadcasts its progress every `bdr.replay_progress_frequency` milliseconds to all other nodes (default is 60000 ms, that is, 1 minute). Expect N * (N-1) rows in this relation.

You might be more interested in the `bdr.node_slots` view for monitoring purposes. See also Monitoring.

`bdr.node_peer_progress` columns

Name	Type	Description
node_id	oid	OID of the originating node that reported this position info
peer_node_id	oid	OID of the node's peer (remote node) for which this position info was reported
last_update_sent_time	timestamptz	Time at which the report was sent by the originating node
last_update_recv_time	timestamptz	Time at which the report was received by the local server
last_update_node_lsn	pg_lsn	LSN on the originating node at the time of the report
peer_position	pg_lsn	Latest LSN of the node's peer seen by the originating node
peer_replay_time	timestamptz	Latest replay time of peer seen by the reporting node
last_update_horizon_xid	oid	Internal resolution horizon: all lower xids are known resolved on the reporting node
last_update_horizon_lsn	pg_lsn	Internal resolution horizon: same in terms of an LSN of the reporting node

`bdr.node_replication_rates`

This view contains information about outgoing replication activity from a given node.

`bdr.node_replication_rates` columns

Column	Type	Description
peer_node_id	oid	OID of node's peer (remote node) for which this info was reported
target_name	name	Name of the target peer node
sent_lsn	pg_lsn	Latest sent position

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Column	Type	Description
replay_lsn	pg_lsn	Latest position reported as replayed (visible)
replay_lag	interval	Approximate lag time for reported replay
replay_lag_bytes	int8	Bytes difference between replay_lsn and current WAL write position on origin
replay_lag_size	text	Human-readable bytes difference between replay_lsn and current WAL write position
apply_rate	bigint	LSNs being applied per second at the peer node
catchup_interval	interval	Approximate time required for the peer node to catch up to all the changes that are yet to be applied

> **Note**
>
> The `replay_lag` is set immediately to zero after reconnect. As a workaround, use `replay_lag_bytes`, `replay_lag_size`, or `catchup_interval`.

`bdr.node_slots`

This view contains information about replication slots used in the current database by PGD.

See Monitoring outgoing replication for guidance on the use and interpretation of this view's fields.

`bdr.node_slots` columns

Name	Type	Description
target_dbname	name	Database name on the target node
node_group_name	name	Name of the PGD group
node_group_id	oid	OID of the PGD group
origin_name	name	Name of the origin node
target_name	name	Name of the target node
origin_id	oid	OID of the origin node
target_id	oid	OID of the target node
local_slot_name	name	Name of the replication slot according to PGD
slot_name	name	Name of the slot according to Postgres (same as above)
is_group_slot	boolean	True if the slot is the node-group crash recovery slot for this node (see ["Group Replication Slot"](nodes#Group Replication Slot))
is_decoder_slot	boolean	Is this slot used by the decoding worker feature
plugin	name	Logical decoding plugin using this slot (should be pglogical_output or bdr)
slot_type	text	Type of the slot (should be logical)
datoid	oid	OID of the current database
database	name	Name of the current database
temporary	bool	Is the slot temporary
active	bool	Is the slot active (does it have a connection attached to it)
active_pid	int4	PID of the process attached to the slot
xmin	xid	XID needed by the slot
catalog_xmin	xid	Catalog XID needed by the slot
restart_lsn	pg_lsn	LSN at which the slot can restart decoding
confirmed_flush_lsn	pg_lsn	Latest confirmed replicated position
usesysid	oid	sysid of the user the replication session is running as
usename	name	username of the user the replication session is running as
application_name	text	Application name of the client connection (used by `synchronous_standby_names`)
client_addr	inet	IP address of the client connection
client_hostname	text	Hostname of the client connection

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
client_port	int4	Port of the client connection
backend_start	timestamptz	When the connection started
state	text	State of the replication (catchup, streaming, ...) or 'disconnected' if offline
sent_lsn	pg_lsn	Latest sent position
write_lsn	pg_lsn	Latest position reported as written
flush_lsn	pg_lsn	Latest position reported as flushed to disk
replay_lsn	pg_lsn	Latest position reported as replayed (visible)
write_lag	interval	Approximate lag time for reported write
flush_lag	interval	Approximate lag time for reported flush
replay_lag	interval	Approximate lag time for reported replay
sent_lag_bytes	int8	Bytes difference between sent_lsn and current WAL write position
write_lag_bytes	int8	Bytes difference between write_lsn and current WAL write position
flush_lag_bytes	int8	Bytes difference between flush_lsn and current WAL write position
replay_lag_bytes	int8	Bytes difference between replay_lsn and current WAL write position
sent_lag_size	text	Human-readable bytes difference between sent_lsn and current WAL write position
write_lag_size	text	Human-readable bytes difference between write_lsn and current WAL write position
flush_lag_size	text	Human-readable bytes difference between flush_lsn and current WAL write position
replay_lag_size	text	Human-readable bytes difference between replay_lsn and current WAL write position

> **Note**
>
> While a peer is reconnecting and replication isn't yet in the `streaming` state, such as during catch-up, `write_lag`, `flush_lag`, and `replay_lag` report an estimate based on the time elapsed since the slot's last confirmed flush. Once the state becomes `streaming`, they report the measured lag.

`bdr.node_summary`

This view contains summary information about all PGD nodes known to the local node.

`bdr.node_summary` columns

Name	Type	Description
node_name	name	Name of the node
node_group_name	name	Name of the PGD group the node is part of
interface_connstr	text	Connection string to the node
peer_state_name	text	Consistent state of the node in human readable form
peer_target_state_name	text	State that the node is trying to reach (during join or promotion)
node_seq_id	int4	Sequence identifier of the node used for generating unique sequence numbers
node_local_dbname	name	Database name of the node
node_id	oid	OID of the node
node_group_id	oid	OID of the PGD node group
node_kind_name	oid	Node kind name
node_uuid	uuid	Globally unique identifier for each BDR node

`bdr.queue`

This table stores the historical record of replicated DDL statements.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.queue` columns

Name	Type	Description
queued_at	timestamptz	When was the statement queued
role	name	Which role has executed the statement
replication_sets	text[]	Which replication sets was the statement published to
message_type	char	Type of a message. Possible values: A - Table sync D - DDL S - Sequence T - Truncate Q - SQL statement
message	json	Payload of the message needed for replication of the statement

`bdr.raft_instances`

Lists the local Raft consensus instance for each top-level node group. There is currently always exactly one Raft instance per top-level group.

`bdr.raft_instances` columns

Name	Type	Description
instance_id	oid	OID of the Raft instance
node_group_id	oid	OID of the top-level node group

`bdr.replication_set`

A table that stores replication set configuration. For user queries, we recommend instead checking the `bdr.replication_sets` view.

`bdr.replication_set` columns

Name	Type	Description
set_id	oid	OID of the replication set
set_nodeid	oid	OID of the node (always local node oid currently)
set_name	name	Name of the replication set
replicate_insert	boolean	Indicates if the replication set replicates INSERTs
replicate_update	boolean	Indicates if the replication set replicates UPDATEs
replicate_delete	boolean	Indicates if the replication set replicates DELETEs
replicate_truncate	boolean	Indicates if the replication set replicates TRUNCATEs
set_isinternal	boolean	Reserved
set_autoadd_tables	boolean	Indicates if new tables are automatically added to this replication set
set_autoadd_seqs	boolean	Indicates if new sequences are automatically added to this replication set

`bdr.replication_set_table`

A table that stores replication set table membership. For user queries, we recommend instead checking the `bdr.tables` view.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.replication_set_table` columns

Name	Type	Description
set_id	oid	OID of the replication set
set_reloid	regclass	Local ID of the table
set_att_list	text[]	Reserved
set_row_filter	pg_node_tree	Compiled row filtering expression

`bdr.replication_set_ddl`

A table that stores replication set ddl replication filters. For user queries, we recommend instead checking the `bdr.ddl_replication` view.

`bdr.replication_set_ddl` Columns

Name	Type	Description
set_id	oid	OID of the replication set
set_ddl_name	name	Name of the DDL filter
set_ddl_tag	text	Command tag for the DDL filter
set_ddl_role	text	Role executing the DDL

`bdr.replication_sets`

A view showing replication sets defined in the PGD group, even if they aren't currently used by any node.

`bdr.replication_sets` columns

Name	Type	Description
set_id	oid	OID of the replication set
set_name	name	Name of the replication set
replicate_insert	boolean	Indicates if the replication set replicates INSERTs
replicate_update	boolean	Indicates if the replication set replicates UPDATEs
replicate_delete	boolean	Indicates if the replication set replicates DELETEs
replicate_truncate	boolean	Indicates if the replication set replicates TRUNCATEs
set_autoadd_tables	boolean	Indicates if new tables are automatically added to this replication set
set_autoadd_seqs	boolean	Indicates if new sequences are automatically added to this replication set

`bdr.replication_status`

A view showing the connection and replay status of each subscription on the local node, joined with the origin and target node names. Useful for checking whether replication from a given peer node is currently connected or blocked.

`bdr.replication_status` columns

Name	Type	Description
node_id	oid	OID of the target (local) node
node_name	name	Name of the target (local) node
origin_node_id	oid	OID of the origin node the subscription replicates from

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
origin_node_name	name	Name of the origin node the subscription replicates from
sub_id	oid	OID of the subscription
sub_name	name	Name of the subscription
connected	boolean	Whether the subscription is currently connected to the origin node
replication_blocked	boolean	Whether replication appears blocked (retries at the same LSN with no commits in progress)
connect_time	timestamptz	Time the current connection was established, if connected
disconnect_time	timestamptz	Time of the last disconnect, if currently disconnected
uptime	interval	How long the current connection has been up, if connected

`bdr.schema_changes`

A simple view to show all the changes to schemas win PGD.

`bdr.schema_changes` columns

Name	Type	Description
schema_changes_ts	timestampstz	ID of the trigger
schema_changes_change	char	Flag of change type
schema_changes_classid	oid	Class ID
schema_changes_objectid	oid	Object ID
schema_changes_subid	smallint	Subscription
schema_changes_descr	text	Object changed
schema_changes_addrnames	text[]	Location of schema change

`bdr.sequence_alloc`

A view to see the allocation details for galloc sequences.

`bdr.sequence_alloc` columns

Name	Type	Description
seqid	regclass	ID of the sequence
seq_chunk_size	bigint	A sequence number for the chunk within its value
seq_allocated_up_to	bigint	
seq_nallocs	bigint	
seq_last_alloc	timestamptz	Last sequence allocated

`bdr.sequences`

This view lists all sequences with their kind, excluding sequences for internal PGD bookkeeping.

`bdr.sequences` columns

Name	Type	Description
nspname	name	Namespace containing the sequence
relname	name	Name of the sequence
seqkind	text	Type of the sequence ('local', 'timeshard', 'galloc')

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.stat_activity`

Dynamic activity for each backend or worker process.

This contains the same information as `pg_stat_activity`, except `wait_event` is set correctly when the wait relates to PGD.

`bdr.stat_commit_scope`

A view containing statistics for each commit scope.

`bdr.stat_commit_scope` columns

Column	Type	Description
commit_scope_name	name	Name of the commit scope
group_name	name	Name of group for which the commit scope is defined
ncalls	bigint	The number of times the commit scope was used
ncommits	bigint	The number of successful commits were made with the commit scope
naborts	bigint	The number of times the commit scope used was eventually aborted
total_commit_time	double precision	Total time spent committing using the commit scope, in milliseconds
min_commit_time	double precision	Minimum time spent committing using the commit scope, in milliseconds
max_commit_time	double precision	Maximum time spend committing using the commit scope, in milliseconds
mean_commit_time	double precision	Mean time spent committing using the commit scope, in milliseconds
stats_reset	timestamp with time zone	Time at which all statistics in the view were last reset

`bdr.stat_commit_scope_state`

A view of information about the current use of commit scopes by backends.

`bdr.stat_commit_scope_state` columns

Column	Type	Description
pid	integer	Process ID of the backend
commit_scope_name	name	Name of the commit scope being used
group_name	name	Name of group for which the commit scope is defined
waiting_op_num	integer	Index of the first operation in the commit scope that is not satisfied yet
waiting_prepare_confirmations	integer	The number of PREPARE confirmations that are still needed by the operation
waiting_commit_confirmations	integer	The number of COMMIT confirmations that are still needed by the operation
waiting_lsn_confirmations	integer	The number of LSN confirmations that are still needed by the operation

`bdr.stat_raft_followers_state`

A view of the state of the raft leader's followers on the Raft leader node (empty on other nodes).

`bdr.stat_raft_followers_state` columns

Column	Type	Description
group_name	name	The group this information is for (each group can have a separate consensus configured)

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Column	Type	Description
node_name	name	Name of the follower node
sent_commit_index	bigint	Latest Raft index sent to the follower node
match_index	bigint	Raft index we expect to match the next response from the follower node
last_message_time	timestamp with time zone	Last message (any, including requests) seen from the follower node
last_heartbeat_send_time	timestamp with time zone	Last time the leader sent heartbeat to the follower node
last_heartbeat_response_time	Lasat time the leader has seen a heartbeat response from the follower node	
approx_clock_drift_ms	bigint	Approximate clock drift seen by the leader against the follower node in milliseconds

`bdr.stat_raft_state`

A view describing the state of the Raft consensus on the local node.

`bdr.stat_raft_state` columns

Column	Type	Description
group_name	name	The group this information is for (each group can have a separate consensus configured)
raft_stat	text	State of the local node in the Raft ('LEADER', 'CANDIDATE', 'FOLLOWER', 'STOPPED')
leader_name	name	Name of the Raft leader, if any
voted_for_name	name	The node the local node voted for as leader last vote
is_voting	boolean	The local node part of Raft is voting
heartbeat_timeout_ms	bigint	The heartbeat timeout on the local node
heartbeat_elapsed_ms	bigint	The number of milliseconds that have elapsed since the local node has seen a heartbeat from the leader
current_term	bigint	The current Raft term the local node is at
commit_index	bigint	The current Raft commit index the local node is at
apply_index	bigint	The Raft commit index the local node applied to catalogs
last_log_term	bigint	Last Raft term in the request log
last_log_index	bigint	Last Raft index in the request log
oldest_log_index	bigint	Oldest Raft index still in the request log
newest_prunable_log_index	bigint	Newest Raft index that can be safely removed from the request log
snapshot_term	bigint	Raft term of the last snapshot
snapshot_index	bigint	Raft index of the last snapshot
nnodes	integer	Number of nodes in the Raft consensus (should normally be the same as the number of nodes in the group)
nvoting_nodes	integer	Number of voting nodes in the Raft consensus

`bdr.stat_receiver`

A view containing all the necessary info about the replication subscription receiver processes.

`bdr.stat_receiver` columns

Column	Type	Description
worker_role	text	Role of the BDR worker (always 'receiver')
worker_state	text	State of receiver worker (can be 'running', 'down', or 'disabled')
worker_pid	integer	Process id of the receiver worker

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Column	Type	Description
sub_name	name	Name of the subscription the receiver belongs to
sub_slot_name	name	Replication slot name used by the receiver
source_name	name	Source node for this receiver (the one it connects to), this is normally the same as the origin node, but is different for forward mode subscriptions
origin_name	name	The origin node for this receiver (the one it receives forwarded changes from), this is normally the same as the source node, but is different for forward mode subscriptions
subscription_mode	char	Mode of the subscription, see `bdr.subscription_summary` for more details
sub_replication_sets	text[]	Replication sets this receiver is subscribed to
sub_apply_delay	interval	Apply delay interval
receive_lsn	pg_lsn	LSN of the last change received so far
receive_commit_lsn	pg_lsn	LSN of the last commit received so far
xact_apply_lsn	pg_lsn	Last applied transaction LSN
xact_flush_lsn	pg_lsn	Last flushed transaction LSN
xact_apply_timestamp	timestamp with time zone	Last applied transaction (commit) timestamp
worker_start	timestamp with time zone	Time at which the receiver started
worker_xact_start	timestamp with time zome	Time at which the receiver started local db transaction (if it is currently processing a local transaction), usually NULL, see `xact_start` in `pg_stat_activity` for more details
worker_backend_state_change	timestamp with time zone	Backend state change timestamp, see `state_change` in `pg_stat_activity` for more details
worker_backend_state	text	Current backend state, see `state` in `pg_stat_activity` for more details
wait_event_type	text	Type of wait event the receiver is currently waiting on (if any), see `wait_event_type` in `pg_stat_activity` for more details
wait_event	text	Exact event the receiver is currently waiting on (if any, see `wait_event` in `pg_stat_activity` for more details)

`bdr.stat_relation`

Shows apply statistics for each relation. Contains data only if tracking is enabled with `bdr.track_relation_apply` and if data was replicated for a given relation.

`lock_acquire_time` is updated only if `bdr.track_apply_lock_timing` is set to `on` (default: `off`).

You can reset the stored relation statistics by calling `bdr.reset_relation_stats()`.

`bdr.stat_relation` columns

Column	Type	Description
nspname	name	Name of the relation's schema
relname	name	Name of the relation
relid	oid	OID of the relation
total_time	double precision	Total time spent processing replication for the relation, in milliseconds
ninsert	bigint	Number of inserts replicated for the relation
nupdate	bigint	Number of updates replicated for the relation
ndelete	bigint	Number of deletes replicated for the relation
ntruncate	bigint	Number of truncates replicated for the relation
shared_blks_hit	bigint	Total number of shared block cache hits for the relation
shared_blks_read	bigint	Total number of shared blocks read for the relation
shared_blks_dirtied	bigint	Total number of shared blocks dirtied for the relation
shared_blks_written	bigint	Total number of shared blocks written for the relation

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Column	Type	Description
blk_read_time	double precision	Total time spent reading blocks for the relation, in milliseconds (if `track_io_timing` is enabled, otherwise zero)
blk_write_time	double precision	Total time spent writing blocks for the relation, in milliseconds (if `track_io_timing` is enabled, otherwise zero)
lock_acquire_time	double precision	Total time spent acquiring locks on the relation, in milliseconds (if `bdr.track_apply_lock_timing` is enabled, otherwise zero)
stats_reset	timestamp with time zone	Time of the last statistics reset (performed by `bdr.reset_relation_stats()`)

`bdr.stat_routing_candidate_state`

A view of information about the routing candidate nodes on the Raft leader (empty on other nodes).

`bdr.stat_routing_candidate_state` columns

Column	Type	Description
node_group_name	name	The group this information is for (each group can have a separate routing proxy)
node_name	name	Candidate node name
node_route_fence	boolean	The node is fenced (when true it cannot become leader or read-only connection target)
node_route_reads	boolean	The node is being considered as a read-only connection target
node_route_writes	boolean	The node is being considered as a write lead candidate.
last_message_time	timestamp with time zone	The time of the last Raft message (any, including requests) seen by this node (used to check liveness of node)

`bdr.stat_routing_state`

A view of the state of the connection routing which PGD Proxy uses to route the connections.

`bdr.stat_routing_state` columns

Column	Type	Description
node_group_name	name	The group this is information for (each group can have a separate routing proxy)
write_lead_name	name	Name of the write lead node
previous_write_lead_name	name	Name of the previous write lead node
read_names	name[]	Array of nodes to which read-only connections are routed
write_candidate_names	name[]	Nodes that match all criteria needed to become write lead in case of failover
read_candidate_names	name[]	Nodes that match all criteria needed to become read-only connection targets in case of failover

`bdr.stat_subscription`

Shows apply statistics for each subscription. Contains data only if tracking is enabled with `bdr.track_subscription_apply`.

You can reset the stored subscription statistics by calling `bdr.reset_subscription_stats()`.

`bdr.stat_subscription` columns

Column	Type	Description
sub_name	name	Name of the subscription
subid	oid	OID of the subscription

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Column	Type	Description
mean_apply_time	double precision	Average time per apply transaction, in milliseconds
nconnect	bigint	Number of times this subscription has connected upstream
ncommit	bigint	Number of commits this subscription did
nabort	bigint	Number of aborts writer did for this subscription
nerror	bigint	Number of errors writer has hit for this subscription
nskippedtx	bigint	Number of transactions skipped by writer for this subscription (due to `skip_transaction` conflict resolver)
ninsert	bigint	Number of inserts this subscription did
nupdate	bigint	Number of updates this subscription did
ndelete	bigint	Number of deletes this subscription did
ntruncate	bigint	Number of truncates this subscription did
nddl	bigint	Number of DDL operations this subscription has executed
ndeadlocks	bigint	Number of errors that were caused by deadlocks
nretries	bigint	Number of retries the writer did (without going for full restart/reconnect)
nstream_writer	bigint	Number of transactions streamed to writer
nstream_file	bigint	Number of transactions streamed to file
nstream_commit	bigint	Number of streaming transactions committed
nstream_abort	bigint	Number of streaming transactions aborted
nstream_start	bigint	Number of STREAM START messages processed
nstream_stop	bigint	Number of STREAM STOP messages processed
nstream_commit	bigint	Number of streaming transactions committed
nstream_abort	bigint	Number of streaming transactions aborted
nstream_prepare	bigint	Number of streaming transactions prepared
nstream_insert	bigint	Number of streaming inserts processed
nstream_update	bigint	Number of streaming updates processed
nstream_delete	bigint	Number of streaming deletes processed
nstream_truncate	bigint	Number of streaming truncates processed
shared_blks_hit	bigint	Total number of shared block cache hits by the subscription
shared_blks_read	bigint	Total number of shared blocks read by the subscription
shared_blks_dirtied	bigint	Total number of shared blocks dirtied by the subscription
shared_blks_written	bigint	Total number of shared blocks written by the subscription
blk_read_time	double precision	Total time the subscription spent reading blocks, in milliseconds (if `track_io_timing` is enabled, otherwise zero)
blk_write_time	double precision	Total time the subscription spent writing blocks, in milliseconds (if `track_io_timing` is enabled, otherwise zero)
connect_time	timestamp with time zone	Time when the current upstream connection was established, NULL if not connected
last_disconnect_time	timestamp with time zone	Time when the last upstream connection was dropped
start_lsn	pg_lsn	LSN from which this subscription requested to start replication from the upstream
retries_at_same_lsn	bigint	Number of attempts the subscription was restarted from the same LSN value
curr_ncommit	bigint	Number of commits this subscription did after the current connection was established
npre_commit_confirmations	bigint	Number of precommit confirmations by CAMO partners
npre_commit	bigint	Number of precommits
ncommit_prepared	bigint	Number of prepared transaction commits
nabort_prepared	bigint	Number of prepared transaction aborts
nprovisional_waits	bigint	Number of update/delete operations on same tuples by concurrent apply transactions. These are provisional waits. See Parallel Apply
ntuple_waits	bigint	Number of update/delete operations that waited to be safely applied. See Parallel Apply
ncommit_waits	bigint	Number of fully applied transactions that had to wait before being committed. See Parallel Apply

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Column	Type	Description
stats_reset	timestamp with time zone	Time of the last statistics reset (performed by `bdr.reset_subscription_stats()`)

`bdr.stat_worker`

A view containing summary information and per worker statistics for PGD manager workers.

`bdr.stat_worker` columns

Column	Type	Description
worker_role	text	Role of the BDR worker
worker_pid	integer	Process id of the worker
sub_name	name	Name of the subscription the worker is related to, if any
worker_start	timestamp with time zone	Time at which the worker started
worker_xact_start	timestamp with time zone	Time at which the worker started the local db transaction, see `xact_start` in `pg_stat_activity` for more details
worker_xid	xid	Transaction id of the worker, see `backend_xid` in `pg_stat_activity` for more details
worker_xmin	xid	Oldest transaction id needed by the worker, see `backend_xmin` in `pg_stat_activity` for more details
worker_backend_state_change	timestamp with time zone	Backend state change timestamp see `state_change` in `pg_stat_activity` for more details
worker_backend_state	text	Current backend state see `state` in `pg_stat_activity` for more details
wait_event_type	text	The type of wait event the worker is currently waitiing on, if any (see `wait_event_type` in `pg_stat_activity` for more details)
wait_event	text	The exact event the worker is waiting on, if any (see `wait_event` in `pg_stat_activity` for more details)
blocked_by_pids	integer[]	List of PIDs blocking the worker, if any
query	text	Query currently being run by the worker
worker_query_start	timestamp with time zone	Timestamp at which the current query run by the worker started

`bdr.stat_writer`

A view containing summary information and statistics for each subscription replication writer. There can be multiple writers for each subscription.

`bdr.stat_writer` columns

Column	Type	Description
worker_role	text	Role of the BDR worker (always 'writer')
worker_state	text	State of the worker (can be 'running', 'down', or 'disabled')
worker_pid	integer	Process id of the writer
sub_name	name	Name of the subscription the writer belongs to
writer_nr	integer	Writer index in the writer group for the same subscription
nxacts	bigint	The number of transactions the writer has processed since start
ncommits	bigint	The number of commits the writer processed since start
naborts	bigint	The number of aborts the writer processed since start
commit_queue_position	integer	Position in the commit queue, when serializing transactions against other writers in the same writer group
xact_source_xid	xid	Transaction id of the currently processed transaction on the source node
xact_source_commit_lsn	pg_lsn	LSN of the currently processed transaction on the source node

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Column	Type	Description
xact_nchanges	bigint	The number of changes in the currently processed transaction that have been written (updated every 1000 changes)
xact_origin_node_name	name	Origin node of the currently processed transaction
xact_origin_lsn	pg_lsn	Origin LSN of the currently processed transaction
xact_origin_timestamp	timestamp with time zone	Origin commit timestamp of the currently processed transaction
streaming_allowed	boolean	The writer can receive direct stream for large transactions
is_streaming	boolean	The writer is currently receiving a direct stream of a large transaction
nstream_file	bigint	The number of stream files the writer has processed
nstream_writer	bigint	The number of directly streamed transactions the writer has processed
worker_start	timestamp with time zone	The time at which the writer started
worker_xact_start	timestamp with time zone	The time at which the writer start the local db transaction (see xact_start in `pg_stat_activity` for more details)
worker_xid	xid	Transaction id of the worker (see `backend_xid` in `pg_stat_activity` for more details)
worker_xmin	xid	Oldest transaction id needed by the worker (see `backend_xmin` in `pg_stat_activity` for more details)
worker_backend_state_change	timestamp with time zone	Backend state change timestamp (see `state_change` in `pg_stat_activity` for more details)
worker_backend_state	text	Current backend state (see `state` in `pg_stat_activity` for more details)
wait_event_type	text	The type of wait event the writer is currently waiting on, if any (see `event_type` in `pg_stat_activity` for more details)
wait_event	text	The exact event the writer is waiting on, if any (see `wait_event` in `pg_stat_activity` for more details)
blocked_by_pids	integer[]	List of PIDs blocking the writer, if any
query	text	Query currently being run by the writer (normally only set for DDL)
worker_query_start	timestamp with time zone	Timestamp at which the current query run by the worker started
command_progress_cmdtag	text	For commands with progress tracking, identifies the command current processed by the writer (can be one of 'CREATE INDEX', 'CREATE INDEX CONCURRENTLY', 'REINDEX', 'REINDEX CONCURRENTLY', 'CLUSTER', and 'VACUUM FULL')
command_progress_relation	text	For commands with progress tracking, identifies therelation which the command is working on
command_progress_phase	text	For commands with progress tracking, name of the current phase the command is in, refer toProgress Reporting in the Postgres documentation for details
command_progress_count	integer	For commands with progress tracking, the number of phases this command has gone through
command_progress_phase_nr	integer	For commands with progress tracking, the number of the phase of `command_progress_count`
command_progress_phase_tuples_total	real	For commands with progress tracking, the number of rows the current phase of the command has to process (if the phase is process rows)
command_progress_tuples_done	bigint	For commands with progress tracking, the number of rows the current phase of the command has already processed (if the phase is process rows)

`bdr.subscription`

This catalog table lists all the subscriptions owned by the local PGD node and their modes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.subscription` columns

Name	Type	Description
sub_id	oid	ID of the subscription
sub_name	name	Name of the subscription
nodegroup_id	oid	ID of nodegroup
origin_node_id	oid	ID of origin node
source_node_id	oid	ID of source node
target_node_id	oid	ID of target node
subscription_mode	char	Mode of subscription
sub_enabled	bool	Whether the subscription is enabled (should be replication)
apply_delay	interval	How much behind should the apply of changes on this subscription be (normally 0)
slot_name	name	Slot on upstream used by this subscription
origin_name	name	Local origin used by this subscription
num_writers	int	Number of writer processes this subscription uses
streaming_mode	char	Streaming configuration for the subscription
replication_sets	text[]	Replication sets replicated by this subscription (NULL = all)
forward_origin	text[]	Origins forwarded by this subscription (NULL = all)

`bdr.subscription_summary`

This view contains summary information about all PGD subscriptions that the local node has to other nodes.

`bdr.subscription_summary` columns

Name	Type	Description
node_group_name	name	Name of the PGD group the node is part of
sub_name	name	Name of the subscription
origin_name	name	Name of the origin node
target_name	name	Name of the target node (normally local node)
sub_enabled	bool	Is the subscription enabled
sub_slot_name	name	Slot name on the origin node used by this subscription
sub_replication_sets	text[]	Replication sets subscribed
sub_forward_origins	text[]	Does the subscription accept changes forwarded from other nodes besides the origin
sub_apply_delay	interval	Delay transactions by this much compared to the origin
sub_origin_name	name	Replication origin name used by this subscription
bdr_subscription_mode	char	Subscription mode
subscription_status	text	Status of the subscription worker
node_group_id	oid	OID of the PGD group the node is part of
sub_id	oid	OID of the subscription
origin_id	oid	OID of the origin node
target_id	oid	OID of the target node
receive_lsn	pg_lsn	Latest LSN of any change or message received (this can go backwards in case of restarts)
receive_commit_lsn	pg_lsn	Latest LSN of last COMMIT received (this can go backwards in case of restarts)
last_xact_replay_lsn	pg_lsn	LSN of last transaction replayed on this subscription
last_xact_flush_lsn	timestamptz	LSN of last transaction replayed on this subscription that's flushed durably to disk
last_xact_replay_timestamp	timestamptz	Timestamp of last transaction replayed on this subscription

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.tables`

This view lists information about table membership in replication sets. If a table exists in multiple replication sets, it appears multiple times in this table.

`bdr.tables` columns

Name	Type	Description
relid	oid	OID of the relation
nspname	name	Name of the schema relation is in
relname	name	Name of the relation
set_name	name	Name of the replication set
set_ops	text[]	List of replicated operations
rel_columns	text[]	List of replicated columns (NULL = all columns) (*)
row_filter	text	Row filtering expression
conflict_detection	text	Conflict detection method used: row_origin (default), row_version or column_level

(*) These columns are reserved for future use and should currently be NULL

`bdr.taskmgr_work_queue`

Contains work items created and processed by task manager. The work items are created on only one node and processed on different nodes.

`bdr.taskmgr_work_queue` columns

Column	Type	Description
ap_wq_workid	bigint	Unique ID of the work item
ap_wq_ruleid	int	ID of the rule listed in autopartition_rules. Rules are specified using bdr.autopartition command
ap_wq_relname	name	Name of the relation the task belongs to
ap_wq_relnamespace	name	Name of the tablespace specified in rule for this work item
ap_wq_partname	name	Name of the partition created by the workitem
ap_wq_work_category	char	Work category; can be `c` (create partition), `m` (migrate partition), `d` (drop partition), or `a` (alter partition)
ap_wq_work_sql	text	SQL query for the work item
ap_wq_work_depends	Oid[]	OIDs of the nodes on which the work item depends

`bdr.taskmgr_workitem_status`

The status of the work items that is updated locally on each node.

`bdr.taskmgr_workitem_status` columns

Column	Type	Description
ap_wi_workid	bigint	ID of the work item
ap_wi_nodeid	Oid	OID of the node on which the work item is being processed
ap_wi_status	char	Status; can be `q` (queued), `c` (complete), `f` (failed), or `u` (unknown)
ap_wi_started_at	timestamptz	Start timestamptz of work item
ap_wi_finished_at	timestamptz	End timestamptz of work item

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.taskmgr_local_work_queue`

Contains work items created and processed by the task manager. This is similar to `bdr.taskmgr_work_queue`, except that these work items are for locally managed tables. Each node creates and processes its own local work items, independent of other nodes in the cluster.

`bdr.taskmgr_local_work_queue` columns

Column	Type	Description
ap_wq_workid	bigint	Unique ID of the work item
ap_wq_ruleid	int	ID of the rule listed in autopartition_rules. Rules are specified using bdr.autopartition command
ap_wq_relname	name	Name of the relation the task belongs to
ap_wq_relnamespace	name	Name of the tablespace specified in rule for this work item.
ap_wq_partname	name	Name of the partition created by the workitem
ap_wq_work_category	char	Category; can be `c` (create partition), `m` (migrate partition), `d` (drop partition), or `a` (alter partition)
ap_wq_work_sql	text	SQL query for the work item
ap_wq_work_depends	Oid[]	Always NULL

`bdr.taskmgr_local_workitem_status`

The status of the work items for locally managed tables.

`bdr.taskmgr_local_workitem_status` columns

Column	Type	Description
ap_wi_workid	bigint	ID of the work item
ap_wi_nodeid	Oid	OID of the node on which the work item is being processed
ap_wi_status	char	Status; can be `q` (queued), `c` (complete), `f` (failed), or `u` (unknown)
ap_wi_started_at	timestamptz	Start timestamptz of work item
ap_wi_finished_at	timestamptz	End timestamptz of work item

`bdr.trigger`

In this view, you can see all the stream triggers created. Often triggers here are created from `bdr.create_conflict_trigger`.

`bdr.trigger` columns

Name	Type	Description
trigger_id	oid	ID of the trigger
trigger_reloid	regclass	Name of the relating function
trigger_pgtgid	oid	Postgres trigger ID
trigger_type	char	Type of trigger call
trigger_name	name	Name of the trigger

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.triggers`

An expanded view of `bdr.trigger` with columns that are easier to read.

Name	Type	Description
trigger_name	name	Name of the trigger
event_manipulation	text	Operations
trigger_type	bdr.trigger_type	Type of trigger
trigger_table	bdr.trigger_reloid	Table that calls the trigger
trigger_function	name	Function used

`bdr.workers`

Information about running PGD worker processes.

This can be joined with `bdr.stat_activity` using pid to get even more insight into the state of PGD workers.

`bdr.workers` Columns

Name	Type	Description
worker_pid	int	Process ID of the worker process
worker_role	int	Numeric representation of worker role
worker_role_name	text	Name of the worker role
worker_subid	oid	Subscription ID if the worker is associated with one

`bdr.writers`

Specific information about PGD writer processes.

`bdr.writers` columns

Name	Type	Description
sub_name	name	Name of the subscription
pid	int	Process ID of the worker process
syncing_rel	int	OID of the relation being synchronized (if any)
streaming_allowed	text	Can this writer be target of direct to writer streaming
is_streaming	bool	Is there transaction being streamed to this writer
remote_xid	xid	Remote transaction id of the transaction being processed (if any)
remote_commit_lsn	pg_lsn	LSN of last commit processed
commit_queue_position	int	Position in the internal commit queue
nxacts	bigint	Number of transactions processed by this writer
ncommits	bigint	Number of transactions committed by this writer
naborts	bigint	Number of transactions aborted by this writer
nstream_file	bigint	Number of streamed-to-file transactions processed by this writer
nstream_writer	bigint	Number of streamed-to-writer transactions processed by this writer
xact_nchanges	bigint	Number of changes processed by this writer (updated every 1000 rows)

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.worker_tasks`

The `bdr.worker_tasks` view shows PGD's current worker launch rate limiting state as well as some basic statistics on background worker launch and registration activity.

Unlike the other views listed here, it isn't specific to the current database and PGD node. State for all PGD nodes on the current PostgreSQL instance is shown. Join on the current database to filter it.

`bdr.worker_tasks` doesn't track walsenders and output plugins.

`bdr.worker_tasks` columns

Column	Type	Description
task_key_worker_role	integer	Worker role identifier
task_key_worker_role_name	text	Worker role name
task_key_dboid	oid	Database identifier, if available
datname	name	Name of the database, if available
task_key_subid	oid	Subscription identifier, if available
sub_name	name	Name of the subscription, if available
task_key_ext_libname	name	Name of the library (most likely bdr)
task_key_ext_funcname	name	Name of the function entry point
task_key_ext_workername	name	Name assigned to the worker
task_key_remoterelid	oid	Identifier of the remote syncing relation, if available
task_pid	integer	Process ID of the worker
task_registered	timestamp with time zone	Worker registration timestamp
since_registered	interval	Interval since the worker registered
task_attached	timestamp with time zone	Worker attach timestamp
since_attached	interval	Interval since the worker attached
task_exited	timestamp with time zone	Worker exit timestamp
since_exited	interval	Interval since the worker exited
task_success	boolean	Is worker still running?
task_next_launch_not_before	timestamp with time zone	Timestamp when the worker will be restarted again
until_launch_allowed	interval	Time remaining for next launch
task_last_launch_requestor_pid	integer	Process ID that requested launch
task_last_launch_request_time	timestamp with time zone	Timestamp when the request was made
since_last_request	interval	Interval since the last request
task_last_launch_request_approved	boolean	Did the last request succeed?
task_nrequests	integer	Number of requests
task_nregistrations	integer	Number of registrations
task_prev_pid	integer	Process ID of the previous generation
task_prev_registered	timestamp with time zone	Timestamp of the previous registered task
since_prev_registered	interval	Interval since the previous registration
task_prev_launched	timestamp with time zone	Timestamp of the previous launch
since_prev_launched	interval	Interval since the previous launch
task_prev_exited	timestamp with time zone	Timestamp when the previous task exited
since_prev_exited	interval	Interval since the previous task exited
task_first_registered	timestamp with time zone	Timestamp when the first registration happened
since_first_registered	interval	Interval since the first registration

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.xid_peer_progress`

Tracks per-transaction progress used by `bdr.wait_for_xid_progress()`. A node records the transaction status here as soon as it makes progress on it, and also reports it to all other nodes; the same table stores the reports received from peer nodes, with `peer_node_id`, `peer_apply_xid`, and `peer_apply_lsn` then referring to the peer.

`bdr.xid_peer_progress` columns

Name	Type	Description
origin_node_id	oid	OID of the node where the transaction originated
origin_node_topxid	xid	Top-level XID of the transaction on the origin node
origin_node_lsn	pg_lsn	LSN on the origin node at the time progress was recorded
peer_node_id	oid	OID of the peer node this progress report is about
peer_apply_xid	xid	XID applied on the peer node
peer_apply_lsn	pg_lsn	LSN applied on the peer node

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.2 System functions

Perform PGD management primarily by using functions you call from SQL. All functions in PGD are exposed in the `bdr` schema. Schema qualify any calls to these functions instead of putting `bdr` in the `search_path`.

Version information functions

`bdr.bdr_version`

This function retrieves the textual representation of the version of the BDR extension currently in use.

`bdr.bdr_version_num`

This function retrieves the version number of the BDR extension that is currently in use. Version numbers are monotonically increasing, allowing this value to be used for less-than and greater-than comparisons.

The following formula returns the version number consisting of major version, minor version, and patch release into a single numerical value:

```
MAJOR_VERSION * 10000 + MINOR_VERSION * 100 + PATCH_RELEASE
```

System information functions

`bdr.get_relation_stats`

Returns the relation information.

`bdr.get_subscription_stats`

Returns the current subscription statistics.

System and progress information parameters

PGD exposes some parameters that you can query directly in SQL using, for example, `SHOW` or the `current_setting()` function. You can also use `PQparameterStatus` (or equivalent) from a client application.

`bdr.local_node_id`

When you initialize a session, this is set to the node id the client is connected to. This allows an application to figure out the node it's connected to, even behind a transparent proxy.

It's also used with Connection pools and proxies.

`bdr.last_committed_lsn`

After every `COMMIT` of an asynchronous transaction, this parameter is updated to point to the end of the commit record on the origin node. Combining it with `bdr.wait_for_apply_queue`, allows applications to perform causal reads across multiple nodes, that is, to wait until a transaction becomes remotely visible.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`transaction_id`

If a CAMO transaction is in progress, `transaction_id` is updated to show the assigned transaction id. You can query this parameter only by using using `PQparameterStatus` or equivalent. See Application use for a usage example.

`bdr.is_node_connected`

Synopsis

```
bdr.is_node_connected(node_name name)
```

Returns boolean by checking if the walsender for a given peer is active on this node.

`bdr.is_node_ready`

Synopsis

```
bdr.is_node_ready(node_name name, span interval DEFAULT NULL)
```

Returns boolean by checking if the lag is lower than the given span or lower than the `timeout` for `TO ASYNC` otherwise.

Consensus function

`bdr.consensus_disable`

Synopsis

```
bdr.consensus_disable(node_group_name text DEFAULT NULL)
```

Disables the consensus worker on the local node until server restart or until it's reenabled using `bdr.consensus_enable` (whichever happens first).

The `node_group_name` parameter is accepted for interface consistency but is currently a placeholder. The function disables the consensus worker database-wide, affecting all Raft instances on the node regardless of the value passed.

> **Warning**
>
> Disabling consensus disables some features of PGD and affects availability of the EDB Postgres Distributed cluster if left disabled for a long time. Use this function only when working with Technical Support.

`bdr.consensus_enable`

Synopsis

```
bdr.consensus_enable(node_group_name text DEFAULT NULL)
```

Re-enables a disabled consensus worker on the local node.

The `node_group_name` parameter is accepted for interface consistency but is currently a placeholder. The function re-enables the consensus worker database-wide, affecting all Raft instances on the node regardless of the value passed.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.consensus_proto_version`

Returns currently used consensus protocol version by the local node.

Needed by the PGD group reconfiguration internal mechanisms.

`bdr.consensus_snapshot_export`

Synopsis

```
bdr.consensus_snapshot_export(version integer DEFAULT NULL, raft_instance_id integer DEFAULT
NULL)
```

Generate a new PGD consensus snapshot from the currently committed-and-applied state of the local node and return it as bytea.

By default, a snapshot for the highest supported Raft version is exported. But you can override that by passing an explicit `version` number.

The `raft_instance_id` parameter identifies which Raft instance to export the snapshot from. When `NULL` (the default), the top-level Raft instance is used. To target a specific node group's Raft instance, pass its instance ID, which you can look up via `bdr.raft_instances`.

The exporting node doesn't have to be the current Raft leader, and it doesn't need to be completely up to date with the latest state on the leader. However, `bdr.consensus_snapshot_import()` might not accept such a snapshot.

The new snapshot isn't automatically stored to the local node's `bdr.local_consensus_snapshot` table. It's only returned to the caller.

The generated snapshot might be passed to `bdr.consensus_snapshot_import()` on any other nodes in the same PGD node group that's behind the exporting node's Raft log position.

The local PGD consensus worker must be disabled for this function to work. Typical usage is:

```
SELECT bdr.bdr_consensus_disable();
COPY (SELECT * FROM bdr.consensus_snapshot_export()) TO
'/var/lib/postgresql/my_node_consensus_snapshot.data';
SELECT bdr.bdr_consensus_enable();
```

While the PGD consensus worker is disabled:

- DDL locking attempts on the node fail or time out.
- galloc sequences don't get new values.
- Eager and CAMO transactions pause or error.
- Other functionality that needs the distributed consensus system is disrupted. The required downtime is generally very brief.

Depending on the use case, it might be practical to extract a snapshot that already exists from the `snapshot` field of the `bdr.local_consensus_snapshot` table and use that instead. Doing so doesn't require you to stop the consensus worker.

`bdr.consensus_snapshot_import`

Synopsis

```
bdr.consensus_snapshot_import(snapshot bytea, raft_instance_id integer DEFAULT
NULL)
```

Import a consensus snapshot that was exported by `bdr.consensus_snapshot_export()`, usually from another node in the same PGD node group.

It's also possible to use a snapshot extracted directly from the `snapshot` field of the `bdr.local_consensus_snapshot` table on another node.

This function is useful for resetting a PGD node's catalog state to a known good state in case of corruption or user error.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

The `raft_instance_id` parameter identifies which Raft instance to import the snapshot into. When `NULL` (the default), the top-level Raft instance is used. To target a specific node group's Raft instance, pass its instance ID, which you can look up via `bdr.raft_instances`.

You can import the snapshot if the importing node's `apply_index` is less than or equal to the snapshot-exporting node's `commit_index` when the snapshot was generated. (See `bdr.get_raft_status()`.) A node that can't accept the snapshot because its log is already too far ahead raises an error and makes no changes. The imported snapshot doesn't have to be completely up to date, as once the snapshot is imported the node fetches the remaining changes from the current leader.

The PGD consensus worker must be disabled on the importing node for this function to work. See notes on `bdr.consensus_snapshot_export()` for details.

It's possible to use this function to force the local node to generate a new Raft snapshot by running:

```
SELECT bdr.consensus_snapshot_import(bdr.consensus_snapshot_export());
```

This approach might also truncate the Raft logs up to the current applied log position.

`bdr.consensus_snapshot_verify`

Synopsis

```
bdr.consensus_snapshot_verify(snapshot
bytea)
```

Verify the given consensus snapshot that was exported by `bdr.consensus_snapshot_export()`. The snapshot header contains the version with which it was generated and the node tries to verify it against the same version.

The snapshot might have been exported on the same node or any other node in the cluster. If the node verifying the snapshot doesn't support the version of the exported snapshot, then an error is raised.

`bdr.get_consensus_status`

Returns status information about the current consensus (Raft) worker, as a JSON document.

Synopsis

```
bdr.get_consensus_status(node_group_name text DEFAULT NULL)
```

Parameters

Parameter	Description
`node_group_name`	Name of the node group to report on. If NULL, reports on the top-level node group.

`bdr.get_raft_status`

Returns status information about the current consensus (Raft) worker, as a JSON document. Both this function and `bdr.get_consensus_status` are backed by the same underlying implementation, so calling `bdr.get_raft_status` without the second argument is equivalent to calling `bdr.get_consensus_status`.

Synopsis

```
bdr.get_raft_status(node_group_name text DEFAULT NULL, include_node_info boolean DEFAULT false)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameters

Parameter	Description
`node_group_name`	Name of the node group to report on. If NULL, reports on the top-level node group.
`include_node_info`	If `true`, also includes per-node information (such as heartbeat response time and clock drift) in the returned JSON. Defaults to `false`.

`bdr.raft_leadership_transfer`

Synopsis

```
bdr.raft_leadership_transfer(node_name text,
                             wait_for_completion boolean,
                             node_group_name text DEFAULT NULL)
```

Request the node identified by `node_name` to be the Raft leader. The request can be initiated from any of the PGD nodes and is internally forwarded to the current leader to transfer the leadership to the designated node. The designated node must be an ACTIVE PGD node with full voting rights.

If `wait_for_completion` is false, the request is served on a best-effort basis. If the node can't become a leader in the `bdr.raft_global_lection_timeout` period, then some other capable node becomes the leader again. Also, the leadership can change over the period of time per Raft protocol. A `true` return result indicates only that the request was submitted successfully.

If `wait_for_completion` is `true`, then the function waits until the given node becomes the new leader and possibly waits infinitely if the requested node fails to become Raft leader (for example, due to network issues). We therefore recommend that you always set a `statement_timeout` with `wait_for_completion` to prevent an infinite loop.

The `node_group_name` is optional and can be used to specify the name of the node group where the leadership transfer happens. If not specified, it defaults to NULL, which is interpreted as the top-level group in the cluster. If the `node_group_name` is specified, the function transfers leadership only within the specified node group.

Utility functions

`bdr.wait_slot_confirm_lsn`

Allows you to wait until the last write on this session was replayed to one or all nodes.

Waits until a slot passes a certain LSN. If no position is supplied, the current write position is used on the local node.

If no slot name is passed, it waits until all PGD slots pass the LSN.

The function polls every 1000 ms for changes from other nodes.

If a slot is dropped concurrently, the wait ends for that slot. If a node is currently down and isn't updating its slot, then the wait continues. You might want to set `statement_timeout` to complete earlier in that case.

If you are using Optimized Topology, we recommend using `bdr.wait_node_confirm_lsn` instead.)

Synopsis

```
bdr.wait_slot_confirm_lsn(slotname name, target
pg_lsn)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Notes

Requires `bdr_application` privileges to use.

Both parameters are required. Pass `NULL` explicitly for either one to get the "wait for all slots" or "use the current write LSN" behavior described above — there's no default that lets you omit them.

Parameters

Parameter	Description
`slotname`	Name of the replication slot to wait for. If NULL, waits for all PGD slots.
`target`	LSN to wait for. If NULL, uses the current write LSN on the local node.

`bdr.wait_node_confirm_lsn`

Wait until a node passes a certain LSN.

This function allows you to wait until the last write on this session was replayed to one or all nodes.

Upon being called, the function waits for a node to pass a certain LSN. If no LSN is supplied, the current wal_flush_lsn (using the `pg_current_wal_flush_lsn()` function) position is used on the local node. Supplying a node name parameter tells the function to wait for that node to pass the LSN. If no node name is supplied (by passing NULL), the function waits until all the nodes pass the LSN.

We recommend using this function if you are using Optimized Topology instead of `bdr.wait_slot_confirm_lsn`.

This is because in an Optimized Topology, not all nodes have replication slots, so the function `bdr.wait_slot_confirm_lsn` might not work as expected. `bdr.wait_node_confirm_lsn` is designed to work with nodes that don't have replication slots, using alternative strategies to determine the progress of a node.

If a node is currently down, isn't updating, or simply can't be connected to, the wait will continue indefinitely. To avoid this condition, set the statement_timeout to the maximum amount of time you are prepared to wait.

Synopsis

```
bdr.wait_node_confirm_lsn(nodename name, target
pg_lsn)
```

Parameters

Parameter	Description
`nodename`	Name of the node to wait for. If NULL, waits for all nodes.
`target`	LSN to wait for. If NULL, uses the current wal_flush_lsn on the local node.

Notes

Requires `bdr_application` privileges to use.

Both parameters are required. Pass `NULL` explicitly for either one to get the "wait for all nodes" or "use the current wal_flush_lsn" behavior described above — there's no default that lets you omit them.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.wait_for_apply_queue`

The function `bdr.wait_for_apply_queue` allows a PGD node to wait for the local application of certain transactions originating from a given PGD node. It returns only after all transactions from that peer node are applied locally. An application or a proxy can use this function to prevent stale reads.

For convenience, PGD provides a variant of this function for CAMO and the CAMO partner node. See bdr.wait_for_camo_partner_queue.

In case a specific LSN is given, that's the point in the recovery stream from which the peer waits. You can use this with `bdr.last_committed_lsn` retrieved from that peer node on a previous or concurrent connection.

If the given `target_lsn` is NULL, this function checks the local receive buffer and uses the LSN of the last transaction received from the given peer node, effectively waiting for all transactions already received to be applied. This is especially useful in case the peer node has failed and it's not known which transactions were sent. In this case, transactions that are still in transit or buffered on the sender side aren't waited for.

Synopsis

```
bdr.wait_for_apply_queue(peer_node_name TEXT, target_lsn pg_lsn)
```

Parameters

Parameter	Description
`peer_node_name`	The name of the peer node from which incoming transactions are expected to be queued and to wait for. If NULL, waits for all peer node's apply queue to be consumed.
`target_lsn`	The LSN in the replication stream from the peer node to wait for, usually learned by way of `bdr.last_committed_lsn` from the peer node.

`bdr.get_node_sub_receive_lsn`

You can use this function on a subscriber to get the last LSN that was received from the given origin. It can be either unfiltered or filtered to take into account only relevant LSN increments for transactions to be applied.

The difference between the output of this function and the output of `bdr.get_node_sub_apply_lsn()` measures the size of the corresponding apply queue.

Synopsis

```
bdr.get_node_sub_receive_lsn(node_name name, committed bool default true)
```

Parameters

Parameter	Description
`node_name`	The name of the node that's the source of the replication stream whose LSN is being retrieved.
`committed`	The default (true) makes this function take into account only commits of transactions received rather than the last LSN overall. This includes actions that have no effect on the subscriber node.

`bdr.get_node_sub_apply_lsn`

You can use this function on a subscriber to get the last LSN that was received and applied from the given origin.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.get_node_sub_apply_lsn(node_name name)
```

Parameters

Parameter	Description
`node_name`	The name of the node that's the source of the replication stream whose LSN is being retrieved.

`bdr.replicate_ddl_command`

Function to replicate a DDL command to a group of nodes.

Synopsis

```
bdr.replicate_ddl_command(ddl_cmd text,
                          replication_sets
text[],
                          ddl_locking
text,
                          execute_locally bool)
```

Parameters

Parameter	Description
`ddl_cmd`	DDL command to execute.
`replication_sets`	An array of replication set names to apply the `ddlcommand` to. If NULL (or the function is passed only the `ddlcommand`), this parameter is set to the active PGD groups's default replication set.
`ddl_locking`	A string that sets the `bdr.ddl_locking` value while replicating. Defaults to the GUC value for `bdr.ddl_locking` on the local system that's running `replicate_ddl_command`.
`execute_locally`	A Boolean that determines whether the DDL command executes locally. Defaults to true.

Notes

The only required parameter of this function is `ddl_cmd`.

`bdr.replicate_ddl_command()` always replicates the command and is unaffected by the setting of `bdr.ddl_replication`.

`bdr.run_on_all_nodes`

Function to run a query on all nodes.

> **Warning**
>
> This function runs an arbitrary query on a remote node with the privileges of the user used for the internode connections as specified in the node's DSN. Use caution when granting privileges to this function.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.run_on_all_nodes(query text)
```

Parameters

Parameter	Description
`query`	Arbitrary query to execute.

Notes

This function connects to other nodes and executes the query, returning a result from each of them in JSON format. Multiple rows might be returned from each node, encoded as a JSON array. Any errors, such as being unable to connect because a node is down, are shown in the response field. No explicit statement_timeout or other runtime parameters are set, so defaults are used.

This function doesn't go through normal replication. It uses direct client connection to all known nodes. By default, the connection is created with `bdr.ddl_replication = off`, since the commands are already being sent to all of the nodes in the cluster.

Be careful when using this function since you risk breaking replication and causing inconsistencies between nodes. Use either transparent DDL replication or `bdr.replicate_ddl_command()` to replicate DDL. DDL might be blocked in a future release.

Example

It's useful to use this function in monitoring, for example, as in the following query:

```
SELECT bdr.run_on_all_nodes($$
    SELECT local_slot_name, origin_name, target_name,
replay_lag_size
      FROM
bdr.node_slots
     WHERE origin_name IS NOT
NULL
$$);
```

This query returns something like this on a two-node cluster:

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
[
    {
        "dsn": "host=node1 port=5432 dbname=bdrdb user=postgres ",
        "node_id": "2232128708",
        "response": {
            "command_status": "SELECT 1",
            "command_tuples": [
                {
                    "origin_name": "node1",
                    "target_name": "node2",
                    "local_slot_name": "bdr_bdrdb_bdrgroup_node2",
                    "replay_lag_size": "0 bytes"
                }
            ]
        },
        "node_name": "node1"
    },
    {
        "dsn": "host=node2 port=5432 dbname=bdrdb user=postgres ",
        "node_id": "2058684375",
        "response": {
            "command_status": "SELECT 1",
            "command_tuples": [
                {
                    "origin_name": "node2",
                    "target_name": "node1",
                    "local_slot_name": "bdr_bdrdb_bdrgroup_node1",
                    "replay_lag_size": "0 bytes"
                }
            ]
        },
        "node_name": "node2"
    }
]
```


`bdr.run_on_nodes`

Function to run a query on a specified list of nodes.

> **Warning**
>
> This function runs an arbitrary query on remote nodes with the privileges of the user used for the internode connections as specified in the node's DSN. Use caution when granting privileges to this function.

Synopsis

```
bdr.run_on_nodes(node_names text[], query text)
```

Parameters

Parameter	Description
`node_names`	Text ARRAY of node names where the query is executed.
`query`	Arbitrary query to execute.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Notes

This function connects to other nodes and executes the query, returning a result from each of them in JSON format. Multiple rows can be returned from each node, encoded as a JSON array. Any errors, such as being unable to connect because a node is down, are shown in the response field. No explicit statement_timeout or other runtime parameters are set, so defaults are used.

This function doesn't go through normal replication. It uses direct client connection to all known nodes. By default, the connection is created with `bdr.ddl_replication = off` to avoid replication issues when the same replicated DDL command is sent to multiple nodes.

Be careful when using this function since you risk breaking replication and causing inconsistencies between nodes. For global schema changes, to replicate DDL, use either transparent DDL replication or `bdr.replicate_ddl_command()` .

`bdr.run_on_group`

Function to run a query on a group of nodes.

> **Warning**
>
> This function runs an arbitrary query on remote nodes with the privileges of the user used for the internode connections as specified in the node's DSN. Use caution when granting privileges to this function.

Synopsis

```
bdr.run_on_group(node_group_name text, query text)
```

Parameters

Parameter	Description
`node_group_name`	Name of the node group where the query is executed.
`query`	Arbitrary query to execute.

Notes

This function connects to other nodes and executes the query, returning a result from each of them in JSON format. Multiple rows can be returned from each node, encoded as a JSON array. Any errors, such as being unable to connect because a node is down, are shown in the response field. No explicit statement_timeout or other runtime parameters are set, so defaults are used.

This function doesn't go through normal replication. It uses direct client connection to all known nodes. By default, the connection is created with `bdr.ddl_replication = off` to avoid replication issues when the same replicated DDL command is sent to multiple nodes.

Be careful when using this function since you risk breaking replication and causing inconsistencies between nodes in the group. For global schema changes, to replicate DDL, use either transparent DDL replication or `bdr.replicate_ddl_command()` .

`bdr.global_lock_table`

This function acquires a global DML locks on a given table. See DDL locking details for information about global DML lock.

Synopsis

```
bdr.global_lock_table(relation regclass)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameters

Parameter	Description
`relation`	Name or oid of the relation to lock.

Notes

This function acquires the global DML lock independently of the `ddl_locking` setting.

The `bdr.global_lock_table` function requires `UPDATE`, `DELETE`, or `TRUNCATE` privilege on the locked `relation` unless `bdr.backwards_compatibility` is set to 30618 or lower.

`bdr.wait_for_xid_progress`

You can use this function to wait for the given transaction (identified by its XID) originated at the given node (identified by its node id) to make enough progress on the cluster. The progress is defined as the transaction being applied on a node and this node having seen all other replication changes done before the transaction is applied.

Synopsis

```
bdr.wait_for_xid_progress(origin_node_id oid, origin_topxid int4, allnodes boolean DEFAULT
true)
```

Parameters

Parameter	Description
`origin_node_id`	Node id of the node where the transaction originated.
`origin_topxid`	XID of the transaction.
`allnodes`	If `true`, wait for the transaction to progress on all nodes. Otherwise, wait only for the current node.

Notes

You can use the function only for those transactions that replicated a DDL command because only those transactions are tracked currently. If a wrong `origin_node_id` or `origin_topxid` is supplied, the function might wait forever or until `statement_timeout` occurs.

`bdr.local_group_slot_name`

Returns the name of the group slot on the local node.

Example

```
bdrdb=# SELECT bdr.local_group_slot_name();

local_group_slot_name
-----------------------
 bdr_bdrdb_bdrgroup
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.node_group_type`

Returns the type of the given node group. Returned value is the same as what was passed to `bdr.create_node_group()` when the node group was created, except `global` is returned if the `node_group_type` was passed as NULL when the group was created.

Example

```
bdrdb=# SELECT bdr.node_group_type('bdrgroup');
 node_group_type
-----------------
 global
```

`bdr.alter_node_kind`

PGD5 introduced a concept of Task Manager Leader node. The node is selected by PGD, but for upgraded clusters, it's important to set the `node_kind` properly for all nodes in the cluster. Do this manually after upgrading to the latest PGD version by calling the `bdr.alter_node_kind()` SQL function for each node.

Synopsis

```
bdr.alter_node_kind(node_name text,
                    node_kind
text);
```

Parameters

Parameter	Description
`node_name`	Name of the node to change kind.
`node_kind`	Kind of the node.

`bdr.alter_subscription_skip_changes_upto`

Because logical replication can replicate across versions, doesn't replicate global changes like roles, and can replicate selectively, sometimes the logical replication apply process can encounter an error and stop applying changes.

Wherever possible, fix such problems by making changes to the target side. `CREATE` any missing table that's blocking replication, `CREATE` a needed role, `GRANT` a necessary permission, and so on. But occasionally a problem can't be fixed that way and it might be necessary to skip entirely over a transaction. Changes are skipped as entire transactions—all or nothing. To decide where to skip to, use log output to find the commit LSN, per the example that follows, or peek the change stream with the logical decoding functions.

Unless a transaction made only one change, you often need to manually apply the transaction's effects on the target side, so it's important to save the problem transaction whenever possible, as shown in the examples that follow.

It's possible to skip over changes without `bdr.alter_subscription_skip_changes_upto` by using `pg_catalog.pg_logical_slot_get_binary_changes` to skip to the LSN of interest, so this is a convenience function. It does do a faster skip, although it might bypass some kinds of errors in logical decoding.

This function works only on disabled subscriptions.

The usual sequence of steps is:

1. Identify the problem subscription and LSN of the problem commit.
2. Disable the subscription.
3. Save a copy of the transaction using `pg_catalog.pg_logical_slot_peek_changes` on the source node, if possible.
4. `bdr.alter_subscription_skip_changes_upto` on the target node.
5. Apply repaired or equivalent changes on the target manually, if necessary.
6. Reenable the subscription.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Warning**
>
> It's easy to make problems worse when using this function. Don't do anything unless you're certain it's the only option.

Synopsis

```
  bdr.alter_subscription_skip_changes_upto(
    subname text,
    skip_upto_and_including
pg_lsn
  );
```

Example

Apply of a transaction is failing with an error, and you've determined that lower-impact fixes such as changes on the target side can't resolve this issue. You determine that you must skip the transaction.

In the error logs, find the commit record LSN to skip to, as in this example:

```
ERROR:  XX000: CONFLICT: target_table_missing; resolver skip_if_recently_dropped returned an error: table does not
exist
CONTEXT:  during apply of INSERT from remote relation public.break_me in xact with commit-end lsn 0/300AC18 xid
131315
committs 2021-02-02 15:11:03.913792+01 (action #2) (effective sess origin id=2 lsn=0/300AC18)
while consuming 'I' message from receiver for subscription bdr_regression_bdrgroup_node1_node2 (id=2667578509)
on node node2 (id=3367056606) from upstream node node1 (id=1148549230, reporiginid=2)
```

In this portion of log, you have the information you need: the_target_lsn: **0/300AC18** the_subscription: **bdr_regression_bdrgroup_node1_node2**

Next, disable the subscription so the apply worker doesn't try to connect to the replication slot:

```
  SELECT
bdr.alter_subscription_disable('the_subscription');
```

You can't skip only parts of the transaction: it's all or nothing. So we strongly recommend that you save a record of it by copying it out on the provider side first, using the subscription's slot name.

```
  \\copy (SELECT * FROM
pg_catalog.pg_logical_slot_peek_changes('the_slot_name',
     'the_target_lsn', NULL, 'min_proto_version', '1', 'max_proto_version', '1',
     'startup_params_format', '1', 'proto_format', 'json'))
   TO 'transaction_to_drop.csv' WITH (FORMAT csv);
```

This example is broken into multiple lines for readability, but issue it in a single line. `\copy` doesn't support multi-line commands.

You can skip the change by changing `peek` to `get`, but `bdr....skip_changes_upto` does a faster skip that avoids decoding and outputting all the data:

```
  SELECT bdr.alter_subscription_skip_changes_upto('subscription_name',
     'the_target_lsn');
```

You can apply the same changes (or repaired versions of them) manually to the target node, using the dumped transaction contents as a guide.

Finally, reenable the subscription:

```
  SELECT bdr.alter_subscription_enable('the_subscription');
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.connection_manager_refresh_pools`

This function tells the PGD connection manager to refresh its connection pools.

This function is useful for integration with other tools or when an immediate re-evaluation of connection pools is required. This function operates only on the local node; to refresh connection managers across the entire cluster, you must execute the function on each node individually. Execution requires the `bdr_superuser` role.
Expand commentComment on line R861Resolved

Synopsis

```
SELECT
bdr.connection_manager_refresh_pools();
```

> **Note**
>
> This function may terminate existing client connections if routing changes are detected (e.g., write leader changed, nodes added/removed from routing targets, or consensus was lost).

Global advisory locks

PGD supports global advisory locks. These locks are similar to the advisory locks available in PostgreSQL except that the advisory locks supported by PGD are global. They follow semantics similar to DDL locks. So an advisory lock is obtained by majority consensus and can be used even if one or more nodes are down or lagging behind, as long as a majority of all nodes can work together.

Currently only EXCLUSIVE locks are supported. So if another node or another backend on the same node has already acquired the advisory lock on the object, then other nodes or backends must wait for the lock to be released.

Advisory lock is transactional in nature. So the lock is released when the transaction ends unless you explicitly release it before the end of the transaction. In this case, it becomes available as soon as it's released. Session-level advisory locks aren't currently supported.

Global advisory locks are reentrant. So if the same resource is locked three times, you must then unlock it three times to release it for use in other sessions.

`bdr.global_advisory_lock`

This function acquires an EXCLUSIVE lock on the provided object. If the lock isn't available, then it waits until the lock becomes available or the `bdr.global_lock_timeout` is reached.

Synopsis

```
bdr.global_advisory_lock(key bigint)
```

parameters

- `key` — The object on which an advisory lock is acquired.

Synopsis

```
bdr.global_advisory_lock(key1 integer, key2 integer)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameters

Parameter	Description
`key1`	First part of the composite key.
`key2`	Second part of the composite key.

`bdr.global_advisory_unlock`

This function releases a previously acquired lock on the application-defined source. The lock must have been obtained in the same transaction by the application. Otherwise, an error is raised.

Synopsis

```
bdr.global_advisory_unlock(key bigint)
```

Parameters

Parameter	Description
`key`	The object on which an advisory lock is acquired.

Synopsis

```
bdr.global_advisory_unlock(key1 integer, key2 integer)
```

Parameters

Parameter	Description
`key1`	First part of the composite key.
`key2`	Second part of the composite key.

Monitoring functions

`bdr.monitor_group_versions`

To provide a cluster-wide version check, this function uses PGD version information returned from the view `bdr.group_version_details`.

Synopsis

```
bdr.monitor_group_versions()
```

Notes

This function returns a record with fields `status` and `message`, as explained in Monitoring.

This function calls `bdr.run_on_all_nodes()`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.monitor_group_raft`

To provide a cluster-wide Raft check, this function uses PGD Raft information returned from the view `bdr.group_raft_details`.

Synopsis

```
bdr.monitor_group_raft()
```

Parameters

Parameter	Description
`node_group_name`	The node group name to check.

Notes

This function returns a record with fields `status` and `message`, as explained in Monitoring.

This function calls `bdr.run_on_all_nodes()`.

`bdr.monitor_local_replslots`

This function uses replication slot status information returned from the view `pg_replication_slots` (slot active or inactive) to provide a local check considering all replication slots except the PGD group slots.

This function also provides status information on subscriber-only nodes that are operating as subscriber-only group leaders in a PGD cluster whenoptimized topology is enabled.

Synopsis

```
bdr.monitor_local_replslots()
```

Notes

This function returns a record with fields `status` and `message`.

Status	Message
UNKNOWN	This node is not part of any BDR group
OK	All BDR replication slots are working correctly
OK	This node is part of a subscriber-only group
CRITICAL	There is at least 1 BDR replication slot which is inactive
CRITICAL	There is at least 1 BDR replication slot which is missing

Further explaination is available in Monitoring replication slots.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.wal_sender_stats`

If the decoding worker is enabled, this function shows information about the decoder slot and current logical change record (LCR) segment file being read by each WAL sender.

Synopsis

```
bdr.wal_sender_stats()
```

Output columns

Column name	Description
`pid`	PID of the WAL sender. (Corresponds to the `pid` column of `pg_stat_replication`).
`is_using_lcr`	Whether the WAL sender is sending LCR files.
`decoder_slot_name`	Name of the decoder replication slot.
`lcr_file_name`	Name of the current LCR file.

`bdr.get_decoding_worker_stat`

If the decoding worker is enabled, this function shows information about the state of the decoding worker associated with the current database. This also provides more granular information about decoding worker progress than is available via `pg_replication_slots`.

Synopsis

```
bdr.get_decoding_worker_stat()
```

Output columns

Column name	Description
`pid`	The PID of the decoding worker. (Corresponds to the column `active_pid` in `pg_replication_slots`.)
`decoded_upto_lsn`	LSN up to which the decoding worker read transactional logs.
`waiting`	Whether the decoding worker is waiting for new WAL.
`waiting_for_lsn`	The LSN of the next expected WAL.

Notes

For details, see Monitoring WAL senders using LCR.

`bdr.lag_control`

If Lag Control is enabled, this function shows information about the commit delay and number of nodes conforming to their configured lag measure for the local node and current database.

Synopsis

```
bdr.lag_control()
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Output columns

Column name	Description
`commit_scope_id`	OID of the commit scope (see `bdr.commit_scopes`).
`sessions`	Number of sessions referencing the lag control entry.
`current_commit_delay`	Current runtime commit delay, in fractional milliseconds.
`maximum_commit_delay`	Configured maximum commit delay, in fractional milliseconds.
`commit_delay_adjust`	Change to runtime commit delay possible during a sample interval, in fractional milliseconds.
`current_conforming_nodes`	Current runtime number of nodes conforming to lag measures.
`minimum_conforming_nodes`	Configured minimum number of nodes required to conform to lag measures, below which a commit delay adjustment is applied.
`lag_bytes_threshold`	Lag size at which a commit delay is applied, in kilobytes.
`maximum_lag_bytes`	Configured maximum lag size, in kilobytes.
`lag_time_threshold`	Lag time at which a commit delay is applied, in milliseconds.
`maximum_lag_time`	Configured maximum lag time, in milliseconds.
`sample_interval`	Configured minimum time between lag samples and possible commit delay adjustments, in milliseconds.

CAMO functions

CAMO requires that a client actively participates in the committing of a transaction by following the transactions progress. The functions listed here are used for that purpose and explained in CAMO.

`bdr.is_camo_partner_connected`

Allows checking of the connection status of a CAMO partner node configured in pair mode. There currently is no equivalent for CAMO used with eager replication.

Synopsis

```
bdr.is_camo_partner_connected()
```

Return value

A Boolean value indicating whether the CAMO partner is currently connected to a WAL sender process on the local node and therefore can receive transactional data and send back confirmations.

`bdr.is_camo_partner_ready`

Allows checking of the readiness status of a CAMO partner node configured in pair mode. Underneath, this triggers the switch to and from local mode.

Synopsis

```
bdr.is_camo_partner_ready()
```

Return value

A Boolean value indicating whether the CAMO partner can reasonably be expected to confirm transactions originating from the local node in a timely manner, that is, before `timeout` for `TO ASYNC` expires.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **Note**
>
> This function queries the past or current state. A positive return value doesn't indicate whether the CAMO partner can confirm future transactions.

`bdr.get_configured_camo_partner`

This function shows the local node's CAMO partner (configured by pair mode).

Synopsis

```
bdr.get_configured_camo_partner()
```

`bdr.wait_for_camo_partner_queue`

The function is a wrapper around `bdr.wait_for_apply_queue` defaulting to query the CAMO partner node. It returns an error if the local node isn't part of a CAMO pair.

Synopsis

```
bdr.wait_for_camo_partner_queue()
```

`bdr.camo_transactions_resolved`

This function begins a wait for CAMO transactions to be fully resolved.

Synopsis

```
bdr.camo_transactions_resolved()
```

`bdr.logical_transaction_status`

To check the status of a transaction that was being committed when the node failed, the application must use this function, passing as parameters the node id of the node the transaction originated from and the transaction id on the origin node.

Synopsis

```
bdr.logical_transaction_status(node_id OID, xid
OID,
                               require_camo_partner boolean DEFAULT true,
                               queried_by_origin boolean DEFAULT false)
```

Note that the underlying function doesn't declare SQL parameter names, so these arguments must be passed positionally rather than by name.

Parameters

Parameter	Description
`node_id`	The node id of the PGD node the transaction originates from, usually retrieved by the client before `COMMIT` from the PQ parameter `bdr.local_node_id`.
`xid`	The transaction id on the origin node, usually retrieved by the client before `COMMIT` from the PQ parameter `transaction_id`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameter	Description
`require_camo_partner`	Defaults to true and enables configuration checks. Set to false to disable these checks and query the status of a transaction that wasn't a CAMO transaction.
`queried_by_origin`	Advanced/internal use. Only the origin node should set this to `true`, and only when it's uncertain about a transaction that is still prepared but not yet finished. It forces the CAMO partner to resolve an otherwise-unknown or provisional-abort decision to `abort`, since the partner can't safely report `committed` before the transaction actually commits. Defaults to `false`.

Return value

The function returns one of these results:

- `'committed'::TEXT` — The transaction was committed, is visible on both nodes of the CAMO pair, and is eventually replicated to all other PGD nodes. No need for the client to retry it.
- `'aborted'::TEXT` — The transaction was aborted and isn't replicated to any other PGD node. The client needs to either retry it or escalate the failure to commit the transaction.
- `'in progress'::TEXT` — The transaction is still in progress on this local node and wasn't committed or aborted yet. The transaction might be in the COMMIT phase, waiting for the CAMO partner to confirm or deny the commit. The recommended client reaction is to disconnect from the origin node and reconnect to the CAMO partner to query that instead. With a load balancer or proxy in between, where the client lacks control over which node gets queried, the client can only poll repeatedly until the status switches to either `'committed'` or `'aborted'`.

  For eager all-node replication, peer nodes yield this result for transactions that aren't yet committed or aborted. Even transactions not yet replicated (or not even started on the origin node) might yield an `in progress` result on a peer PGD node in this case. However, the client must not query the transaction status prior to attempting to commit on the origin.
- `'unknown'::TEXT` — The transaction specified is unknown because it's either in the future, not replicated to that specific node yet, or too far in the past. The status of such a transaction isn't yet or is no longer known. This return value is a sign of improper use by the client.

The client must be prepared to retry the function call on error.

Commit Scope functions

`bdr.add_commit_scope`

Deprecated. Use `bdr.create_commit_scope` instead. Previously, this function was used to add a commit scope to a node group. It's now deprecated and will emit a warning until it is removed in a future release, at which point it will raise an error.

`bdr.create_commit_scope`

`bdr.create_commit_scope` creates a rule for the given commit scope name and origin node group. If the rule is the same for all nodes in the EDB Postgres Distributed cluster, invoking this function once for the top-level node group is enough to fully define the commit scope.

Alternatively, you can invoke it multiple times with the same `commit_scope_name` but different origin node groups and rules for commit scopes that vary depending on the origin of the transaction.

Synopsis

```
bdr.create_commit_scope(
    commit_scope_name NAME,
    origin_node_group NAME,
    rule TEXT,
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
    wait_for_ready boolean DEFAULT
true)
```

Note

`bdr.create_commit_scope` replaces the deprecated `bdr.add_commit_scope` function. Unlike `add_commit_scope`, it does not silently overwrite existing commit scopes when the same name is used. Instead, an error is reported.

`bdr.alter_commit_scope`

`bdr.alter_commit_scope` allows you to change a specific rule for a single origin node group in a commit scope.

Synopsis

```
bdr.alter_commit_scope(
    commit_scope_name NAME,
    origin_node_group NAME,
    rule TEXT)
```

`bdr.drop_commit_scope`

Drops a single rule in a commit scope. If you define multiple rules for the commit scope, you must invoke this function once per rule to fully remove the entire commit scope.

Synopsis

```
bdr.drop_commit_scope(
    commit_scope_name NAME,
    origin_node_group NAME)
```

> **Note**
>
> Dropping a commit scope that's still used as default by a node group isn't allowed.

`bdr.remove_commit_scope`

Deprecated. Use `bdr.drop_commit_scope` instead. Previously, this function was used to remove a commit scope from a node group. It's now deprecated and will emit a warning until it is removed in a future release, at which point it will raise an error.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.3 PGD settings

You can set PGD-specific configuration settings. Unless noted otherwise, you can set the values at any time.

Conflict handling

`bdr.default_conflict_detection`

Sets the default conflict detection method for newly created tables. Accepts same values as bdr.alter_table_conflict_detection().

Global sequence parameters

`bdr.default_sequence_kind`

Sets the default sequence kind.

The default is `distributed`, which means `snowflakeid` is used for `int8` sequences (that is, `bigserial`) and `galloc` sequence for `int4` (that is, `serial`) and `int2` sequences.

DDL handling

`bdr.default_replica_identity`

Sets the default value for `REPLICA IDENTITY` on newly created tables. The `REPLICA IDENTITY` defines the information written to the write-ahead log to identify rows that are updated or deleted.

The accepted values are:

Value	Description
`default`	Records the old values of the columns of the primary key, if any (this is the default PostgreSQL behavior).
`full`	Records the old values of all columns in the row.
`nothing`	Records no information about the old row.
`auto`	Tables with PK are created with REPLICA IDENTITY DEFAULT, and tables without PK are created with REPLICA IDENTITY FULL. This is the default PGD behavior.

See the PostgreSQL documentation for more details.

PGD can't replicate `UPDATE` and `DELETE` operations on tables without a `PRIMARY KEY` or `UNIQUE` constraint. The exception is when the replica identity for the table is `FULL`, either by table-specific configuration or by `bdr.default_replica_identity`.

If `bdr.default_replica_identity` is `default` and there is a `UNIQUE` constraint included in the table definition, it won't be automatically picked up as `REPLICA IDENTITY`. You need to set the `REPLICA IDENTITY` explicitly using `ALTER TABLE ... REPLICA IDENTITY ...`.

Setting the replica identity of tables to `full` increases the volume of WAL written and the amount of data replicated on the wire for the table.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **On setting bdr.default_replica_identity to default**
>
> When setting `bdr.default_replica_identity` to `default` using `ALTER SYSTEM`, always quote the value, like this:
>
> ```
> ALTER SYSTEM SET bdr.default_replica_identity="default";
> ```
>
> You need to include the quotes because default, unquoted, is a special value to the ALTER SYSTEM command that triggers the removal of the setting from the configuration file. When the setting is removed, the system uses the PGD default setting, which is `auto`.

`bdr.ddl_replication`

Automatically replicates DDL across nodes (default is `on`).

This parameter can be set only by bdr_superuser or superuser roles.

Running DDL or calling PGD administration functions with `bdr.ddl_replication = off` can create situations where replication stops until an administrator can intervene. See DDL replication for details.

A `LOG`-level log message is emitted to the PostgreSQL server logs whenever `bdr.ddl_replication` is set to `off`. Additionally, a `WARNING`-level message is written whenever replication of captured DDL commands or PGD replication functions is skipped due to this setting.

`bdr.role_replication`

Automatically replicates ROLE commands across nodes (default is `on`). Only a superuser can set this parameter. This setting works only if `bdr.ddl_replication` is turned on as well.

Turning this parameter off without using external methods to ensure roles are in sync across all nodes might cause replicated DDL to interrupt replication until the administrator intervenes.

See Role manipulation statements for details.

`bdr.ddl_locking`

Configures the operation mode of global locking for DDL.

This parameter can be set only by bdr_superuser or superuser roles.

Possible options are:

Value	Description
`all`	Use global locking for all DDL operations. (Default)
`dml`	Use global locking only for DDL operations that need to prevent writes by taking the global DML lock for a relation.
`off`	Don't use global locking for DDL operations.

Default is `all`.

A `LOG`-level log message is emitted to the PostgreSQL server logs whenever `bdr.ddl_replication` is set to `off`. Additionally, a `WARNING` message is written whenever any global locking steps are skipped due to this setting. It's normal for some statements to result in two `WARNING` messages: one for skipping the DML lock and one for skipping the DDL lock.

For backward compatibility, `bdr.ddl_locking` supports aliases. `on` and `true` are an alias for `all`. `false` is an alias for `off`.

See also Global locking.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.truncate_locking`

Sets the TRUNCATE command's locking behavior (default is `off`). When `true`, TRUNCATE obeys the `bdr.ddl_locking` setting.

Global locking

DDL locking is controlled by `bdr.ddl_locking`. Other global locking settings include the following.

`bdr.global_lock_max_locks`

Sets the maximum number of global locks that can be held on a node (default is 1000). Can be set only at Postgres server start.

`bdr.global_lock_timeout`

Sets the maximum allowed duration of any wait for a global lock (default is 10 minutes). A value of zero disables this timeout.

`bdr.global_lock_statement_timeout`

Sets the maximum allowed duration of any statement holding a global lock (default is 60 minutes). A value of zero disables this timeout.

`bdr.global_lock_idle_timeout`

Sets the maximum allowed duration of idle time in a transaction holding a global lock (default is 10 minutes). A value of zero disables this timeout.

`bdr.lock_table_locking`

Sets locking behavior for LOCK TABLE statement (default is off). When enabled, LOCK TABLE statement also takes a global DML lock on the cluster, blocking other locking statements.

Value	Description
`on`	Use global locking for all table locks.
`off`	Don't use global locking for table locks. (Default)

`bdr.predictive_checks`

Sets the log level for predictive checks (currently used only by global locks). Can be `DEBUG`, `LOG`, `WARNING` (default), or `ERROR`. Predictive checks are early validations for expected cluster state when doing certain operations. You can use them for those operations for fail early rather than wait for timeouts. In global lock terms, PGD checks that there are enough nodes connected and withing reasonable lag limit for getting the quorum needed by the global lock.

Node management

`bdr.replay_progress_frequency`

Sets the interval for sending replication position info to the rest of the cluster (default is 1 minute).

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Generic replication

`bdr.writers_per_subscription`

Sets the default number of writers per subscription. (In PGD, you can also change this with `bdr.alter_node_group_option` for a group.)

`bdr.max_writers_per_subscription`

Maximum number of writers per subscription. Sets the upper limit for the `bdr.writers_per_subscription` setting.

Reloadable at runtime (`PGC_SIGHUP`) since PGD 5.9.2: change the value with `ALTER SYSTEM` followed by `pg_reload_conf()` — no node restart is required. The value is captured by each writer group at initialization, so an in-flight subscription continues with the value it was started with; the new limit takes effect on the next writer-group start (subscription disable/enable, or the next reconnect cycle).

`bdr.xact_replication`

Replicates current transaction (default is `on`).

Turning this off makes the whole transaction local only, which means the transaction isn't visible to logical decoding by PGD and all other downstream targets of logical decoding. Data isn't transferred to any other node, including logical standby nodes.

This parameter can be set only by the bdr_superuser or superuser roles.

This parameter can be set only inside the current transaction using the `SET LOCAL` command unless `bdr.permit_unsafe_commands = on` .

> **Note**
>
> Even with transaction replication disabled, WAL is generated, but those changes are filtered away on the origin.

> **Warning**
>
> Turning off `bdr.xact_replication` leads to data inconsistency between nodes. Use it only to recover from data divergence between nodes or in replication situations where changes on single nodes are required for replication to continue. Use at your own risk.

`bdr.permit_unsafe_commands`

Overrides safety check on commands that are deemed unsafe for general use.

Requires bdr_superuser or PostgreSQL superuser.

> **Warning**
>
> The commands that are normally not considered safe can either produce inconsistent results or break replication altogether. Use at your own risk.

`bdr.batch_inserts`

Number of consecutive inserts to one table in a single transaction that turns on batch processing of inserts for that table.

This setting allows replication of large data loads as COPY internally, rather than as a set of inserts. It's also how the initial data during node join is copied.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.maximum_clock_skew`

Specifies the maximum difference between the incoming transaction commit timestamp and the current time on the subscriber before triggering `bdr.maximum_clock_skew_action`.

It checks if the timestamp of the currently replayed transaction is in the future compared to the current time on the subscriber. If it is, and the difference is larger than `bdr.maximum_clock_skew`, it performs the action specified by the `bdr.maximum_clock_skew_action` setting.

The default is `-1`, which means ignore clock skew (the check is turned off). It's valid to set 0 as when the clocks on all servers are synchronized. The fact that the transaction is being replayed means it was committed in the past.

`bdr.maximum_clock_skew_action`

Specifies the action to take if a clock skew higher than `bdr.maximum_clock_skew` is detected.

There are two possible values for this setting:

Value	Description
`WARN`	Log a warning about this fact. The warnings are logged once per minute at the maximum to prevent flooding the server log.
`WAIT`	Wait until the current local timestamp is no longer older than remote commit timestamp minus the `bdr.maximum_clock_skew`.

`bdr.accept_connections`

Enables or disables connections to PGD (default is `on`).

Requires bdr_superuser or PostgreSQL superuser.

`bdr.standby_slot_names`

This setting is typically used in failover configurations to ensure that the failover-candidates streaming physical replicas for this PGD node have received and flushed all changes before they ever become visible to subscribers. That guarantees that a commit can't vanish on failover to a standby for the provider.

Replication slots whose names are listed in the comma-separated `bdr.standby_slot_names` list are treated specially by the WAL sender on a PGD node.

PGD's logical replication WAL senders ensure that all local changes are sent and flushed to the replication slots in `bdr.standby_slot_names` before the node sends those changes to any other PGD replication clients. Effectively, it provides a synchronous replication barrier between the named list of slots and all other replication clients.

Any replication slot can be listed in `bdr.standby_slot_names`. Both logical and physical slots work, but it's generally used for physical slots.

Without this safeguard, two anomalies are possible where a commit can be received by a subscriber and then vanish from the provider on failover because the failover candidate hadn't received it yet:

- For 1+ subscribers, the subscriber might have applied the change but the new provider might execute new transactions that conflict with the received change, as it never happened as far as the provider is concerned.
- For 2+ subscribers, at the time of failover, not all subscribers have applied the change. The subscribers now have inconsistent and irreconcilable states because the subscribers that didn't receive the commit have no way to get it.

Setting `bdr.standby_slot_names` by design causes other subscribers not listed in there to lag behind the provider if the required number of listed nodes are not keeping up. Monitoring is thus essential.

Another use case where `bdr.standby_slot_names` is useful is when using a subscriber-only node, to ensure that it doesn't move ahead of any of the regular PGD nodes. This can best be achieved by listing the logical slots of all regular PGD peer nodes in combination with setting `bdr.standby_slots_min_confirmed` to at least 1.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.standby_slots_min_confirmed`

Controls how many of the `bdr.standby_slot_names` have to confirm before sending data to PGD subscribers.

`bdr.writer_input_queue_size`

Specifies the size of the shared memory queue used by the receiver to send data to the writer process. If the writer process is stalled or making slow progress, then the queue might get filled up, stalling the receiver process too. So it's important to provide enough shared memory for this queue. The default is 1 MB, and the maximum allowed size is 1 GB. While any storage size specifier can be used to set the GUC, the default is KB.

`bdr.writer_output_queue_size`

Specifies the size of the shared memory queue used by the receiver to receive data from the writer process. Since the writer isn't expected to send a large amount of data, a relatively smaller sized queue is enough. The default is 32 KB, and the maximum allowed size is 1 MB. While any storage size specifier can be used to set the GUC, the default is KB.

`bdr.min_worker_backoff_delay`

Allows for rate limiting of PGD background worker launches by preventing a given worker from being relaunched more often than every `bdr.min_worker_backoff_delay` milliseconds. On repeated errors, the backoff increases exponentially with added jitter up to a maximum of `bdr.max_worker_backoff_delay`.

Time-unit suffixes are supported.

> **Note**
>
> This setting currently affects only receiver worker, which means it primarily affects how fast a subscription tries to reconnect on error or connection failure.

The default for `bdr.min_worker_backoff_delay` is 1 second. For `bdr.max_worker_backoff_delay`, it's 1 minute.

If the backoff delay setting is changed and the PostgreSQL configuration is reloaded, then all current backoffs wait for reset. Additionally, the `bdr.worker_task_reset_backoff_all()` function is provided to allow the administrator to force all backoff intervals to immediately expire.

A tracking table in shared memory is maintained to remember the last launch time of each type of worker. This tracking table isn't persistent. It's cleared by PostgreSQL restarts, including soft restarts during crash recovery after an unclean backend exit.

You can use the view `bdr.worker_tasks` to inspect this state so the administrator can see any backoff rate limiting currently in effect.

For rate-limiting purposes, workers are classified by task. This key consists of the worker role, database OID, subscription ID, subscription writer ID, extension library name and function name, extension-supplied worker name, and the remote relation ID for sync writers. `NULL` is used where a given classifier doesn't apply, for example, when manager workers don't have a subscription ID and receivers don't have a writer ID.

CRDTs

`bdr.crdt_raw_value`

Sets the output format of CRDT data types.

The default output (when this setting is `off`) is to return only the current value of the base CRDT type, for example, a bigint for `crdt_pncounter`. When set to `on`, the returned value represents the full representation of the CRDT value, which can, for example, include the state from multiple nodes.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Commit scope

`bdr.commit_scope`

Sets the current (or default) commit scope (default is an empty string).

Commit At Most Once

`bdr.camo_local_mode_delay`

The commit delay that applies in CAMO's asynchronous mode to emulate the overhead that normally occurs with the CAMO partner having to confirm transactions (default is 5 ms). Set to `0` to disable this feature.

`bdr.camo_enable_client_warnings`

Emits warnings if an activity is carried out in the database for which CAMO properties can't be guaranteed (default is enabled). Well-informed users can choose to disable this setting to reduce the amount of warnings going into their logs.

Transaction streaming

`bdr.default_streaming_mode`

Controls transaction streaming by the subscriber node. Possible values are: `off`, `writer`, `file`, and `auto`. Defaults to `auto`. If set to `off`, the subscriber doesn't request transaction streaming. If set to one of the other values, the subscriber requests transaction streaming and the publisher provides it if it supports them and if configured at group level. For more details, see Transaction streaming.

Lag Control

`bdr.lag_control_min_conforming_nodes`

Minimum number of nodes required to stay below acceptable lag measures.

`bdr.lag_control_commit_delay_adjust`

Commit delay micro adjustment measured as a fraction of the maximum commit delay time. At a default value of 0.01%, it takes 100 net increments to reach the maximum commit delay.

`bdr.lag_control_sample_interval`

Minimum time between lag samples and commit delay micro adjustments, in milliseconds.

`bdr.lag_control_commit_delay_start`

The lag threshold at which commit delay increments start to be applied, expressed as a fraction of acceptable lag measures. At a default value of 1.0%, commit delay increments don't begin until acceptable lag measures are breached.

By setting a smaller fraction, it might be possible to prevent a breach by "bending the lag curve" earlier so that it's asymptotic with the acceptable lag measure.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Timestamp-based snapshots

`bdr.timestamp_snapshot_keep`

Time to keep valid snapshots for the timestamp-based snapshot use (default is `0`, meaning don't keep past snapshots).

Monitoring and logging

`bdr.debug_level`

Defines the log level that PGD uses to write its debug messages. The default value is `debug3`. If you want to see detailed PGD debug output, set `bdr.debug_level = 'log'`.

`bdr.trace_level`

Similar to `bdr.debug_level`, defines the log level to use for PGD trace messages. Enabling tracing on all nodes of an EDB Postgres Distributed cluster might help EDB Support to diagnose issues. You can set this parameter only at Postgres server start.

> **Warning**
>
> Setting `bdr.debug_level` or `bdr.trace_level` to a value >= `log_min_messages` can produce a very large volume of log output. Don't enabled it long term in production unless plans are in place for log filtering, archival, and rotation to prevent disk space exhaustion.

`bdr.track_subscription_apply`

Tracks apply statistics for each subscription with `bdr.stat_subscription` (default is `on`).

`bdr.track_relation_apply`

Tracks apply statistics for each relation with `bdr.stat_relation` (default is `off`).

`bdr.track_apply_lock_timing`

Tracks lock timing when tracking statistics for relations with `bdr.stat_relation` (default is `off`).

Decoding worker

`bdr.enable_wal_decoder`

Enables logical change record (LCR) sending on a single node with a decoding worker (default is false). When set to true, a decoding worker process starts, and WAL senders send the LCRs it produces. If set back to false, any WAL senders using LCR are restarted and use the WAL directly.

> **Note**
>
> You also need to enable this setting on all nodes in the PGD group and set the `enable_wal_decoder` option to true on the group.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.receive_lcr`

When subscribing to another node, this setting enables the node to request the use of logical change records (LCRs) for the subscription (default is false). When this setting is true on a downstream node, the node requests that upstream nodes use LCRs when sending to it. If you set `bdr.enable_wal_decoder` to true on a node, also set this setting to true.

> **Note**
>
> You also need to enable this setting on all nodes in the PGD group and set the `enable_wal_decoder` option to true on the group.

`bdr.lcr_cleanup_interval`

Logical change record (LCR) file cleanup interval (default is 3 minutes). When the decoding worker is enabled, the decoding worker stores LCR files as a buffer. These files are periodically cleaned, and this setting controls the interval between any two consecutive cleanups. Setting it to zero disables cleanup.

Connectivity settings

The following are a set of connectivity settings affecting all cross-node `libpq` connections. The defaults are set to fairly conservative values and cover most production needs. All variables have `SIGHUP` context, meaning changes are applied upon reload.

`bdr.global_connection_timeout`

Maximum time to wait while connecting, in seconds (default is 15 seconds). Write as a decimal integer, for example, 10. Zero, negative, or not specified means wait indefinitely. The minimum allowed timeout is 2 seconds, therefore a value of 1 is interpreted as 2.

`bdr.global_keepalives`

Controls whether TCP keepalives are used (default is 1, meaning on). If you don't want keepalives, you can change this to 0, meaning off. This parameter is ignored for connections made by a Unix-domain socket.

`bdr.global_keepalives_idle`

Controls the number of seconds of inactivity after which TCP sends a keepalive message to the server (default is 1 second). A value of zero uses the system default. This parameter is ignored for connections made by a Unix-domain socket or if keepalives are disabled. It's supported only on systems where `TCP_KEEPIDLE` or an equivalent socket option is available. On other systems, it has no effect.

`bdr.global_keepalives_interval`

Controls the number of seconds after which to retransmit a TCP keepalive message that isn't acknowledged by the server (default is 2 seconds). A value of zero uses the system default. This parameter is ignored for connections made by a Unix-domain socket or if keepalives are disabled. It's supported only on systems where `TCP_KEEPINTVL` or an equivalent socket option is available. On other systems, it has no effect.

`bdr.global_keepalives_count`

Controls the number of TCP keepalives that can be lost before the client's connection to the server is considered dead (default is 3). A value of zero uses the system default. This parameter is ignored for connections made by a Unix-domain socket or if keepalives are disabled. It's supported only on systems where `TCP_KEEPCNT` or an equivalent socket option is available. On other systems, it has no effect.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.global_tcp_user_timeout`

Controls the number of milliseconds that transmitted data can remain unacknowledged before a connection is forcibly closed (default is 5000, that is, 5 seconds). A value of zero uses the system default. This parameter is ignored for connections made by a Unix-domain socket. It's supported only on systems where `TCP_USER_TIMEOUT` is available. On other systems, it has no effect.

Topology settings

`bdr.force_full_mesh`

Forces the full mesh topology (default is `on`). When set to `off`, PGD will attempt to use the optimized topology for subscriber-only groups. This setting is only effective when the requirements for the optimized topology are met. See Optimizing subscriber-only groups for more information.

Internal settings - Raft timeouts

`bdr.raft_global_election_timeout`

To account for network failures, the Raft consensus protocol implements timeouts for elections and requests. This value is used when a request is being sent to the global (top-level) group. The default is 6 seconds (6s).

`bdr.raft_group_election_timeout`

To account for network failures, the Raft consensus protocol implements timeouts for elections and requests. This value is used when a request is being sent to the sub-group. The default is 3 seconds (3s).

`bdr.raft_response_timeout`

For responses, the settings of `bdr.raft_global_election_timeout` and `bdr.raft_group_election_timeout` are used as appropriate. You can override this behavior by setting this variable. The setting of `bdr.raft_response_timeout` must be less than either of the election timeout values. Set this variable to -1 to disable the override. The default is -1.

Internal settings - Other Raft values

`bdr.raft_keep_min_entries`

The minimum number of entries to keep in the Raft log when doing log compaction (default is `1000`; PGD 5.3 and earlier: `100`). The value of `0` disables log compaction. You can set this parameter only at Postgres server start.

> **Warning**
>
> If log compaction is disabled, the log grows in size forever.

`bdr.raft_log_min_apply_duration`

To move the state machine forward, Raft appends entries to its internal log. During normal operation, appending takes only a few milliseconds. This poses an upper threshold on the duration of that append action, above which an `INFO` message is logged. This can indicate a problem. Default is 3000 ms.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.raft_log_min_message_duration`

When to log a consensus request. Measures roundtrip time of a PGD consensus request and logs an `INFO` message if the time exceeds this parameter (default is 5000 ms).

`bdr.raft_group_max_connections`

The maximum number of connections across all PGD groups for a Postgres server (default is 100 connections). These connections carry PGD consensus requests between the groups' nodes. You can set this parameter only at Postgres server start.

`bdr.raft_vacuum_interval`

The interval between routine vacuum operations on the Raft catalog tables (default is 5 minutes). The minimum value is `60s` and the maximum value is `24h`, and it must be set to a lower value than `bdr.raft_vacuum_full_interval`. This setting cannot be disabled.

`bdr.raft_vacuum_full_interval`

The interval between vacuum full operations on the Raft catalog tables (default is 1 day). The minimum value is `1h`, and it must be set to a higher value than `bdr.raft_vacuum_interval`. `-1` disables this setting entirely.

Internal settings - Other values

`bdr.backwards_compatibility`

Specifies the version to be backward compatible to, in the same numerical format as used by `bdr.bdr_version_num`, for example, `30618`. (Default is the current PGD version.) Enables exact behavior of a former PGD version, even if this has generally unwanted effects. Since this changes from release to release, we advise against explicit use in the configuration file unless the value is different from the current version.

`bdr.track_replication_estimates`

Tracks replication estimates in terms of apply rates and catchup intervals for peer nodes. Protocols like CAMO can use this information to estimate the readiness of a peer node. This parameter is enabled by default.

`bdr.lag_tracker_apply_rate_weight`

PGD monitors how far behind peer nodes are in terms of applying WAL from the local node and calculate a moving average of the apply rates for the lag tracking. This parameter specifies how much contribution newer calculated values have in this moving average calculation. Default is 0.1.

`bdr.enable_auto_sync_reconcile`

When enabled, nodes perform automatic synchronization of data from a node that is furthest ahead with respect to the down node. Default (from 5.5.1) is off.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.4 Node management

List of node states

State	Description
`NONE`	Node state is unset when the worker starts, expected to be set quickly to the current known state.
`CREATED`	`bdr.create_node()` was executed, but the node isn't a member of any EDB Postgres Distributed cluster yet.
`JOIN_START`	`bdr.join_node_group()` begins to join the local node to an existing EDB Postgres Distributed cluster.
`JOINING`	The node join has started and is currently at the initial sync phase, creating the schema and data on the node.
`CATCHUP`	Initial sync phase is completed. Now the join is at the last step of retrieving and applying transactions that were performed on the upstream peer node since the join started.
`STANDBY`	Node join finished but hasn't yet started to broadcast changes. All joins spend some time in this state, but if defined as a logical standby, the node continues in this state.
`PROMOTE`	Node was a logical standby and `bdr.promote_node` was just called to move the node state to `ACTIVE`. These two `PROMOTE` states have to be coherent to the fact that only one node can be with a state higher than `STANDBY` but lower than `ACTIVE`.
`PROMOTING`	Promotion from logical standby to full PGD node is in progress.
`ACTIVE`	The node is a full PGD node and is currently `ACTIVE`. This is the most common node status.
`PART_START`	Node was `ACTIVE` or `STANDBY` and `bdr.part_node` was just called to remove the node from the EDB Postgres Distributed cluster.
`PARTING`	Node disconnects from other nodes and plays no further part in consensus or replication.
`PART_CATCHUP`	Nonparting nodes synchronize any missing data from the recently parted node.
`PARTED`	Node parting operation is now complete on all nodes.

Only one node at a time can be in either of the states PROMOTE or PROMOTING.

Node-management commands

PGD also provides a command-line utility for adding nodes to the PGD group using a physical copy (`pg_basebackup`) of an existing node.

`bdr_init_physical`

> **Version requirement**
>
> `bdr_init_physical` requires that both the source node and the joining node have exactly the same PGD version. You can't use this command to join a node with a different PGD version to an existing cluster. This means that you can't use `bdr_init_physical` for rolling upgrades using the node join method. For rolling upgrades, use logical join instead. See Rolling upgrade using node join for more details.

This is a regular command that's added to PostgreSQL's bin directory.

You must specify a data directory. If this data directory is empty, use `pg_basebackup -X stream` to fill the directory using a fast block-level copy operation.

If the specified data directory isn't empty, it's used as the base for the new node. Initially, it waits for catchup and then promotes to a master node before joining the PGD group. The `--standby` option, if used, turns it into a logical standby node.

This command drops all PostgreSQL-native logical replication subscriptions from the database (or disables them when the `-S` option is used) as well as any replication origins and slots.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr_init_physical [OPTION] ...
```

Options

General options

- `-D, --pgdata=DIRECTORY` — The data directory to use for the new node. It can be either an empty or nonexistent directory or a directory populated using the `pg_basebackup -X stream` command (required).
- `-l, --log-file=FILE` — Use FILE for logging. The default is `bdr_init_physical_postgres.log`.
- `-n, --node-name=NAME` — The name of the newly created node (required).
- `--replication-sets=SETS` — The name of a comma-separated list of replication set names to use. All replication sets are used if not specified.
- `--standby` — Create a logical standby (receive-only node) rather than full send/receive node.
- `--node-group-name` — Group to join. Defaults to the same group as source node.
- `-s, --stop` — Stop the server once the initialization is done.
- `-v` — Increase logging verbosity.
- `-L` — Perform selective pg_basebackup when used with an empty/nonexistent data directory (-D option). This is a feature of EDB Postgres Extended Server only.
- `-S` — Instead of dropping logical replication subscriptions, disable them.

Connection options

- `-d, --remote-dsn=CONNSTR` — Connection string for remote node (required).
- `--local-dsn=CONNSTR` — Connection string for local node (required).

Configuration files override

- `--hba-conf` — Path to the new `pg_hba.conf`.
- `--postgresql-conf` — Path to the new `postgresql.conf`.
- `--postgresql-auto-conf` — Path to the new `postgresql.auto.conf`.

Notes

The replication set names specified in the command don't affect the data that exists in the data directory before the node joins the PGD group. This is true whether `bdr_init_physical` makes its own base backup or an existing base backup is being promoted to a new PGD node. Thus the `--replication-sets` option affects only the data published and subscribed to after the node joins the PGD node group. This behavior is different from the way replication sets are used in a logical join, as when using `bdr.join_node_group()`.

The operator can truncate unwanted tables after the join completes. Refer to the `bdr.tables` catalog to determine replication set membership and identify tables that aren't members of any subscribed-to replication set. We strongly recommend that you truncate the tables rather than drop them, because:

- DDL replication sets aren't necessarily the same as row (DML) replication sets, so you might inadvertently drop the table on other nodes.
- If you later want to add the table to a replication set and you dropped it on some subset of nodes, you need to re-create it only on those nodes without creating DDL conflicts before you can add it to any replication sets.

It's simpler and safer to truncate your nonreplicated tables, leaving them present but empty.

> **Note**
>
> For very large databases, where `pg_basebackup` takes hours, see Joining large PGD nodes with 2 steps for a procedure that populates the data directory manually before running `bdr_init_physical` and protects the WAL with a permanent replication slot.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr_config`

This command-line utility allows you to examine the configuration of a PGD installation. It is analogous to the `pg_config` utility that comes with PostgreSQL. You can use it to assist in troubleshooting and support.

Synopsis

```
bdr_config [OPTION] ...
```

Options

Option	Description
`--all`	Show all the keys and values in the configuration.
`--version`	Show only the BDR version related keys and values. This includes the full version of the BDR extension, the Postgres version and flavor it is running against, and the BDRPG and BDR plugin API versions.
`--debug`	Show only the BDR debug keys and values, including build information and feature enablement.

Example

```
$ /usr/lib/edb-as/16/bin/bdr_config --all
```

output

```
BDR_VERSION_COMPLETE=5.6.0
BDR_VERSION_NUM=50600
PG_VERSION=16.4.1 (Debian 16.4.1~~snapshot11329862135.2980.1.88fbec6-1.bookworm)
PG_VERSION_NUM=160004
PG_FLAVOR=EPAS
BDRPG_API_VERSION_NUM=202309131
BDR_PLUGIN_API_VERSION=7011
USE_ASSERT_CHECKING=false
USE_VALGRIND=false
EXT_ENABLE_DTRACE=false
HAVE_LAG_CONTROL=true
HAVE_ASSESS_UPDATE_RI_HOOK=false
HAVE_BDRPG_PROBES=false
HAVE_CAMO=true
HAVE_DEADLOCK_DETECTOR_HOOK=true
HAVE_HEAP_UPDATE_HOOK=true
HAVE_LAG_TRACKER=true
HAVE_LCR=true
HAVE_LOG_TOAST_COLUMNS=false
HAVE_MISC_HOOKS=true
HAVE_MISSING_PARTITION_CONFLICT=true
HAVE_MULTI_PITR=false
HAVE_SELECTIVE_BASEBACKUP=false
HAVE_SNAPSHOT_TIMESTAMP=false
HAVE_STREAMING_XACTS=true
HAVE_SYNC_COMMIT_HOOK=true
HAVE_TWOPHASE_DATA_HOOKS=true
HAVE_XLOG_FIND_NEXT_RECORD=true
HAVE_DETACH_CONCURRENTLY=true
HAVE_ANALYTICS=true
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.5 Node management interfaces

You can add and remove nodes dynamically using the SQL interfaces.

`bdr.alter_node_group_option`

Modifies a PGD node group configuration.

Synopsis

```
bdr.alter_node_group_option(node_group_name text,
    config_key text,
    config_value text)
```

Parameters

Name	Description
`node_group_name`	Name of the group to change.
`config_key`	Key of the option in the node group to change.
`config_value`	New value to set for the given key.

`config_value` is parsed into the data type appropriate for the option.

The table shows the group options that can be changed using this function.

Name	Type	Description
`apply_delay`	`interval`	How long nodes wait to apply incoming changes. This option is useful mainly to set up a special subgroup with delayed subscriber-only nodes. Don't set this on groups that contain data nodes or on the top-level group. Default is `0s`.
`check_constraints`	`boolean`	Whether the apply process checks the constraints when writing replicated data. We recommend keeping the default value or you risk data loss. Valid values are `on` or `off`. Default is `on`.
`default_commit_scope`	`text`	The commit scope to use by default, initially the `local` commit scope. This option applies only to the top-level node group. You can use individual rules for different origin groups of the same commit scope. See Origin groups for more details.
`enable_proxy_routing`	`boolean`	Where `pgd-proxy` through the group leader is enabled for given group. Valid values are `on` or `off`. Default is `off`.
`enable_raft`	`boolean`	Whether group has its own Raft consensus. This option is necessary for setting `enable_proxy_routing` to `on`. This option is always `on` for the top-level group. Valid values are `on` or `off`. Default is `off` for subgroups.
`enable_wal_decoder`	`boolean`	Enables/disables the decoding worker process. You can't enable the decoding worker process if `streaming_mode` is already enabled. Valid values are `on` or `off`. Default is `off`.
`location`	`text`	Information about group location. This option is purely metadata for monitoring. Default is `''` (empty string).

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
num_writers	integer	Number of parallel writers for the subscription backing this node group. Valid values are -1 or a positive integer. -1 means the value specified by the GUC bdr.writers_per_subscription is used. -1 is the default.
route_reader_max_lag	integer	Maximum lag in bytes for a node to be considered a viable read-only node. Currently reserved for future use.
route_writer_max_lag	integer	Maximum lag in bytes of the new write candidate to be selected as write leader. If no candidate passes this, no writer is selected. Default is -1.
route_writer_wait_flush	boolean	Whether to switch if PGD needs to wait for the flush. Currently reserved for future use.
streaming_mode	text	Enables/disables streaming of large transactions. When set to off, streaming is disabled. When set to any other value, large transactions are decoded while they're still in progress, and the changes are sent to the downstream. If the value is set to file, then the incoming changes of streaming transactions are stored in a file and applied only after the transaction is committed on upstream. If the value is set to writer, then the incoming changes are directly sent to one of the writers, if available. If parallel apply is disabled or no writer is free to handle streaming transactions, then the changes are written to a file and applied after the transaction is committed. If the value is set to auto, PGD tries to intelligently pick between file and writer, depending on the transaction property and available resources. You can't enable streaming_mode if the WAL decoder is already enabled. Default is auto. For more details, see Transaction streaming.
failover_slot_scope	text	PGD 5.7 and later only. Sets the scope for Logical Slot Failover support. Valid values are global or local. Default is local. For more information, see CDC Failover support.

Return value

bdr.alter_node_group_option() returns VOID on success.

An ERROR is raised if any of the provided parameters is invalid.

Notes

You can examine the current state of node group options by way of the view bdr.node_group_summary.

This function passes a request to the group consensus mechanism to change the defaults. The changes made are replicated globally using the consensus mechanism.

The function isn't transactional. The request is processed in the background, so you can't roll back the function call. Also, the changes might not be immediately visible to the current transaction.

This function doesn't hold any locks.

bdr.alter_node_interface

Changes the connection string (DSN) of a specified node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.alter_node_interface(node_name text, interface_dsn text)
```

Parameters

Name	Description
`node_name`	Name of an existing node to alter.
`interface_dsn`	New connection string for a node.

Notes

Run this function and make the changes only on the local node. This means that you normally execute it on every node in the PGD group, including the node that's being changed.

This function is transactional. You can roll it back, and the changes are visible to the current transaction.

The function holds lock on the local node.

`bdr.alter_node_option`

Modifies the PGD node routing configuration.

Synopsis

```
bdr.alter_node_option(node_name text,
    config_key text,
    config_value
text);
```

Parameters

Name	Description
`node_name`	Name of the node to change.
`config_key`	Key of the option in the node to change.
`config_value`	New value to set for the given key.

The node options you can change using this function are:

Config Key	Description
`route_priority`	Relative routing priority of the node against other nodes in the same node group. Default is `'-1'`.
`route_fence`	Whether the node is fenced from routing. When true, the node can't receive connections from PGD Proxy. Default is `'f'` (false).
`route_writes`	Whether writes can be routed to this node, that is, whether the node can become write leader. Default is `'t'` (true) for data nodes and `'f'` (false) for other node types.
`route_reads`	Whether read-only connections can be routed to this node. Currently reserved for future use. Default is `'t'` (true) for data and subscriber-only nodes, `'f'` (false) for witness and standby nodes.
`route_dsn`	The dsn for the proxy to use to connect to this node. This option is optional. If not set, it defaults to the node's `node_dsn` value.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

bdr.alter_subscription_enable

Enables either the specified subscription or all the subscriptions of the local PGD node. This is also known as resume subscription. No error is thrown if the subscription is already enabled. Returns the number of subscriptions affected by this operation.

Synopsis

```
bdr.alter_subscription_enable(
    subscription_name name DEFAULT NULL,
    immediate boolean DEFAULT false
)
```

Parameters

Name	Description
subscription_name	Name of the subscription to enable. If NULL (the default), all subscriptions on the local node are enabled.
immediate	Used to force the action immediately, starting all the workers associated with the enabled subscription. When this option is true, you can't run this function inside of the transaction block.

Notes

This function isn't replicated and affects only local node subscriptions (either a specific node or all nodes).

This function is transactional. You can roll it back, and the current transaction can see any catalog changes. The subscription workers are started by a background process after the transaction has committed.

bdr.alter_subscription_disable

Disables either the specified subscription or all the subscriptions of the local PGD node. Optionally, it can also immediately stop all the workers associated with the disabled subscriptions. This is also known as pause subscription. No error is thrown if the subscription is already disabled. Returns the number of subscriptions affected by this operation.

Synopsis

```
bdr.alter_subscription_disable(
    subscription_name name DEFAULT NULL,
    immediate boolean DEFAULT false,
    fast boolean DEFAULT true
)
```

Parameters

Name	Description
subscription_name	Name of the subscription to disable. If NULL (the default), all subscriptions on the local node are disabled.
immediate	Used to force the action immediately, stopping all the workers associated with the disabled subscription. When this option is true, you can't run this function inside of the transaction block.
fast	This argument influences the behavior of immediate. If set to true (the default), it stops all the workers associated with the disabled subscription without waiting for them to finish current work.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Notes

This function isn't replicated and affects only local node subscriptions (either a specific subscription or all subscriptions).

This function is transactional. You can roll it back, and the current transaction can see any catalog changes. However, the timing of the subscription worker stopping depends on the value of `immediate`. If set to `true`, the workers receive the stop without waiting for the `COMMIT`. If the `fast` argument is set to `true`, the interruption of the workers doesn't wait for current work to finish.

`bdr.create_node`

Creates a node.

Synopsis

```
bdr.create_node(node_name text,
                local_dsn text,
                node_kind DEFAULT NULL)
```

Parameters

Name	Description
`node_name`	Name of the new node. Only one node is allowed per database. Valid node names consist of lowercase letters, numbers, hyphens, and underscores.
`local_dsn`	Connection string to the node.
`node_kind`	One of `data` (the default), `standby`, `subscriber-only`, or `witness`. If you don't set this parameter, or if you provide `NULL`, the default `data` node kind is used.

Notes

This function creates a record for the local node with the associated public connection string. There can be only one local record, so once it's created, the function reports an error if run again.

This function is a transactional function. You can roll it back and the changes made by it are visible to the current transaction.

The function holds lock on the newly created node until the end of the transaction.

`bdr.create_node_group`

Creates a PGD node group. By default, the local node joins the group as the only member. You can add more nodes to the group with `bdr.join_node_group()`.

Synopsis

```
bdr.create_node_group(node_group_name text,
                      parent_group_name text DEFAULT NULL,
                      join_node_group boolean DEFAULT true,
                      node_group_type text DEFAULT NULL)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameters

Name	Description
`node_group_name`	Name of the new PGD group. As with the node name, valid group names consist of only lowercase letters, numbers, and underscores.
`parent_group_name`	If a node subgroup is being created, this must be the name of the parent group. Provide `NULL` (the default) when creating the main node group for the cluster.
`join_node_group`	Determines whether the node joins the group being created. The default value is `true`. Providing `false` when creating a subgroup means the local node won't join the new group, for example, when creating an independent remote group. In this case, you must specify `parent_group_name`.
`node_group_type`	The valid values are `NULL` or `subscriber-only`. `NULL` (the default) is for creating a normal, general-purpose node group. `subscriber-only` is for creating subscriber-only groups whose members receive changes only from the fully joined nodes in the cluster but that never send changes to other nodes.

Notes

This function passes a request to the local consensus worker that's running for the local node.

The function isn't transactional. The creation of the group is a background process, so once the function finishes, you can't roll back the changes. Also, the changes might not be immediately visible to the current transaction. You can call `bdr.wait_for_join_completion` to wait until they are.

The group creation doesn't hold any locks.

`bdr.drop_node_group`

Drops an empty PGD node group. If there are any joined nodes in the group, the function will fail.

Synopsis

```
bdr.drop_node_group(node_group_name text)
```

Parameters

Name	Description
`node_group_name`	Name of the PGD group to drop.

Notes

This function passes a request to the group consensus mechanism to drop the group. The function isn't transactional. The dropping process happens in the background, and you can't roll it back.

`bdr.join_node_group`

Joins the local node to an already existing PGD group.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.join_node_group
(
    join_target_dsn text,
    node_group_name text DEFAULT NULL,
    pause_in_standby boolean DEFAULT
NULL,
    wait_for_completion boolean DEFAULT
true,
    synchronize_structure text DEFAULT
'all'
)
```

Parameters

Name	Description
`join_target_dsn`	Specifies the connection string to an existing (source) node in the PGD group you want to add the local node to.
`node_group_name`	Optional name of the PGD group. Defaults to NULL, which tries to detect the group name from information present on the source node.
`wait_for_completion`	Wait for the join process to complete before returning. Defaults to `true`.
`synchronize_structure`	Specifies whether to perform database structure (schema) synchronization during the join. `all`, the default setting, synchronizes the complete database structure. `none` does not synchronize any structure. However, data will still be synchronized, meaning the database structure must already be present on the joining node. Note that by design, neither schema nor data will ever be synchronized to witness nodes.
`pause_in_standby`	Optionally tells the join process to join only as a logical standby node, which can be later promoted to a full member. This option is deprecated and will be disabled or removed in future versions of PGD.

> **Warning**
>
> `pause_in_standby` is deprecated since BDR 5.0. The recommended way to create a logical standby is to set `node_kind` to `standby` when creating the node with `bdr.create_node`.

If `wait_for_completion` is specified as `false`, the function call returns as soon as the joining procedure starts. You can see the progress of the join in the log files and the `bdr.event_summary` information view. You can call the function `bdr.wait_for_join_completion()` after `bdr.join_node_group()` to wait for the join operation to complete. It can emit progress information if called with `verbose_progress` set to `true`.

Notes

This function passes a request to the group consensus mechanism by way of the node that the `join_target_dsn` connection string points to. The changes made are replicated globally by the consensus mechanism.

The function isn't transactional. The joining process happens in the background and you can't roll it back. The changes are visible only to the local transaction if `wait_for_completion` was set to `true` or by calling `bdr.wait_for_join_completion` later.

Node can be part of only a single group, so you can call this function only once on each node.

Node join doesn't hold any locks in the PGD group.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.part_node`

Removes (parts) the node from the PGD group but doesn't remove data from the node.

You can call the function from any active node in the PGD group, including the node that you're removing.

Executing parting from the node being removed runs the risk of incorrectly reporting, or never reporting, the status of the removal. This is because in the process of being removed, communications are cut off from the rest of the cluster. While the removal may succeed, there's no way to inform the node that issued the command that it failed or succeeded on the other nodes. The function can't be set to wait for completion either, for the same reason.

Once a node has parted itself, it can't part other nodes in the cluster as it's no longer part of the cluster.

We recommend avoiding using nodes to part themselves from the cluster. Instead, perform node parting operations from a node that can wait for completion and check the cluster status after the operation is complete.

> **Note**
>
> If you're parting the local node, you must set `wait_for_completion` to `false`. Otherwise, it reports an error.

> **Warning**
>
> This action is permanent. If you want to temporarily halt replication to a node, use `bdr.alter_subscription_disable()`.

Synopsis

```
bdr.part_node
(
    node_name text,
    wait_for_completion boolean DEFAULT
true,
    force boolean DEFAULT false
)
```

Parameters

Name	Description
`node_name`	Name of an existing node to part.
`wait_for_completion`	If `true`, the function doesn't return until the node is fully parted from the cluster. Otherwise, the function starts the parting procedure and returns immediately without waiting. Always set to `false` when executing on the local node or when using `force`.
`force`	Forces removal of the node on the local node. This sets the node state locally if consensus can't be reached or if the node-parting process is stuck.

> **Warning**
>
> Using `force = true` can leave the PGD group in an inconsistent state. Use it only to recover from failures in which you can't remove the node any other way.

Notes

This function passes a request to the group consensus mechanism to part the given node. The changes made are replicated globally by the consensus mechanism. The parting process happens in the background, and you can't roll it back. The changes made by the parting process are visible only to the local transaction if `wait_for_completion` was set to `true`.

With `force` set to `true`, on consensus failure, this function sets the state of the given node only on the local node. In such a case, the function is transactional (because the function changes the node state) and you can roll it back. If the function is called on a node that's already in process of parting with `force` set to `true`, it also marks the given node as parted locally and exits. This is useful only when the consensus can't be reached on the cluster (that is, the majority of the nodes are down) or if the parting process is stuck. But it's important to take into account that when the parting node that was receiving writes, the parting process can take a long time without being stuck. The other nodes need to resynchronize any missing data from the given node. The force parting completely skips this resynchronization and can leave the other nodes in an inconsistent state.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

The parting process doesn't hold any locks.

`bdr.promote_node`

Promotes a local logical standby node to a full member of the PGD group.

Synopsis

```
bdr.promote_node(wait_for_completion boolean DEFAULT true)
```

Notes

This function passes a request to the group consensus mechanism to change the defaults. The changes made are replicated globally by the consensus mechanism.

The function isn't transactional. The promotion process happens in the background, and you can't roll it back. The changes are visible only to the local transaction if `wait_for_completion` was set to `true` or by calling `bdr.wait_for_join_completion` later.

The promotion process holds lock against other promotions. This lock doesn't block other `bdr.promote_node` calls but prevents the background process of promotion from moving forward on more than one node at a time.

`bdr.switch_node_group`

Switches the local node from its current subgroup to another subgroup in the same existing PGD node group.

Synopsis

```
bdr.switch_node_group
(
    node_group_name text,
    wait_for_completion boolean DEFAULT
true
)
```

Parameters

Name	Description
`node_group_name`	Name of the PGD group or subgroup.
`wait_for_completion`	Wait for the switch process to complete before returning. Defaults to `true`.

If `wait_for_completion` is set to `false`, this is an asynchronous call that returns as soon as the switching procedure starts. You can see progress of the switch in logs and the `bdr.event_summary` information view or by calling the `bdr.wait_for_join_completion()` function after `bdr.switch_node_group()` returns.

Notes

This function passes a request to the group consensus mechanism. The changes made are replicated globally by the consensus mechanism.

The function isn't transactional. The switching process happens in the background and you can't roll it back. The changes are visible only to the local transaction if `wait_for_completion` was set to `true` or by calling `bdr.wait_for_join_completion` later.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

The local node changes membership from its current subgroup to another subgroup in the same PGD node group without needing to part the cluster. The node's kind must match that of existing nodes in the target subgroup.

Node switching doesn't hold any locks in the PGD group.

Restrictions: currently, the function allows switching only between a subgroup and its PGD node group. To effect a move between subgroups you need to make two separate calls: 1) switch from subgroup to node group and, 2) switch from node group to other subgroup.

`bdr.wait_for_join_completion`

This function waits for the join procedure of a local node to finish.

Synopsis

```
bdr.wait_for_join_completion(verbose_progress boolean DEFAULT false)
```

Parameters

Name	Description
`verbose_progress`	Optionally prints information about individual steps taken during the join procedure.

Notes

This function waits until the checks state of the local node reaches the target state, which was set by `bdr.create_node_group`, `bdr.join_node_group`, or `bdr.promote_node`.

`bdr.alter_node_group_config`

Changes the configuration parameters of an existing PGD group. Options with NULL value (default for all of them) aren't modified.

> **Warning**
>
> This function exists only for compatibility with PGD4 and 3.7. Use `bdr.alter_node_group_option` instead.

Synopsis

```
bdr.alter_node_group_config(node_group_name text,
                            insert_to_update boolean DEFAULT
NULL,
                            update_to_insert boolean DEFAULT
NULL,
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
                           ignore_redundant_updates boolean DEFAULT
NULL,
                           check_full_tuple boolean DEFAULT
NULL,
                           apply_delay interval DEFAULT
NULL,
                           check_constraints boolean DEFAULT NULL,
                           num_writers int DEFAULT
NULL,
                           enable_wal_decoder boolean DEFAULT NULL,
                           streaming_mode text DEFAULT
NULL,
                           default_commit_scope text DEFAULT NULL)
```

Parameters

Name	Description
`node_group_name`	Name of an existing PGD group. The local node must be part of the group.
`insert_to_update`	Reserved for backward compatibility.
`update_to_insert`	Reserved for backward compatibility. This option is deprecated and will be disabled or removed in future versions of PGD. Use `bdr.alter_node_set_conflict_resolver` instead.
`ignore_redundant_updates`	Reserved for backward compatibility.
`check_full_tuple`	Reserved for backward compatibility.
`apply_delay`	How long nodes wait to apply incoming changes. This parameter is useful mainly to set up a special subgroup with delayed subscriber-only nodes. Don't set this on groups that contain data nodes or on the top-level group. Default is `0s`.
`check_constraints`	Whether the apply process checks the constraints when writing replicated data. We recommend keeping this set to the default value or you risk data loss. Valid values are `on` or `off`. Default is `on`. Applies to top-level group only.
`num_writers`	Number of parallel writers for the subscription backing this node group. Valid values are `-1` or a positive integer. `-1` means the value specified by the GUC `bdr.writers_per_subscription` is used. `-1` is the default. Applies to top-level group only.
`enable_wal_decoder`	Enables/disables the decoding worker process. You can't enable the decoding worker process if `streaming_mode` is already enabled. Valid values are `on` or `off`. Default is `off`. Applies to top-level group only.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Description
`streaming_mode`	Enables/disables streaming of large transactions. When set to `off`, streaming is disabled. When set to any other value, large transactions are decoded while they're still in progress, and the changes are sent to the downstream. If the value is set to `file`, then the incoming changes of streaming transactions are stored in a file and applied only after the transaction is committed on upstream. If the value is set to `writer`, then the incoming changes are directly sent to one of the writers, if available. If parallel apply is disabled or no writer is free to handle streaming transaction, then the changes are written to a file and applied after the transaction is committed. If the value is set to `auto`, PGD tries to intelligently pick between `file` and `writer`, depending on the transaction property and available resources. You can't enable `streaming_mode` if the WAL decoder is already enabled. For more details, see Transaction streaming. Applies to top-level group only.
`default_commit_scope`	The commit scope to use by default, initially the `local` commit scope. This parameter applies only to the top-level node group. You can use individual rules for different origin groups of the same commit scope. See Origin groups for more details.

Notes

This function passes a request to the group consensus mechanism to change the defaults. The changes made are replicated globally using the consensus mechanism.

The function isn't transactional. The request is processed in the background so you can't roll back the function call. Also, the changes might not be immediately visible to the current transaction.

This function doesn't hold any locks.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.6 Routing functions

`bdr.create_proxy`

Create a proxy configuration.

Synopsis

```
bdr.create_proxy(proxy_name text, node_group text, proxy_mode
text);
```

Parameters

Name	Type	Default	Description
`proxy_name`	text		Name of the new proxy.
`node_group`	text		Name of the group to be used by the proxy.
`proxy_mode`	text	`'default'`	Mode of the proxy. It can be `'default'` (listen_port connections follow write leader, no read_listen_port), `'read-only'` (no listen_port, read_listen_port connections follow read-only nodes), or `'any'` (listen_port connections follow write_leader, read_listen_port connections follow read-only nodes). Default is `'default'`.

When proxy_mode is set to `'default'`, all read options in the proxy config are set to NULL. When it's set to `'read-only'`, all write options in the proxy config are set to NULL. When set to `'any'` all options are set to their defaults.

`bdr.alter_proxy_option`

Change a proxy configuration.

Synopsis

```
bdr.alter_proxy_option(proxy_name text, config_key text, config_value
text);
```

Parameters

Name	Type	Default	Description
`proxy_name`	text		Name of the proxy to change.
`config_key`	text		Key of the option in the proxy to change.
`config_value`	text		New value to set for the given key.

The table shows the proxy options (`config_key`) that can be changed using this function.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Option	Description
`listen_address`	Address for the proxy to listen on. Default is '{0.0.0.0}'.
`listen_port`	Port for the proxy to listen on. Default is '6432' in 'default' or 'any' mode and '0' in 'read-only' mode, which disables the write leader following port.
`max_client_conn`	Maximum number of connections for the proxy to accept. Default is '32767'.
`max_server_conn`	Maximum number of connections the proxy can make to the Postgres node. Default is '32767'.
`server_conn_timeout`	Connection timeout for server connections. Default is '2' (seconds).
`server_conn_keepalive`	Keepalive interval for server connections. Default is '10' (seconds).
`consensus_grace_period`	Duration for which proxy continues to route even upon loss of a Raft leader. If set to 0s, proxy stops routing immediately. Default is generally '6' (seconds) for local proxies and '12' (seconds) for global proxies. These values will be overridden if `raft_response_timeout`, `raft_global_election_timeout`, or `raft_group_election_timeout` are changed from their defaults.
`read_listen_address`	Address for the read-only proxy to listen on. Default is '{0.0.0.0}'.
`read_listen_port`	Port for the read-only proxy to listen on. Default is '6433' in 'read-only' or 'any' mode and '0' in 'default' mode, which disables the read-only port.
`read_max_client_conn`	Maximum number of connections for the read-only proxy to accept. Default is '32767'.
`read_max_server_conn`	Maximum number of connections the read-only proxy can make to the Postgres node. Default is '32767'.
`read_server_conn_keepalive`	Keepalive interval for read-only server connections. Default is '10' (seconds).
`read_server_conn_timeout`	Connection timeout for read-only server connections. Default is '2' (seconds).
`read_consensus_grace_period`	Duration for which read-only proxy continues to route even upon loss of a Raft leader. Default is 1 hour.

Changing any of these values requires a restart of the proxy.

`bdr.drop_proxy`

Drop a proxy configuration.

Synopsis

```
bdr.drop_proxy(proxy_name
text);
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameters

Name	Type	Default	Description
`proxy_name`	text		Name of the proxy to drop.

`bdr.routing_leadership_transfer`

Changing the routing leader transfers the leadership of the node group to another node.

Synopsis

```
bdr.routing_leadership_transfer(node_group_name text,
              leader_name
text,
              transfer_method text DEFAULT 'strict',
              transfer_timeout interval DEFAULT
'10s');
```

Parameters

Name	Type	Default	Description
`node_group_name`	text		Name of group where the leadership transfer is requested.
`leader_name`	text		Name of node that will become write leader.
`transfer_method`	text	`'strict'`	Type of the transfer. It can be `'fast'` or the default, `'strict'`, which checks the maximum lag.
`transfer_timeout`	interval	'10s'	Timeout of the leadership transfer. Default is 10 seconds.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.7 Commit scopes

Commit scopes are rules that determine how transaction commits and conflicts are handled within a PGD system. You can read more about them in Commit Scopes.

You can manipulate commit scopes using the following functions:

- `bdr.create_commit_scope`
- `bdr.alter_commit_scope`
- `bdr.drop_commit_scope`

Commit scope syntax

The overall grammar for commit scope rules is composed as follows:

```
commit_scope:
    commit_scope_operation [AND ...]

commit_scope_operation:
    commit_scope_group confirmation_level commit_scope_kind

commit_scope_target:
    { (node_group [, ...])
      | ORIGIN_GROUP }

commit_scope_group:
{ ANY num [NOT] commit_scope_target
  | MAJORITY [NOT] commit_scope_target
  | ALL [NOT] commit_scope_target }

confirmation_level:
    [ ON { received|replicated|durable|visible } ]

commit_scope_kind:
{ GROUP COMMIT [ ( group_commit_parameter = value [, ... ] ) ] [ ABORT ON ( abort_on_parameter = value ) ] [ DEGRADE
ON (degrade_on_parameter = value [, ... ] ) TO commit_scope_degrade_operation ]
  | CAMO [ DEGRADE ON ( degrade_on_parameter = value [, ... ] ) TO ASYNC ]
  | LAG CONTROL [ ( lag_control_parameter = value [, ... ] ) ]
  | SYNCHRONOUS COMMIT [ DEGRADE ON (degrade_on_parameter = value ) TO commit_scope_degrade_operation ] }

commit_scope_degrade_operation:
   commit_scope_group confirmation_level commit_scope_kind
```

Where `node_group` is the name of a PGD data node group.

commit_scope_degrade_operation

The `commit_scope_degrade_operation` is either the same commit scope kind with a less restrictive commit scope group as the overall rule being defined, or is asynchronous (`ASYNC`).

For instance, you can degrade from an `ALL SYNCHRONOUS COMMIT` to a `MAJORITY SYNCHRONOUS COMMIT` or a `MAJORITY SYNCHRONOUS COMMIT` to an `ANY 3 SYNCHRONOUS COMMIT` or even an `ANY 3 SYNCHRONOUS COMMIT` to an `ANY 2 SYNCHRONOUS COMMIT` . You can also degrade from `SYNCHRONOUS COMMIT` to `ASYNC` . However, you cannot degrade from `SYNCHRONOUS COMMIT` to `GROUP COMMIT` or the other way around, regardless of the commit scope groups involved.

It is also possible to combine rules using `AND` , each with their own degradation clause:

```
ALL ORIGIN_GROUP SYNCHRONOUS COMMIT DEGRADE ON (timeout = 10s) TO MAJORITY ORIGIN_GROUP SYNCHRONOUS COMMIT AND ANY 1
NOT ORIGIN_GROUP SYNCHRONOUS COMMIT DEGRADE ON (timeout = 20s) TO ASYNC
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Commit scope targets

ORIGIN_GROUP

Instead of targeting a specific group, you can also use `ORIGIN_GROUP`, which dynamically refers to the bottommost group from which a transaction originates. Therefore, if you have a top level group, `top_group`, and two subgroups as children, `left_dc` and `right_dc`, then adding a commit scope like:

```
SELECT
bdr.create_commit_scope(
    commit_scope_name := 'example_scope',
    origin_node_group := 'top_level_group',
    rule := 'MAJORITY ORIGIN_GROUP SYNCHRONOUS
COMMIT',
    wait_for_ready :=
true
);
```

would mean that for transactions originating on a node in `left_dc`, a majority of the nodes of `left_dc` would need to confirm the transaction synchronously before the transaction is committed. Moreover, the same rule would also mean that for transactions originating from a node in `right_dc`, a majority of nodes from `right_dc` are required to confirm the transaction synchronously before it is committed. This saves the need to add two seperate rules, one for `left_dc` and one for `right_dc`, to the commit scope.

Commit scope groups

ANY

Example: `ANY 2 (left_dc)`

A transaction under this commit scope group will be considered committed after any two nodes in the `left_dc` group confirm they processed the transaction.

ANY NOT

Example: `ANY 2 NOT (left_dc)`

A transaction under this commit scope group will be considered committed if any two nodes that aren't in the `left_dc` group confirm they processed the transaction.

MAJORITY

Example: `MAJORITY (left_dc)`

A transaction under this commit scope group will be considered committed if a majority of the nodes in the `left_dc` group confirm they processed the transaction.

MAJORITY NOT

Example: `MAJORITY NOT (left_dc)`

A transaction under this commit scope group will be considered committed if a majority of the nodes that aren't in the `left_dc` group confirm they processed the transaction.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

ALL

Example: `ALL (left_dc)`

A transaction under this commit scope group will be considered committed if all of the nodes in the `left_dc` group confirm they processed the transaction.

When `ALL` is used with `GROUP COMMIT`, the `commit_decision` setting must be set to `raft` to avoid reconciliation issues.

ALL NOT

Example: `ALL NOT (left_dc)`

A transaction under this commit scope group will be considered committed if all of the nodes that aren't in the `left_dc` group confirm they processed the transaction.

Confirmation level

The confirmation level sets the point in time when a remote PGD node confirms that it reached a particular point in processing a transaction.

ON received

A transaction is confirmed immediately after receiving it, prior to starting the local application.

ON replicated

A transaction is confirmed after applying changes of the transaction but before flushing them to disk.

ON durable

A transaction is confirmed after all of its changes are flushed to disk.

ON visible

This is the default visibility. A transaction is confirmed after all of its changes are flushed to disk and it's visible to concurrent transactions.

Commit Scope kinds

More details of the commit scope kinds and details of their parameters:

- Synchronous Commit
- Group Commit
- CAMO (Commit At Most Once)
- Lag Control

> **Parameter values**
>
> Specify Boolean, enum, int, and interval values using the Postgres GUC parameter value conventions.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

SYNCHRONOUS COMMIT

```
SYNCHRONOUS COMMIT [ DEGRADE ON (degrade_on_parameter = value ) TO commit_scope_degrade_operation ]
```

DEGRADE ON parameters

Parameter	Type	Default	Description
`timeout`	interval	0	Timeout in milliseconds (accepts other units) after which operation degrades. (0 means not set.)
`require_write_lead`	Boolean	False	Specifies whether the node must be a write lead to be able to switch to degraded operation.

These set the conditions on which the commit scope rule will degrade to a less restrictive mode of operation.

commit_scope_degrade_operation

The `commit_scope_degrade_operation` must be `SYNCHRONOUS COMMIT` with a less restrictive commit scope group—or must be asynchronous (`ASYNC`).

GROUP COMMIT

Allows commits to be confirmed by a consensus of nodes, controls conflict resolution settings, and, like `SYNCHRONOUS COMMIT`, has optional rule-degredation parameters.

```
GROUP COMMIT [ ( group_commit_parameter = value [, ...] ) ] [ ABORT ON ( abort_on_parameter = value ) ] [ DEGRADE ON
(degrade_on_parameter = value ) TO commit_scope_degrade_operation ]
```

GROUP COMMIT parameters

Parameter	Type	Default	Description
`transaction_tracking`	Boolean	Off/False	Specifies whether to track status of transaction. See transaction_tracking settings.
`conflict_resolution`	enum	async	Specifies how to handle conflicts. (`async` | `eager`). See conflict_resolution settings.
`commit_decision`	enum	group	Specifies how the COMMIT decision is made. (`group` | `partner` | `raft`). See commit_decision settings.

ABORT ON parameters

Parameter	Type	Default	Description
`timeout`	interval	0	Timeout in milliseconds (accepts other units). (0 means not set.)
`require_write_lead`	Boolean	False	CAMO only. If set, then for a transaction to switch to local (async) mode, a consensus request is required.

DEGRADE ON parameters

Parameter	Type	Default	Description
`timeout`	interval	0	Timeout in milliseconds (accepts other units) after which operation degrades. (0 means not set.)
`require_write_lead`	Boolean	False	Specifies whether the node must be a write lead to be able to switch to degraded operation.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

transaction_tracking settings

When set to true, two-phase commit transactions:

- Look up commit decisions when a writer is processing a PREPARE message.
- When recovering from an interruption, look up the transactions prepared before the interruption. When found, it then looks up the commit scope of the transaction and any corresponding RAFT commit decision. Suppose the node is the origin of the transaction and doesn't have a RAFT commit decision, and `transaction_tracking` is on in the commit scope. In that case, it periodically looks for a RAFT commit decision for this unresolved transaction until it's committed or aborted.

conflict_resolution settings

The value `async` means resolve conflicts asynchronously during replication using the conflict resolution policy.

The value `eager` means that conflicts are resolved eagerly during COMMIT by aborting one of the conflicting transactions.

Eager is only available with `MAJORITY` or `ALL` commit scope groups.

When used with the `ALL` commit scope group, the `commit_decision` must be set to `raft` to avoid reconcilation issue.

See "Conflict resolution" in Group Commit.

commit_decision settings

The value `group` means the preceding `commit_scope_group` specification also affects the COMMIT decision, not just durability.

The value `partner` means the partner node decides whether transactions can be committed. This value is allowed only on groups with 2 data nodes.

The value `raft` means the decision makes use of PGD's built-in Raft consensus. Once all the nodes in the selected commit scope group have confirmed the transaction, to ensure that all the nodes in the PGD cluster have noted the transaction, it is noted with the all-node Raft.

This option must be used when the `ALL` commit scope group is being used to ensure no divergence between the nodes over the decision. This option may have low performance.

See "Commit decisions" in Group Commit.

commit_scope_degrade_operation settings

The `commit_scope_degrade_operation` must be `GROUP_COMMIT` with a less restrictive commit scope group—or must be asynchronous (`ASYNC`).

CAMO

With the client's cooperation, enables protection to prevent multiple insertions of the same transaction in failover scenarios.

See "CAMO" in Durability for more details.

```
CAMO [ DEGRADE ON ( degrade_on_parameter = value ) TO ASYNC ]
```

DEGRADE ON parameters

Allows degrading to asynchronous operation on timeout.

Parameter	Type	Default	Description
`timeout`	interval	0	Timeout in milliseconds (accepts other units) after which operation becomes asynchronous. (0 means not set.)

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameter	Type	Default	Description
require_write_lead	Boolean	False	Specifies whether the node must be a write lead to be able to switch to asynchronous mode.

LAG CONTROL

Allows the configuration of dynamic rate-limiting controlled by replication lag.

See "Lag Control" in Durability for more details.

```
LAG CONTROL [ ( lag_control_parameter = value [, ... ] ) ]
```

LAG CONTROL parameters

Parameter	Type	Default	Description
max_lag_size	int	0	The maximum lag in kB that a given node can have in the replication connection to another node. When the lag exceeds this maximum scaled by max_commit_delay, lag control adjusts the commit delay.
max_lag_time	interval	0	The maximum replication lag in milliseconds that the given origin can have with regard to a replication connection to a given downstream node.
max_commit_delay	interval	0	Configures the maximum delay each commit can take, in fractional milliseconds. If set to 0, it disables Lag Control. After each commit delay adjustment (for example, if the replication is lagging more than max_lag_size or max_lag_time), the commit delay is recalculated with the weight of the bdr.lag_control_commit_delay_adjust GUC. The max_commit_delay is a ceiling for the commit delay.

- If max_lag_size and max_lag_time are set to 0, the LAG CONTROL is disabled.
- If max_commit_delay is not set or set to 0, the LAG CONTROL is disabled.

The lag size is derived from the delta of the send_ptr of the walsender to the apply_ptr of the receiver.

The lag time is calculated according to the following formula:

```
  lag_time = (lag_size / apply_rate) * 1000;
```

Where lag_size is the delta between the send_ptr and apply_ptr (as used for max_lag_size), and apply_rate is a weighted exponential moving average, following the simplified formula:

```
  apply_rate = prev_apply_rate * (1 - apply_rate_weight) +
               ((apply_ptr_diff * apply_rate_weight) / diff_secs);
```

Where:

- prev_apply_rate was the previously configured apply_rate, before recalculating the new rate.
- apply_rate_weight is the value of the GUC bdr.lag_tracker_apply_rate_weight.
- apply_ptr_diff is the difference between the current apply_ptr and the apply_ptr at the point in time when the apply rate was last computed.
- diff_secs is the delta in seconds from the last time the apply rate was calculated.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.8 Conflicts

Conflict detection

List of conflict types

PGD recognizes the following conflict types, which can be used as the `conflict_type` parameter:

Conflict type	Description
`insert_exists`	An incoming insert conflicts with an existing row by way of a primary key or a unique key/index.
`update_differing`	An incoming update's key row differs from a local row. This can happen only when using row version conflict detection.
`update_origin_change`	An incoming update is modifying a row that was last changed by a different node.
`update_missing`	An incoming update is trying to modify a row that doesn't exist.
`update_recently_deleted`	An incoming update is trying to modify a row that was recently deleted.
`update_pkey_exists`	An incoming update has modified the `PRIMARY KEY` to a value that already exists on the node that's applying the change.
`multiple_unique_conflicts`	An incoming row conflicts with multiple rows per UNIQUE/EXCLUDE indexes of the target table.
`delete_recently_updated`	An incoming delete with an older commit timestamp than the most recent update of the row on the current node or when using row version conflict detection.
`delete_missing`	An incoming delete is trying to remove a row that doesn't exist.
`target_column_missing`	The target table is missing one or more columns present in the incoming row.
`source_column_missing`	The incoming row is missing one or more columns that are present in the target table.
`target_table_missing`	The target table is missing.
`apply_error_ddl`	An error was thrown by Postgres when applying a replicated DDL command.

Conflict resolution

Most conflicts can be resolved automatically. PGD defaults to a last-update-wins mechanism or, more accurately, the `update_if_newer` conflict resolver. This mechanism retains the most recently inserted or changed row of the two conflicting ones based on the same commit timestamps used for conflict detection. The behavior in certain corner-case scenarios depends on the settings used for `bdr.create_node_group` and alternatively for `bdr.alter_node_group`.

PGD lets you override the default behavior of conflict resolution by using the following function.

List of conflict resolvers

Several conflict resolvers are available in PGD, with differing coverages of the conflict types they can handle:

Resolver	Description
`error`	Throws an error and stops replication.
`skip`	Skips processing the remote change and continues replication with the next change. Can be used for `insert_exists`, `update_differing`, `update_origin_change`, `update_missing`, `update_recently_deleted`, `update_pkey_exists`, `delete_recently_updated`, `delete_missing`, `target_table_missing`, `target_column_missing`, and `source_column_missing` conflict types.
`skip_if_recently_dropped`	Skips the remote change if it's for a table that doesn't exist downstream because it was recently (within one day) dropped on the downstream. Throw an error otherwise. Can be used for the `target_table_missing` conflict type. This conflict resolver can pose challenges if a table with the same name is re-created shortly after it's dropped. In that case, one of the nodes might see the DMLs on the re-created table before it sees the DDL to re-create the table. It then incorrectly skips the remote data, assuming that the table is recently dropped, and causes data loss. We recommend that when using this resolver, you don't reuse the object names immediately after they're dropped.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Resolver	Description
`skip_transaction`	Skips the whole transaction that generated the conflict.
`update_if_newer`	Updates if the remote row was committed later (as determined by the wall clock of the originating node) than the conflicting local row. If the timestamps are same, the node id is used as a tie-breaker to ensure that same row is picked on all nodes (higher nodeid wins). Can be used for `insert_exists`, `update_differing`, `update_origin_change`, and `update_pkey_exists` conflict types.
`update`	Always performs the replicated action. Can be used for `insert_exists` (turns the `INSERT` into `UPDATE`), `update_differing`, `update_origin_change`, `update_pkey_exists`, and `delete_recently_updated` (performs the delete).
`insert_or_skip`	Tries to build a new row from available information sent by the origin and INSERT it. If there isn't enough information available to build a full row, skips the change. Can be used for `update_missing` and `update_recently_deleted` conflict types.
`insert_or_error`	Tries to build new row from available information sent by origin and insert it. If there isn't enough information available to build full row, throws an error and stops the replication. If there isn't enough information available to build full row, throws an error and stops the replication. Can be used for `update_missing` and `update_recently_deleted` conflict types.
`ignore`	Ignores any missing target column and continues processing.Can be used for the `target_column_missing` conflict type.
`ignore_if_null`	Ignores a missing target column if the extra column in the remote row contains a NULL value. Otherwise, throws an error and stops replication. Can be used for the `target_column_missing` conflict type.
`use_default_value`	Fills the missing column value with the default (including NULL if that's the column default) and continues processing. Any error while processing the default or violation of constraints (that is, NULL default on NOT NULL column) stops replication. Can be used for the `source_column_missing` conflict type.

The `insert_exists`, `update_differing`, `update_origin_change`, `update_missing`, `multiple_unique_conflicts`, `update_recently_deleted`, `update_pkey_exists`, `delete_recently_updated`, and `delete_missing` conflict types can also be resolved by user-defined logic using Conflict triggers.

This matrix shows the conflict types each conflict resolver can handle.

	insert_exists	update_differing	update_origin_change	update_missing	update_recently_deleted	update_pkey_exists	delete_recently_updated	delete_missing	target_column_missing	source_column_missing	target_table_missing	multiple_unique_conflicts
error	X	X	X	X	X	X	X	X	X	X	X	X
skip	X	X	X	X	X	X	X	X	X	X	X	X
skip_if_recently_dropped											X	
update_if_newer	X	X	X			X						
update	X	X	X			X	X					X
insert_or_skip				X	X							
insert_or_error				X	X							
ignore									X			
ignore_if_null									X			
use_default_value										X		
conflict_trigger	X	X	X	X	X	X	X	X				X

Default conflict resolvers

Conflict type	Resolver
insert_exists	update_if_newer
update_differing	update_if_newer
update_origin_change	update_if_newer
update_missing	insert_or_skip
update_recently_deleted	skip
update_pkey_exists	update_if_newer

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Conflict type	Resolver
multiple_unique_conflicts	error
delete_recently_updated	skip
delete_missing	skip
target_column_missing	ignore_if_null
source_column_missing	use_default_value
target_table_missing (see note)	skip_if_recently_dropped
apply_error_ddl	error

> **target_table_missing**
>
> This conflict type isn't detected on community Postgresql. If the target table is missing, it causes an error and halts replication. EDB Postgres servers detect and handle missing target tables and can invoke the resolver.

List of conflict resolutions

The conflict resolution represents the kind of resolution chosen by the conflict resolver and corresponds to the specific action that was taken to resolve the conflict.

The following conflict resolutions are currently supported for the `conflict_resolution` parameter:

Resolution	Description
`apply_remote`	The remote (incoming) row was applied.
`skip`	Processing of the row was skipped (no change was made locally).
`merge`	A new row was created, merging information from remote and local row.
`user`	User code (a conflict trigger) produced the row that was written to the target table.

Conflict logging

To ease diagnosing and handling multi-master conflicts, PGD, by default, logs every conflict into the `bdr.conflict_history` table. You can change this behavior with more granularity using bdr.alter_node_set_log_config.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.9 Conflict functions

`bdr.alter_table_conflict_detection`

Allows the table owner to change how conflict detection works for a given table.

Synopsis

```
bdr.alter_table_conflict_detection(relation regclass,
                                   method text,
                                   column_name name DEFAULT
NULL)
```

Parameters

- `relation` — Name of the relation for which to set the new conflict detection method.
- `method` — The conflict detection method to use.
- `column_name` — The column to use for storing the column detection data. This can be skipped, in which case the column name is chosen based on the conflict detection method. The `row_origin` method doesn't require an extra column for metadata storage.

The recognized methods for conflict detection are:

- `row_origin` — Origin of the previous change made on the tuple (see Origin conflict detection). This is the only method supported that doesn't require an extra column in the table.
- `row_version` — Row version column (see Row version conflict detection).
- `column_commit_timestamp` — Per-column commit timestamps (described in CLCD).
- `column_modify_timestamp` — Per-column modification timestamp (described in CLCD).

Notes

For more information about the difference between `column_commit_timestamp` and `column_modify_timestamp` conflict detection methods, see Current versus commit timestamp.

This function uses the same replication mechanism as `DDL` statements. This means the replication is affected by the ddl filters configuration.

The function takes a `DML` global lock on the relation for which column-level conflict resolution is being enabled.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction, and the changes are visible to the current transaction.

Only the owner of the `relation` can execute the `bdr.alter_table_conflict_detection` function unless `bdr.backwards_compatibility` is set to 30618 or less.

> **Warning**
>
> When changing the conflict detection method from one that uses an extra column to store metadata, that column is dropped.

> **Warning**
>
> This function disables CAMO and gives a warning, as long as warnings aren't disabled with `bdr.camo_enable_client_warnings`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.alter_node_set_conflict_resolver`

This function sets the behavior of conflict resolution on a given node.

Synopsis

```
bdr.alter_node_set_conflict_resolver(node_name text,
                                     conflict_type text,
                                     conflict_resolver text)
```

Parameters

- `node_name` — Name of the node that's being changed.
- `conflict_type` — Conflict type for which to apply the setting (see List of conflict types).
- `conflict_resolver` — Resolver to use for the given conflict type (see List of conflict resolvers).

Notes

Currently you can change only the local node. The function call isn't replicated. If you want to change settings on multiple nodes, you must run the function on each of them.

The configuration change made by this function overrides any default behavior of conflict resolutions specified by `bdr.create_node_group` or `bdr.alter_node_group`.

This function is transactional. You can roll back the changes, and they are visible to the current transaction.

`bdr.alter_node_set_log_config`

Set the conflict logging configuration for a node.

Synopsis

```
bdr.alter_node_set_log_config(node_name text,
                              log_to_file bool DEFAULT
true,
                              log_to_table bool DEFAULT true,
                              conflict_type text[] DEFAULT
NULL,
                              conflict_resolution text[] DEFAULT
NULL)
```

Parameters

- `node_name` — Name of the node that's being changed.
- `log_to_file` — Whether to log to the node log file.
- `log_to_table` — Whether to log to the `bdr.conflict_history` table.
- `conflict_type` — Conflict types to log. NULL (the default) means all.
- `conflict_resolution` — Conflict resolutions to log. NULL (the default) means all.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Notes

You can change only the local node. The function call isn't replicated. If you want to change settings on multiple nodes, you must run the function on each of them.

This function is transactional. You can roll back the changes, and they're visible to the current transaction.

Listing conflict logging configurations

The view `bdr.node_log_config` shows all the logging configurations. It lists the name of the logging configuration, where it logs, and the conflict type and resolution it logs.

Logging conflicts to a table

If `log_to_table` is set to true, conflicts are logged to a table. The target table for conflict logging is `bdr.conflict_history`.

This table is range partitioned on the column `local_time`. The table is managed by autopartition. By default, a new partition is created for every day, and conflicts of the last one month are maintained. After that, the old partitions are dropped. Autopartition creates between 7 and 14 partitions in advance. bdr_superuser can change these defaults.

Since conflicts generated for all tables managed by PGD are logged to this table, it's important to ensure that only legitimate users can read the conflicted data. PGD does this by defining ROW LEVEL SECURITY policies on the `bdr.conflict_history` table. Only owners of the tables are allowed to read conflicts on the respective tables. If the underlying tables have RLS policies defined, enabled, and enforced, then even owners can't read the conflicts. RLS policies created with the FORCE option also apply to owners of the table. In that case, some or all rows in the underlying table might not be readable even to the owner. So PGD also enforces a stricter policy on the conflict log table.

The predefined role bdr_read_all_conflicts can be granted to users who need to see all conflict details logged to the `bdr.conflict_history` table without also granting them bdr_superuser role.

The default role bdr_read_all_stats has access to a catalog view called `bdr.conflict_history_summary`. This view doesn't contain user data, allowing monitoring of any conflicts logged.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.10 Replication set management

> **Replication management and DDL**
>
> With the exception of `bdr.alter_node_replication_sets`, the following functions are considered to be `DDL`. DDL replication and global locking apply to them, if that's currently active. See DDL replication.

`bdr.create_replication_set`

This function creates a replication set.

Replication of this command is affected by DDL replication configuration, including DDL filtering settings.

Synopsis

```
bdr.create_replication_set(set_name name,
                           replicate_insert boolean DEFAULT
true,
                           replicate_update boolean DEFAULT
true,
                           replicate_delete boolean DEFAULT
true,
                           replicate_truncate boolean DEFAULT true,
                           autoadd_tables boolean DEFAULT
false,
                           autoadd_existing boolean DEFAULT
true)
```

Parameters

- `set_name` — Name of the new replication set. Must be unique across the PGD group.
- `replicate_insert` — Indicates whether to replicate inserts into tables in this replication set.
- `replicate_update` — Indicates whether to replicate updates of tables in this replication set.
- `replicate_delete` — Indicates whether to replicate deletes from tables in this replication set.
- `replicate_truncate` — Indicates whether to replicate truncates of tables in this replication set.
- `autoadd_tables` — Indicates whether to replicate newly created (future) tables to this replication set
- `autoadd_existing` — Indicates whether to add all existing user tables to this replication set. This parameter has an effect only if `autoadd_tables` is set to `true`.

Notes

By default, new replication sets don't replicate DDL or PGD administration function calls. See DDL filters for how to set up DDL replication for replication sets. A preexisting DDL filter is set up for the default group replication set that replicates all DDL and admin function calls. It's created when the group is created but can be dropped in case you don't want the PGD group default replication set to replicate DDL or the PGD administration function calls.

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the DDL filters configuration.

The function takes a `DDL` global lock.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.alter_replication_set`

This function modifies the options of an existing replication set.

Replication of this command is affected by DDL replication configuration, including DDL filtering settings.

Synopsis

```
bdr.alter_replication_set(set_name name,
                          replicate_insert boolean DEFAULT
NULL,
                          replicate_update boolean DEFAULT
NULL,
                          replicate_delete boolean DEFAULT
NULL,
                          replicate_truncate boolean DEFAULT NULL,
                          autoadd_tables boolean DEFAULT
NULL)
```

Parameters

- `set_name` — Name of an existing replication set.
- `replicate_insert` — Indicates whether to replicate inserts into tables in this replication set.
- `replicate_update` — Indicates whether to replicate updates of tables in this replication set.
- `replicate_delete` — Indicates whether to replicate deletes from tables in this replication set.
- `replicate_truncate` — Indicates whether to replicate truncates of tables in this replication set.
- `autoadd_tables` — Indicates whether to add newly created (future) tables to this replication set.

Any of the options that are set to NULL (the default) remain the same as before.

Notes

This function uses the same replication mechanism as `DDL` statements. This means the replication is affected by the DDL filters configuration.

The function takes a `DDL` global lock.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

`bdr.drop_replication_set`

This function removes an existing replication set.

Replication of this command is affected by DDL replication configuration, including DDL filtering settings.

Synopsis

```
bdr.drop_replication_set(set_name name)
```

Parameters

- `set_name` — Name of an existing replication set.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Notes

This function uses the same replication mechanism as `DDL` statements. This means the replication is affected by the ddl filters configuration.

The function takes a `DDL` global lock.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

> **Warning**
>
> Don't drop a replication set that's being used by at least another node because doing so stops replication on that node. If that happens, unsubscribe the affected node from that replication set. For the same reason, don't drop a replication set with a join operation in progress when the node being joined is a member of that replication set. Replication set membership is checked only at the beginning of the join. This happens because the information on replication set usage is local to each node, so that you can configure it on a node before it joins the group.

You can manage replication set subscriptions for a node using `alter_node_replication_sets`.

`bdr.alter_node_replication_sets`

This function changes the replication sets a node publishes and is subscribed to.

Synopsis

```
bdr.alter_node_replication_sets(node_name name,
                                set_names text[] DEFAULT
NULL,
                                pub_repsets text[] DEFAULT
NULL,
                                sub_repsets text[] DEFAULT
NULL)
```

Parameters

- `node_name` — The node to modify. Currently must be a local node.
- `set_names` — Replication sets applied to both the published and subscribed lists. Omit or pass `NULL` to leave the common list unchanged.
- `pub_repsets` — Additional replication sets added to the node's published list only, on top of `set_names`. Omit or pass `NULL` for none.
- `sub_repsets` — Additional replication sets added to the node's subscribed list only, on top of `set_names`. Omit or pass `NULL` for none.

You must give at least one of `set_names`, `pub_repsets`, or `sub_repsets` a non-`NULL` value. Calling the function without specifying any of them raises an error.

The node's final published replication sets are the union of `set_names` and `pub_repsets`. The node's final subscribed replication sets are the union of `set_names` and `sub_repsets`. Names appearing in more than one array aren't duplicated in the result.

Notes

This function is executed only on the local node and isn't replicated in any manner.

The replication sets listed aren't checked for existence, since this function is designed to execute before the node joins. Be careful to specify replication set names correctly to avoid errors.

This behavior allows for calling the function not only on the node that's part of the PGD group but also on a node that hasn't joined any group yet. This approach limits the data synchronized during the join. However, the schema is always fully synchronized without regard to the replication sets setting. All tables are copied across, not just the ones specified in the replication set. You can drop unwanted tables by referring to the `bdr.tables` catalog table. (These might be removed automatically in later versions of PGD.) This is currently true even if the DDL filters configuration otherwise prevents replication of DDL.

The replication sets that the node subscribes to after this call are published by the other nodes for actually replicating the changes from those nodes to the node where this function is executed.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.11 Replication set membership

`bdr.replication_set_add_table`

This function adds a table to a replication set.

This function adds a table to a replication set and starts replicating changes from the committing of the transaction that contains the call to the function. Any existing data the table might have on a node isn't synchronized. Replication of this command is affected by DDL replication configuration, including DDL filtering settings.

Synopsis

```
bdr.replication_set_add_table(relation regclass,
                              set_name name DEFAULT
NULL,
                              columns text[] DEFAULT
NULL,
                              row_filter text DEFAULT NULL)
```

Parameters

- `relation` — Name or Oid of a table.
- `set_name` — Name of the replication set. If NULL (the default), then the PGD group default replication set is used.
- `columns` — Reserved for future use (currently does nothing and must be NULL).
- `row_filter` — SQL expression to use for filtering the replicated rows. If this expression isn't defined (that is, it's set to NULL, the default) then all rows are sent.

The `row_filter` specifies an expression producing a Boolean result, with NULLs. Expressions evaluating to True or Unknown replicate the row. A False value doesn't replicate the row. Expressions can't contain subqueries or refer to variables other than columns of the current row being replicated. You can't reference system columns.

`row_filter` executes on the origin node, not on the target node. This puts an additional CPU overhead on replication for this specific table but completely avoids sending data for filtered rows. Hence network bandwidth is reduced and overhead on the target node is applied.

`row_filter` never removes `TRUNCATE` commands for a specific table. You can filter away `TRUNCATE` commands at the replication set level.

You can replicate just some columns of a table. See Replicating between nodes with differences.

Notes

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the DDL filters configuration.

If the `row_filter` isn't NULL, the function takes a `DML` global lock on the relation that's being added to the replication set. Otherwise it takes just a `DDL` global lock.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

`bdr.replication_set_remove_table`

This function removes a table from the replication set.

Replication of this command is affected by DDL replication configuration, including DDL filtering settings.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.replication_set_remove_table(relation regclass,
                                 set_name name DEFAULT
NULL)
```

Parameters

- `relation` — Name or Oid of a table.
- `set_name` — Name of the replication set. If NULL (the default), then the PGD group default replication set is used.

Notes

This function uses the same replication mechanism as `DDL` statements. This means the replication is affected by the DDL filters configuration.

The function takes a `DDL` global lock.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.12 DDL replication filtering

See also DDL replication filtering.

`bdr.replication_set_add_ddl_filter`

This function adds a DDL filter to a replication set.

Any DDL that matches the given filter is replicated to any node that's subscribed to that set. This function also affects replication of PGD admin functions.

This function doesn't prevent execution of DDL on any node. It only alters whether DDL is replicated to other nodes. Suppose two nodes have a replication filter between them that excludes all index commands. Index commands can still be executed freely by directly connecting to each node and executing the desired DDL on that node.

The DDL filter can specify a `command_tag` and `role_name` to allow replication of only some DDL statements. The `command_tag` is the same as those used by event triggers for regular PostgreSQL commands. A typical example might be to create a filter that prevents additional index commands on a logical standby from being replicated to all other nodes.

You can filter the PGD admin functions used by using a tagname matching the qualified function name. For example, `bdr.replication_set_add_table` is the command tag for the function of the same name. In this case, this tag allows all PGD functions to be filtered using `bdr.*`.

The `role_name` is used for matching against the current role that's executing the command. Both `command_tag` and `role_name` are evaluated as regular expressions, which are case sensitive.

Synopsis

```
bdr.replication_set_add_ddl_filter(set_name name,
                                   ddl_filter_name text,
                                   command_tag
text,
                                   role_name text DEFAULT NULL,
                                   base_relation_name text DEFAULT NULL,
                                   query_match text DEFAULT
NULL,
                                   exclusive boolean DEFAULT FALSE)
```

Parameters

- `set_name` — Name of the replication set. If NULL then the PGD group default replication set is used.
- `ddl_filter_name` — Name of the DDL filter. This name must be unique across the whole PGD group.
- `command_tag` — Regular expression for matching command tags. NULL means match everything.
- `role_name` — Regular expression for matching role name. NULL means match all roles.
- `base_relation_name` — Reserved for future use. Must be NULL.
- `query_match` — Regular expression for matching the query. NULL means match all queries.
- `exclusive` — If true, other matched filters aren't taken into consideration (that is, only the exclusive filter is applied). When multiple exclusive filters match, an error is thrown. This parameter is useful for routing specific commands to a specific replication set, while keeping the default replication through the main replication set.

Notes

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the DDL filters configuration. This also means that replication of changes to DDL filter configuration is affected by the existing DDL filter configuration.

The function takes a `DDL` global lock.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

To view the defined replication filters, use the view `bdr.ddl_replication`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Examples

To include only PGD admin functions, define a filter like this:

```
SELECT bdr.replication_set_add_ddl_filter('mygroup', 'mygroup_admin',
$$bdr\..*$$);
```

To exclude everything except for index DDL:

```
SELECT bdr.replication_set_add_ddl_filter('mygroup', 'index_filter',
                '^(?!(CREATE INDEX|DROP INDEX|ALTER
INDEX)).*');
```

To include all operations on tables and indexes but exclude all others, add two filters: one for tables and one for indexes. This example shows that multiple filters provide the union of all allowed DDL commands:

```
SELECT bdr.replication_set_add_ddl_filter('bdrgroup','index_filter', '^((?!INDEX).)*$');
SELECT bdr.replication_set_add_ddl_filter('bdrgroup','table_filter', '^((?!TABLE).)*$');
```

`bdr.replication_set_remove_ddl_filter`

This function removes the DDL filter from a replication set.

Replication of this command is affected by DDL replication configuration, including the DDL filtering settings.

Synopsis

```
bdr.replication_set_remove_ddl_filter(set_name name,
                                      ddl_filter_name text)
```

Parameters

- `set_name` — Name of the replication set. If NULL then the PGD group default replication set is used.
- `ddl_filter_name` — Name of the DDL filter to remove.

Notes

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the DDL filters configuration. This also means that replication of changes to the DDL filter configuration is affected by the existing DDL filter configuration.

The function takes a `DDL` global lock.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.13 Testing and tuning commands

EDB Postgres Distributed has tools that help with testing and tuning your PGD clusters. For background, see Testing and tuning.

`pgd_bench`

Synopsis

A benchmarking tool for EDB Postgres Distributed deployments.

```
pgd_bench [OPTION]... [DBNAME] [DBNAME2]
```

`DBNAME` can be a conninfo string of the format: `"host=10.1.1.2 user=postgres dbname=master"`

See pgd_bench in Testing and tuning for examples of pgd_bench options and usage.

Options

The pgd_bench command is implemented as a wrapper around the pgbench command. This means that it shares many of the same options and created tables named `pgbench` as it performs its testing.

Options that are specific to pgd_bench include the following.

Setting mode

`-m` or `--mode`

The mode can be set to `regular`, `camo`, or `failover`. The default is `regular`.

- `regular` — Only a single node is needed to run pgd_bench.
- `camo` — A second node must be specified to act as the CAMO partner. (CAMO must be set up.)
- `failover` — A second node must be specified to act as the failover.

When using `-m failover`, an additional option `--retry` is available. This option instructs pgd_bench to retry transactions when there's a failover. The `--retry` option is automatically enabled when `-m camo` is used.

Setting GUC variables

`-o` or `--set-option`

This option is followed by `NAME=VALUE` entries, which are applied using the Postgres `SET` command on each server that pgd_bench connects to, and only those servers.

The other options are identical to the Postgres pgbench command. For details, see the PostgreSQL pgbench documentation.

The complete list of options (pgd_bench and pgbench) follow.

Initialization options

- `-i, --initialize` — Invoke initialization mode.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

- `-I, --init-steps=[dtgGvpf]+` (default `"dtgvp"`) — Run selected initialization steps.
  - `d` — Drop any existing pgbench tables.
  - `t` — Create the tables used by the standard pgbench scenario.
  - `g` — Generate data client-side and load it into the standard tables, replacing any data already present.
  - `G` — Generate data server-side and load it into the standard tables, replacing any data already present.
  - `v` — Invoke `VACUUM` on the standard tables.
  - `p` — Create primary key indexes on the standard tables.
  - `f` — Create foreign key constraints between the standard tables.

- `-F, --fillfactor=NUM` — Set fill factor.
- `-n, --no-vacuum` — Don't run `VACUUM` during initialization.
- `-q, --quiet` — Quiet logging (one message every 5 seconds).
- `-s, --scale=NUM` — Scaling factor.
- `--foreign-keys` — Create foreign key constraints between tables.
- `--index-tablespace=TABLESPACE` — Create indexes in the specified tablespace.
- `--partition-method=(range|hash)` — Partition `pgbench_accounts` with this method. The default is `range`.
- `--partitions=NUM` — Partition `pgbench_accounts` into `NUM` parts. The default is `0`.
- `--tablespace=TABLESPACE` — Create tables in the specified tablespace.
- `--unlogged-tables` — Create tables as unlogged tables. (Note: Unlogged tables aren't replicated.)

Options to select what to run

- `-b, --builtin=NAME[@W]` — Add built-in script NAME weighted at W. The default is 1. Use `-b list` to list available scripts.
- `-f, --file=FILENAME[@W]` — Add script `FILENAME` weighted at W. The default is 1.
- `-N, --skip-some-updates` — Updates of pgbench_tellers and pgbench_branches. Same as `-b simple-update`.
- `-S, --select-only` — Perform SELECT-only transactions. Same as `-b select-only`.

Benchmarking options

- `-c, --client=NUM` — Number of concurrent database clients. The default is 1.
- `-C, --connect` — Establish new connection for each transaction.
- `-D, --define=VARNAME=VALUE` — Define variable for use by custom script.
- `-j, --jobs=NUM` — Number of threads. The default is 1.
- `-l, --log` — Write transaction times to log file.
- `-L, --latency-limit=NUM` — Count transactions lasting more than NUM ms as late.
- `-m, --mode=regular|camo|failover` — Mode in which to run pgbench. The default is `regular`.
- `-M, --protocol=simple|extended|prepared` — Protocol for submitting queries. The default is `simple`.
- `-n, --no-vacuum` — Don't run `VACUUM` before tests.
- `-o, --set-option=NAME=VALUE` — Specify runtime `SET` option.
- `-P, --progress=NUM` — Show thread progress report every NUM seconds.
- `-r, --report-per-command` — Latencies, failures, and retries per command.
- `-R, --rate=NUM` — Target rate in transactions per second.
- `-s, --scale=NUM` — Report this scale factor in output.
- `-t, --transactions=NUM` — Number of transactions each client runs. The default is 10.
- `-T, --time=NUM` — Duration of benchmark test, in seconds.
- `-v, --vacuum-all` — Vacuum all four standard tables before tests.
- `--aggregate-interval=NUM` — Data over NUM seconds.
- `--failures-detailed` — Report the failures grouped by basic types.
- `--log-prefix=PREFIX` — Prefix for transaction time log file. The default is `pgbench_log`.
- `--max-tries=NUM` — Max number of tries to run transaction. The default is `1`.
- `--progress-timestamp` — Use Unix epoch timestamps for progress.
- `--random-seed=SEED` — Set random seed (`time`, `rand`, `integer`).
- `--retry` — Retry transactions on failover. Used with `-m`.
- `--sampling-rate=NUM` — Fraction of transactions to log, for example, 0.01 for 1%.
- `--show-script=NAME` — Show built-in script code, then exit.
- `--verbose-errors` — Print messages of all errors.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Common options:

- `-d, --debug` — Print debugging output.
- `-h, --host=HOSTNAME` — Database server host or socket directory.
- `-p, --port=PORT` — Database server port number.
- `-U, --username=USERNAME` — Connect as specified database user.
- `-V, --version` — Output version information, then exit.
- `-?, --help` — Show help, then exit.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.14 Global sequence management interfaces

PGD provides an interface for converting between a standard PostgreSQL sequence and the PGD global sequence.

The following functions are considered to be `DDL`, so DDL replication and global locking applies to them.

Sequence functions

`bdr.alter_sequence_set_kind`

Allows the owner of a sequence to set the kind of a sequence. Once set, `seqkind` is visible only by way of the `bdr.sequences` view. In all other ways, the sequence appears as a normal sequence.

PGD treats this function as `DDL`, so DDL replication and global locking applies, if it's currently active. See DDL replication.

Synopsis

```
bdr.alter_sequence_set_kind(seqoid regclass, seqkind text, start bigint DEFAULT
NULL)
```

Parameters

- `seqoid` — Name or Oid of the sequence to alter.
- `seqkind` — `local` for a standard PostgreSQL sequence, `snowflakeid` or `galloc` for globally unique PGD sequences, or `timeshard` for legacy globally unique sequence.
- `start` — Allows specifying new starting point for galloc and local sequences.

Notes

When changing the sequence kind to `galloc`, the first allocated range for that sequence uses the sequence start value as the starting point. When there are existing values that were used by the sequence before it was changed to `galloc`, we recommend moving the starting point so that the newly generated values don't conflict with the existing ones using the following command:

```
ALTER SEQUENCE seq_name START starting_value
RESTART
```

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the DDL filters configuration.

The function takes a global `DDL` lock. It also locks the sequence locally.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

Only the owner of the sequence can execute the `bdr.alter_sequence_set_kind` function, unless `bdr.backwards_compatibility` is set to 30618 or lower.

`bdr.extract_timestamp_from_snowflakeid`

This function extracts the timestamp component of the `snowflakeid` sequence. The return value is of type `timestamptz`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.extract_timestamp_from_snowflakeid(snowflakeid bigint)
```

Parameters

- `snowflakeid` — Value of a `snowflakeid` sequence.

Notes

This function executes only on the local node.

`bdr.extract_nodeid_from_snowflakeid`

This function extracts the nodeid component of the `snowflakeid` sequence.

Synopsis

```
bdr.extract_nodeid_from_snowflakeid(snowflakeid bigint)
```

Parameters

- `snowflakeid` — Value of a `snowflakeid` sequence.

Notes

This function executes only on the local node.

`bdr.extract_localseqid_from_snowflakeid`

This function extracts the local sequence value component of the `snowflakeid` sequence.

Synopsis

```
bdr.extract_localseqid_from_snowflakeid(snowflakeid bigint)
```

Parameters

- `snowflakeid` — Value of a `snowflakeid` sequence.

Notes

This function executes only on the local node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.timestamp_to_snowflakeid`

This function converts a timestamp value to a dummy `snowflakeid` sequence value.

This is useful for doing indexed searches or comparisons of values in the `snowflakeid` column and for a specific timestamp.

For example, given a table `foo` with a column `id` that's using a `snowflakeid` sequence, you can get the number of changes since yesterday midnight like this:

```
SELECT count(1) FROM foo WHERE id > bdr.timestamp_to_snowflakeid('yesterday')
```

A query formulated this way uses an index scan on the column `id`.

Synopsis

```
bdr.timestamp_to_snowflakeid(ts timestamptz)
```

Parameters

- `ts` — Timestamp to use for the `snowflakeid` sequence generation.

Notes

This function executes only on the local node.

`bdr.extract_timestamp_from_timeshard`

This function extracts the timestamp component of the `timeshard` sequence. The return value is of type `timestamptz`.

Synopsis

```
bdr.extract_timestamp_from_timeshard(timeshard_seq bigint)
```

Parameters

- `timeshard_seq` — Value of a `timeshard` sequence.

Notes

This function executes only on the local node.

`bdr.extract_nodeid_from_timeshard`

This function extracts the nodeid component of the `timeshard` sequence.

Synopsis

```
bdr.extract_nodeid_from_timeshard(timeshard_seq bigint)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameters

- `timeshard_seq` — Value of a `timeshard` sequence.

Notes

This function executes only on the local node.

`bdr.extract_localseqid_from_timeshard`

This function extracts the local sequence value component of the `timeshard` sequence.

Synopsis

```
bdr.extract_localseqid_from_timeshard(timeshard_seq bigint)
```

Parameters

- `timeshard_seq` — Value of a `timeshard` sequence.

Notes

This function executes only on the local node.

`bdr.timestamp_to_timeshard`

This function converts a timestamp value to a dummy `timeshard` sequence value.

This is useful for doing indexed searches or comparisons of values in the `timeshard` column and for a specific timestamp.

For example, given a table `foo` with a column `id` that's using a `timeshard` sequence, you can get the number of changes since yesterday midnight like this:

```
SELECT count(1) FROM foo WHERE id > bdr.timestamp_to_timeshard('yesterday')
```

A query formulated this way uses an index scan on the column `id`.

Synopsis

```
bdr.timestamp_to_timeshard(ts timestamptz)
```

Parameters

- `ts` — Timestamp to use for the `timeshard` sequence generation.

Notes

This function executes only on the local node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.galloc_chunk_info`

This function retrieves the ranges allocated to a galloc sequence on the local node.

An empty result set will be returned if the sequence has not yet been accessed on the local node.

An ERROR will be raised if the provided sequence name is not a galloc sequence.

Synopsis

```
bdr.galloc_chunk_info(seqname regclass)
```

Parameters

- `seqname` - the name of the galloc sequence to query

Notes

This function executes only on the local node.

KSUUID v2 functions

Functions for working with `KSUUID` v2 data, K-Sortable UUID data. See also KSUUID in the sequences documentation.

`bdr.gen_ksuuid_v2`

This function generates a new `KSUUID` v2 value using the value of timestamp passed as an argument or current system time if NULL is passed. If you want to generate KSUUID automatically using the system time, pass a NULL argument.

The return value is of type UUID.

Synopsis

```
bdr.gen_ksuuid_v2(timestamptz)
```

Notes

This function executes only on the local node.

`bdr.ksuuid_v2_cmp`

This function compares the `KSUUID` v2 values.

It returns 1 if the first value is newer, -1 if the second value is lower, or zero if they are equal.

Synopsis

```
bdr.ksuuid_v2_cmp(uuid, uuid)
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Parameters

- `UUID` — `KSUUID` v2 to compare.

Notes

This function executes only on the local node.

`bdr.extract_timestamp_from_ksuuid_v2`

This function extracts the timestamp component of `KSUUID` v2. The return value is of type `timestamptz`.

Synopsis

```
bdr.extract_timestamp_from_ksuuid_v2(uuid)
```

Parameters

- `UUID` — `KSUUID` v2 value to extract timestamp from.

Notes

This function executes only on the local node.

KSUUID v1 functions

Functions for working with `KSUUID` v1 data, K-Sortable UUID data(v1). Deprecated - See KSUUID in the sequences documentationfor details.

`bdr.gen_ksuuid`

This function generates a new `KSUUID` v1 value, using the current system time. The return value is of type UUID.

Synopsis

```
bdr.gen_ksuuid()
```

Notes

This function executes only on the local node.

`bdr.uuid_v1_cmp`

This function compares the `KSUUID` v1 values.

It returns 1 if the first value is newer, -1 if the second value is lower, or zero if they are equal.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.uuid_v1_cmp(uuid, uuid)
```

Notes

This function executes only on the local node.

Parameters

- `UUID` — `KSUUID` v1 to compare.

`bdr.extract_timestamp_from_ksuuid`

This function extracts the timestamp component of `KSUUID` v1 or `UUIDv1` values. The return value is of type `timestamptz`.

Synopsis

```
bdr.extract_timestamp_from_ksuuid(uuid)
```

Parameters

- `UUID` — `KSUUID` v1 value to extract timestamp from.

Notes

This function executes on the local node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.15 Autopartition

Autopartition allows you to split tables into several partitions. For more information, see Scaling.

`bdr.autopartition`

The `bdr.autopartition` function configures automatic RANGE partitioning of a table.

Synopsis

```
bdr.autopartition(relation regclass,
        partition_increment
text,
        partition_initial_lowerbound text DEFAULT NULL,
        partition_autocreate_expression text DEFAULT
NULL,
        minimum_advance_partitions integer DEFAULT
2,
        maximum_advance_partitions integer DEFAULT
5,
        data_retention_period interval DEFAULT
NULL,
        managed_locally boolean DEFAULT true,
        enabled boolean DEFAULT on,
        analytics_offload_period interval DEFAULT
NULL,
    drop_after_retention_period boolean DEFAULT true
    );
```

Parameters

- `relation` — Name or Oid of a table.
- `partition_increment` — Interval or increment to next partition creation.
- `partition_initial_lowerbound` — If the table has no partition, then the first partition with this lower bound and `partition_increment` apart upper bound is created.
- `partition_autocreate_expression` — The expression used to detect if it's time to create new partitions.
- `minimum_advance_partitions` — The system attempts to always have at least `minimum_advance_partitions` partitions.
- `maximum_advance_partitions` — Number of partitions to create in a single go after the number of advance partitions falls below `minimum_advance_partitions`.
- `data_retention_period` — Interval until older partitions are dropped, if defined. This value must be greater than `migrate_after_period`.
- `managed_locally` — Whether partitions are managed locally. Setting this to `false` is not recommended.
- `enabled` — Allows activity to be disabled or paused and later resumed or reenabled.
- `analytics_offload_period` — Provides support for partition offloading. Reserved for future use.
- `drop_after_retention_period` — If `false` then partitions are only detached (but not dropped) after the retention period is over.

Examples

Daily partitions, keep data for one month:

```
CREATE TABLE measurement
(
logdate date not null,
peaktemp int,
unitsales int
) PARTITION BY RANGE (logdate);

bdr.autopartition('measurement', '1 day', data_retention_period := '30
days');
```

Create five advance partitions when only two more partitions remain. Each partition can hold 1 billion orders.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
bdr.autopartition('Orders', '1000000000',
        partition_initial_lowerbound := '0',
        minimum_advance_partitions :=
2,
        maximum_advance_partitions :=
5
     );
```

`bdr.drop_autopartition`

Use `bdr.drop_autopartition()` to drop the autopartitioning rule for the given relation. All pending work items for the relation are deleted, and no new work items are created.

```
bdr.drop_autopartition(relation regclass);
```

Parameters

- `relation` — Name or Oid of a table.

`bdr.autopartition_wait_for_partitions`

Partition creation is an asynchronous process. AutoPartition provides a set of functions to wait for the partition to be created, locally or on all nodes.

Use `bdr.autopartition_wait_for_partitions()` to wait for the creation of partitions on the local node. The function takes the partitioned table name and a partition key column value and waits until the partition that holds that value is created.

The function waits only for the partitions to be created locally. It doesn't guarantee that the partitions also exists on the remote nodes.

To wait for the partition to be created on all PGD nodes, use the `bdr.autopartition_wait_for_partitions_on_all_nodes()` function. This function internally checks local as well as all remote nodes and waits until the partition is created everywhere.

Synopsis

```
bdr.autopartition_wait_for_partitions(relation regclass, upperbound
text);
```

Parameters

- `relation` — Name or Oid of a table.
- `upperbound` — Partition key column value.

`bdr.autopartition_wait_for_partitions_on_all_nodes`

Synopsis

```
bdr.autopartition_wait_for_partitions_on_all_nodes(relation regclass, upperbound
text);
```

Parameters

- `relation` — Name or Oid of a table.
- `upperbound` — Partition key column value.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.autopartition_find_partition`

Use the `bdr.autopartition_find_partition()` function to find the partition for the given partition key value. If partition to hold that value doesn't exist, then the function returns NULL. Otherwise Oid of the partition is returned.

Synopsis

```
bdr.autopartition_find_partition(relname regclass, searchkey
text);
```

Parameters

- `relname` — Name of the partitioned table.
- `searchkey` — Partition key value to search.

`bdr.autopartition_enable`

Use `bdr.autopartition_enable` to enable AutoPartitioning on the given table. If AutoPartitioning is already enabled, then no action occurs. See `bdr.autopartition_disable` to disable AutoPartitioning on the given table.

Synopsis

```
bdr.autopartition_enable(relname regclass);
```

Parameters

- `relname` — Name of the relation to enable AutoPartitioning.

`bdr.autopartition_disable`

Use `bdr.autopartition_disable` to disable AutoPartitioning on the given table. If AutoPartitioning is already disabled, then no action occurs.

Synopsis

```
bdr.autopartition_disable(relname regclass);
```

Parameters

- `relname` — Name of the relation to disable AutoPartitioning.

Internal functions

`bdr.autopartition_create_partition`

AutoPartition uses an internal function `bdr.autopartition_create_partition` to create a standalone AutoPartition on the parent table.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.autopartition_create_partition(relname regclass,
                                   partname
name,
                                     lowerb
text,
                                     upperb
text,
                                     nodes oid[]);
```

Parameters

- `relname` — Name or Oid of the parent table to attach to.
- `partname` — Name of the new AutoPartition.
- `lowerb` — Lower bound of the partition.
- `upperb` — Upper bound of the partition.
- `nodes` — List of nodes that the new partition resides on. This parameter is internal to PGD and reserved for future use.

Notes

This is an internal function used by AutoPartition for partition management. We recommend that you don't use the function directly.

`bdr.autopartition_drop_partition`

AutoPartition uses an internal function `bdr.autopartition_drop_partition` to drop a partition that's no longer required, as per the data-retention policy. If the partitioned table was successfully dropped, the function returns `true`.

Synopsis

```
bdr.autopartition_drop_partition(relname regclass)
```

Parameters

- `relname` — The name of the partitioned table to drop.

Notes

This function places a DDL lock on the parent table before using `DROP TABLE` on the chosen partition table. This function is an internal function used by AutoPartition for partition management. We recommend that you don't use the function directly.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.16 Stream triggers reference

> **SeeAlso**
>
> Stream Triggers for an introduction to Stream Triggers.

Both conflict triggers and transform triggers have access to information about rows and metadata by way of the predefined variables provided by the trigger API and additional information functions provided by PGD.

In PL/pgSQL, you can use the predefined variables and functions that follow:

- Row variables
- Row Information functions
  - `bdr.trigger_get_row`
  - `bdr.trigger_get_committs`
  - `bdr.trigger_get_xid`
  - `bdr.trigger_get_type`
  - `bdr.trigger_get_conflict_type`
  - `bdr.trigger_get_origin_node_id`
  - `bdr.ri_fkey_on_del_trigger`

Creating and dropping stream triggers is managed through the manipulation interfaces:

- Manipulation interfaces
  - `bdr.create_conflict_trigger`
  - `bdr.create_transform_trigger`
  - `bdr.drop_trigger`

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.16.1 Stream triggers manipulation interfaces

You can create stream triggers only on tables with `REPLICA IDENTITY FULL` or tables without any columns to which `TOAST` applies.

`bdr.create_conflict_trigger`

This function creates a new conflict trigger.

Synopsis

```
bdr.create_conflict_trigger(trigger_name text,
                            events text[],
                            relation
regclass,
                            function regprocedure,
                            args text[] DEFAULT
'{}')
```

Parameters

- `trigger_name` — Name of the new trigger.
- `events` — Array of events on which to fire this trigger. Valid values are '`INSERT`', '`UPDATE`', and '`DELETE`'.
- `relation` — Relation to fire this trigger for.
- `function` — The function to execute.
- `args` — Optional. Specifies the array of parameters the trigger function receives on execution (contents of `TG_ARGV` variable).

Notes

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the ddl filters configuration.

The function takes a global DML lock on the relation on which the trigger is being created.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

Similar to normal PostgreSQL triggers, the `bdr.create_conflict_trigger` function requires `TRIGGER` privilege on the `relation` and `EXECUTE` privilege on the function. This applies with a `bdr.backwards_compatibility` of 30619 or above. Additional security rules apply in PGD to all triggers including conflict triggers. See Security and roles.

`bdr.create_transform_trigger`

This function creates a transform trigger.

Synopsis

```
bdr.create_transform_trigger(trigger_name text,
                             events text[],
                             relation
regclass,
                             function regprocedure,
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

```
                            args text[] DEFAULT
'{}')
```

Parameters

- `trigger_name` — Name of the new trigger.
- `events` — Array of events on which to fire this trigger. Valid values are '`INSERT`', '`UPDATE`', and '`DELETE`'.
- `relation` — Relation to fire this trigger for.
- `function` — The function to execute.
- `args` — Optional. Specify array of parameters the trigger function receives on execution (contents of `TG_ARGV` variable).

Notes

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the ddl filters configuration.

The function takes a global DML lock on the relation on which the trigger is being created.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

Similarly to normal PostgreSQL triggers, the `bdr.create_transform_trigger` function requires the `TRIGGER` privilege on the `relation` and `EXECUTE` privilege on the function. Additional security rules apply in PGD to all triggers including transform triggers. See Security and roles.

`bdr.drop_trigger`

This function removes an existing stream trigger (both conflict and transform).

Synopsis

```
bdr.drop_trigger(trigger_name text,
                 relation
regclass,
                 ifexists boolean DEFAULT
false)
```

Parameters

- `trigger_name` — Name of an existing trigger.
- `relation` — The relation the trigger is defined for.
- `ifexists` — When set to `true`, this function ignores missing triggers.

Notes

This function uses the same replication mechanism as `DDL` statements. This means that the replication is affected by the ddl filters configuration.

The function takes a global DML lock on the relation on which the trigger is being created.

This function is transactional. You can roll back the effects with the `ROLLBACK` of the transaction. The changes are visible to the current transaction.

Only the owner of the `relation` can execute the `bdr.drop_trigger` function.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.16.2 Stream triggers row functions

`bdr.trigger_get_row`

This function returns the contents of a trigger row specified by an identifier as a `RECORD`. This function returns `NULL` if called inappropriately, that is, called with `SOURCE_NEW` when the operation type (TG_OP) is `DELETE`.

Synopsis

```
bdr.trigger_get_row(row_id text)
```

Parameters

- `row_id` — Identifier of the row. Can be any of `SOURCE_NEW`, `SOURCE_OLD`, and `TARGET`, depending on the trigger type and operation. (See the descriptions of the individual trigger types.)

`bdr.trigger_get_committs`

This function returns the commit timestamp of a trigger row specified by an identifier. If not available because a row is frozen or isn't available, returns `NULL`. Always returns `NULL` for row identifier `SOURCE_OLD`.

Synopsis

```
bdr.trigger_get_committs(row_id text)
```

Parameters

- `row_id` — Identifier of the row. Can be any of `SOURCE_NEW`, `SOURCE_OLD`, and `TARGET`, depending on trigger type and operation. (See the descriptions of the individual trigger types.)

`bdr.trigger_get_xid`

This function returns the local transaction id of a TARGET row specified by an identifier. If not available because a row is frozen or isn't available, returns `NULL`. Always returns `NULL` for `SOURCE_OLD` and `SOURCE_NEW` row identifiers.

Available only for conflict triggers.

Synopsis

```
bdr.trigger_get_xid(row_id text)
```

Parameters

- `row_id` — Identifier of the row. Can be any of `SOURCE_NEW`, `SOURCE_OLD`, and `TARGET`, depending on trigger type and operation. (See the descriptions of the individual trigger types.)

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.trigger_get_type`

This function returns the current trigger type, which can be `CONFLICT` or `TRANSFORM`. Returns null if called outside a stream trigger.

Synopsis

```
bdr.trigger_get_type()
```

`bdr.trigger_get_conflict_type`

This function returns the current conflict type if called inside a conflict trigger. Otherwise, returns `NULL`.

See Conflict types for possible return values of this function.

Synopsis

```
bdr.trigger_get_conflict_type()
```

`bdr.trigger_get_origin_node_id`

This function returns the node id corresponding to the origin for the trigger row_id passed in as argument. If the origin isn't valid (which means the row originated locally), returns the node id of the source or target node, depending on the trigger row argument. Always returns `NULL` for row identifier `SOURCE_OLD`. You can use this function to define conflict triggers to always favor a trusted source node.

Synopsis

```
bdr.trigger_get_origin_node_id(row_id text)
```

Parameters

- `row_id` — Identifier of the row. Can be any of `SOURCE_NEW`, `SOURCE_OLD`, and `TARGET`, depending on trigger type and operation. (See the descriptions of the individual trigger types.)

`bdr.ri_fkey_on_del_trigger`

When called as a BEFORE trigger, this function uses FOREIGN KEY information to avoid FK anomalies.

Synopsis

```
bdr.ri_fkey_on_del_trigger()
```

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.16.3 Stream triggers row variables

`TG_NAME`

Data type name. This variable contains the name of the trigger actually fired. The actual trigger name has a `\_bdrt` or `\_bdrc` suffix (depending on trigger type) compared to the name provided during trigger creation.

`TG_WHEN`

Data type text. This variable says `BEFORE` for both conflict and transform triggers. You can get the stream trigger type by calling the `bdr.trigger_get_type()` information function. See bdr.trigger_get_type.

`TG_LEVEL`

Data type text: a string of `ROW`.

`TG_OP`

Data type text: a string of `INSERT`, `UPDATE`, or `DELETE` identifying the operation for which the trigger was fired.

`TG_RELID`

Data type oid: the object ID of the table that caused the trigger invocation.

`TG_TABLE_NAME`

Data type name: the name of the table that caused the trigger invocation.

`TG_TABLE_SCHEMA`

Data type name: the name of the schema of the table that caused the trigger invocation. For partitioned tables, this is the name of the root table.

`TG_NARGS`

Data type integer: the number of arguments given to the trigger function in the `bdr.create_conflict_trigger()` or `bdr.create_transform_trigger()` statement.

`TG_ARGV[]`

Data type array of text: the arguments from the `bdr.create_conflict_trigger()` or `bdr.create_transform_trigger()` statement. The index counts from 0. Invalid indexes (less than 0 or greater than or equal to `TG_NARGS`) result in a `NULL` value.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.17 Internal catalogs and views

Catalogs and views are listed here in alphabetical order.

`bdr.autopartition_partitions`

An internal catalog table that stores information about the partitions created by the autopartitioning feature.

`bdr.autopartition_partitions` columns

Name	Type	Description
ap_parent_relid	oid	OID for relation
ap_part_relname	name	Name of created relation
ap_part_created_at	timestamp with time zone	Creation timestamp
ap_part_migrated_at	timestamp with time zone	Migration timestamp
ap_part_dropped_at	timestamp with time zone	Timestamp when dropped

`bdr.autopartition_rules`

An internal catalog table that stores information about the autopartitioning rules.

`bdr.autopartition_rules` columns

Name	Type	Description
ap_partition_relid	oid	
ap_partition_relname	name	
ap_partition_schemaname	name	
ap_partition_increment_kind	"char"	
ap_secondary_tablespace	oid	
ap_maximum_advance_partitions	integer	
ap_is_autoscaled	boolean	
ap_latest_partitions	integer	
ap_enabled	boolean	
ap_migrate_after_period	interval	
ap_data_retention_period	interval	
ap_last_triggered	timestamp with time zone	
ap_partition_increment_value	text	
ap_partition_autocreate_expr	text	
ap_partition_initial_lowerbound	text	
ap_partition_last_upperbound	text	
ap_is_local	boolean	
ap_partition_min_upperbound	text	

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.ddl_epoch`

An internal catalog table holding state per DDL epoch.

`bdr.ddl_epoch` columns

Name	Type	Description
ddl_epoch	int8	Monotonically increasing epoch number
origin_node_id	oid	Internal node ID of the node that requested creation of this epoch
epoch_consume_timeout	timestamptz	Timeout of this epoch
epoch_consumed	boolean	Switches to true as soon as the local node has fully processed the epoch
epoch_consumed_lsn	boolean	LSN at which the local node has processed the epoch

`bdr.event_history`

Internal catalog table that tracks cluster membership events for a given PGD node. Specifically, it tracks:

- Node joins (to the cluster)
- Raft state changes (that is, whenever the node changes its role in the consensus protocol - leader, follower, or candidate to leader); seeMonitoring Raft consensus
- Whenever a worker has errored out (see bdr.workers and Monitoring PGD replication workers)

`bdr.event_history` columns

Name	Type	Description
event_node_id	oid	ID of the node to which the event refers
event_type	int	Type of the event (a node, raft, or worker-related event)
event_sub_type	int	Subtype of the event, that is, if it's a join, a state change, or an error
event_source	text	Name of the worker process where the event was sourced
event_time	timestamptz	Timestamp at which the event occurred
event_text	text	Textual representation of the event (for example, the error of the worker)
event_detail	text	A more detailed description of the event (for now, only relevant for worker errors)

`bdr.event_summary`

A view of the `bdr.event_history` catalog that displays the information in a more human-friendly format. Specifically, it displays the event types and subtypes as textual representations rather than integers.

`bdr.local_leader_change`

This is a local cache of the recent portion of leader change history. It has the same fields as `bdr.leader`, except that it is an ordered set of (node_group_id, leader_kind, generation) instead of a map tracking merely the current version.

`bdr.node_config`

An internal catalog table with per-node configuration options.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.node_config` columns

Name	Type	Description
node_id	oid	Node ID
node_route_priority	int	Priority assigned to this node
node_route_fence	boolean	Switch to fence this node
node_route_writes	boolean	Switch to allow writes
node_route_reads	boolean	Switch to allow reads
node_route_dsn	text	Interface of this node

`bdr.node_config_summary`

A view of the `bdr.node_config` catalog that displays the information in a more human-readable format.

`bdr.node_config_summary` columns

Name	Type	Description
node_name	text	The name of this node
node_id	oid	Node ID
node_route_priority	int	Priority assigned to this node
node_route_fence	boolean	Switch to fence this node
node_route_writes	boolean	Switch to allow writes
node_route_reads	boolean	Switch to allow reads
node_route_dsn	text	Interface of this node
effective_route_dsn	text	Full DSN of this node

`bdr.node_group_config`

An internal catalog table with per-node group configuration options.

`bdr.node_group_config` columns

Name	Type	Description
node_group_id	oid	Node group ID
route_writer_max_lag	bigint	Maximum write lag accepted
route_reader_max_lag	bigint	Maximum read lag accepted
route_writer_wait_flush	boolean	Switch if we need to wait for the flush

`bdr.node_group_routing_config_summary`

Per-node-group routing configuration options.

`bdr.node_group_routing_config_summary` columns

Name	Type	Description
node_group_name	name	Node group name
location	name	Node group location
enable_proxy_routing	boolean	Group proxy routing enabled?

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
node_group_type	text	Node group type (one of "global", "data", or "subscriber-only")
route_writer_max_lag	bigint	Maximum write lag accepted
route_reader_max_lag	bigint	Maximum read lag accepted
route_writer_wait_flush	boolean	Wait for flush

`bdr.node_group_routing_info`

An internal catalog table holding current routing information for a proxy.

`bdr.node_group_routing_info` columns

Name	Type	Description
node_group_id	oid	Node group ID.
write_node_id	oid	Current write node.
prev_write_node_id	oid	Previous write node.
read_node_ids	oid[]	List of read-only nodes IDs.
record_version	bigint	Record version. Incremented by 1 on every material change to the routing record.
record_ts	timestamptz	Timestamp of last update to record_version.
write_leader_version	bigint	Write leader version. Copied from record_version every time write_node_id is changed.
write_leader_ts	timestamptz	Write leader timestamp. Copied from record_ts every time write_node_id is changed.
read_nodes_version	bigint	Read nodes version. Copied from record_version every time read_node_ids list is changed.
read_nodes_ts	timestamptz	Read nodes timestamp. Copied from record_tw every time read_node_ids list is changed.

`bdr.node_group_routing_summary`

A view of `bdr.node_group_routing_info` catalog that shows the information in more friendly way.

`bdr.node_group_routing_summary` columns

Name	Type	Description
node_group_name	name	Node group name
write_lead	name	Current write lead
previous_write_lead	name	Previous write lead
read_nodes	name[]	Current read-only nodes

`bdr.node_peer_progress_mapping`

A internal catalog used to track the relative progress of each node in the cluster against each other node to assist with group slot movement.

This is an internal relation used by PGD to assist with node progress tracking. Its contents are primarily for system use and should not be used as a standalone reference to infer the exact state or health of replication progress.

`bdr.node_peer_progress_mapping` columns

Name	Type	Description
peer_node_id	oid	OID of the remote peer node for which this progress information was reported.
local_lsn	pg_lsn	LSN on the local node at the time the progress was recorded.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
remote_lsn	pg_lsn	LSN on the originating node at the time the progress was reported.

`bdr.node_routing_config_summary`

A friendly view of the per-node routing configuration options. Shows the node name rather than the oid and shorter field names.

`bdr.node_routing_config_summary` columns

Name	Type	Description
node_name	name	Node name
route_priority	int	Priority assigned to this node
route_fence	boolean	Switch to fence this node
route_writes	boolean	Switch to allow writes
route_reads	boolean	Switch to allow reads
route_dsn	text	Interface of this node

`bdr.proxy_config`

An internal catalog table holding proxy specific configurations.

`bdr.proxy_config` columns

Name	Type	Description
proxy_name	name	Name of the proxy
node_group_id	oid	Node group ID that this proxy uses
listen_port	int	Port that the proxy uses for read-write connections (setting to 0 disables port)
max_client_conn	int	Number of maximum read-write client connections that the proxy accepts
max_server_conn	int	Number of maximum read-write connections that the server accepts
server_conn_timeout	interval	Timeout for the read-write server connections
server_conn_keepalive	interval	Interval between the server connection keep-alive
fallback_group_timeout	interval	Timeout needed for the fallback
fallback_group_ids	oid[]	List of group IDs to use for the fallback
listen_addrs	text[]	Listen address
read_listen_port	int	Port that the proxy uses for read-only connections (setting to 0 disables port)
read_max_client_conn	int	Number of maximum read-only client connections that the proxy accepts
read_max_server_conn	int	Number of maximum read-only connections that the server accepts
read_server_conn_timeout	interval	Timeout for the server read-only connections
read_server_conn_keepalive	interval	Interval between the server read-only connection keep-alive
read_listen_addrs	text[]	Listen address for read-only connections
read_consensus_grace_period	interval	Duration for which proxy continues to route even upon loss of consensus

`bdr.proxy_config_summary`

A friendly view of per-proxy, instance-specific configuration options.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.proxy_config_summary` columns

Name	Type	Description
proxy_name	name	Name of the proxy
node_group_name	name	Node group name that this proxy uses
listen_port	int	Port that the proxy uses for read-write connections (setting to -1 disables port)
max_client_conn	int	Number of maximum read-write client connections that the proxy accepts
max_server_conn	int	Number of maximum read-write connections that the server accepts
server_conn_timeout	interval	Timeout for the read-write server connections
server_conn_keepalive	interval	Interval between the server connection keep-alive
node_group_enable_proxy_routing	boolean	Does the group the proxy is in enable proxy routing?
node_group_location	name	The group's location value
fallback_group_timeout	interval	Timeout needed for the fallback
fallback_group_ids	oid[]	List of group IDs to use for the fallback
listen_addrs	text[]	Listen address
read_listen_port	int	Port that the proxy uses for read-only connections (setting to -1 disables port)
read_max_client_conn	int	Number of maximum read-only client connections that the proxy accepts
read_max_server_conn	int	Number of maximum read-only connections that the server accepts
read_server_conn_timeout	interval	Timeout for the server read-only connections
read_server_conn_keepalive	interval	Interval between the server read-only connection keep-alive
read_listen_addrs	text[]	Listen address for read-only connections
read_consensus_grace_period	interval	Duration for which proxy continues to route even upon loss of consensus

`bdr.sequence_kind`

An internal state table storing the type of each non-local sequence. We recommend the view `bdr.sequences` for diagnostic purposes.

`bdr.sequence_kind` columns

Name	Type	Description
seqid	oid	Internal OID of the sequence
seqkind	char	Internal sequence kind (`l` =local, `t` =timeshard, `s` =snowflakeid, `g` =galloc)

`bdr.sync_node_requests`

An internal state table storing the state of node synchronization requests. The view `bdr.sync_node_requests_summary` provides a human-readable representation of this table.

`bdr.sync_node_requests` columns

Name	Type	Description
sn_origin_node_id	oid	Unavailable node with changes to be synchronized
sn_target_node_id	oid	Node with the origin node's changes
sn_source_node_id	oid	Target node for the sync request
sn_sync_start_lsn	pg_lsn	Start LSN of the sync request
sn_sync_start_ts	timestamptz	Start timestamp of the sync request
sn_sync_end_lsn	pg_lsn	End LSN of the sync request
sn_sync_end_ts	timestamptz	End timestamp of the sync request

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Name	Type	Description
sn_sync_status	text	Status of the sync request

`bdr.sync_node_requests_summary`

A view providing a human-readable version of the underlying `bdr.sync_node_requests` table.

`bdr.sync_node_requests_summary` columns

Name	Type	Description
origin	text	Unavailable node with changes to be synchronized
source	text	Node with the origin node's changes
target	text	Target node for the sync request
sync_start_lsn	pg_lsn	Start LSN of the sync request
sync_start_ts	timestamptz	Start timestamp of the sync request
sync_end_lsn	pg_lsn	End LSN of the sync request
sync_end_ts	timestamptz	End timestamp of the sync request
sync_status	text	Status of the sync request

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.18 Internal system functions

The following are internal system functions. Many are used when creating various views. We recommend that you do not use the functions directly but instead use the views that they serve.

General internal functions

`bdr.bdr_get_commit_decisions`

Convenience routine to inspect shared memory state.

Synopsis

```
bdr.bdr_get_commit_decisions(dbid OID,
            origin_node_id
OID,
            origin_xid xid,
            local_xid xid,
            decision
"char",
            decision_ts
timestamptz,
            is_camo boolean)
```

`bdr.bdr_track_commit_decision`

Save the transaction commit status in the shared memory hash table. This function is used by the upgrade scripts to transfer commit decisions saved in bdr.commit_decisions catalog to the shared memory hash table. The transaction commit status will also be logged to the WAL and hence can be reloaded from WAL.

Synopsis

```
bdr.bdr_track_commit_decision(OID, xid, xid, "char", timestamptz, boolean);
```

`bdr.consensus_kv_fetch`

Fetch value from the consistent KV Store in JSON format.

Synopsis

```
bdr.consensus_kv_fetch(IN key text) RETURNS jsonb
```

Parameters

Parameter	Description
`key`	An arbitrary key to fetch.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Notes

This function is an internal function, mainly used by HARP.

> **Warning**
>
> Don't use this function in user applications.

`bdr.consensus_kv_store`

Stores value in the consistent KV Store.

Returns the timestamp of the value expiration time. This function depends on `ttl`. If `ttl` is `NULL`, then this function returns `infinity`. If the value was deleted, it returns `-infinity`.

Synopsis

```
bdr.consensus_kv_store(key text, value
jsonb,
        prev_value jsonb DEFAULT NULL, ttl int DEFAULT
NULL)
```

Parameters

Parameter	Description
`key`	An arbitrary unique key to insert, update, or delete.
`value`	JSON value to store. If NULL, any existing record is deleted.
`prev_value`	If set, the write operation is done only if the current value is equal to `prev_value`.
`ttl`	Time-to-live of the new value, in milliseconds.

Notes

This is an internal function, mainly used by HARP.

> **Warning**
>
> Don't use this function in user applications.

`bdr.decode_message_payload`

PGD message payload function that decodes the payloads of consensus messages to a more human-readable output. Used primarily by the `bdr.global_consensus_journal_details` debug view.

`bdr.decode_message_response_payload`

PGD message payload function that decodes the payloads of responses to consensus messages to a more human-readable output. Used primarily by the `bdr.global_consensus_journal_details` debug view.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.difference_fix_origin_create`

Creates a replication origin with a given name passed as an argument but adding a `bdr_` prefix. Returns the internal id of the origin. This function has the same functionality as `pg_replication_origin_create()` except this function requires bdr_superuser rather than postgres superuser permissions.

`bdr.difference_fix_session_reset`

Marks the current session as not replaying from any origin, essentially resetting the effect of `bdr.difference_fix_session_setup()`. It returns void. This function has the same functionality as `pg_replication_origin_session_reset()` except this function requires bdr_superuser rather than postgres superuser permissions.

Synopsis

```
bdr.difference_fix_session_reset()
```

`bdr.difference_fix_session_setup`

Marks the current session as replaying from the current origin. The function uses the pre-created `bdr_local_only_origin` local replication origin implicitly for the session. It allows replay progress to be reported and returns void. This function has the same functionality as `pg_replication_origin_session_setup()` except that this function requires bdr_superuser rather than postgres superuser permissions. The earlier form of the function, `bdr.difference_fix_session_setup(text)`, was deprecated and will be removed in a future release.

Synopsis

```
bdr.difference_fix_session_setup()
```

`bdr.difference_fix_xact_set_avoid_conflict`

Marks the current transaction as replaying a transaction that committed at LSN '0/0' and timestamp '2000-01-01'. This function has the same functionality as `pg_replication_origin_xact_setup('0/0', '2000-01-01')` except this function requires bdr_superuser rather than postgres superuser permissions.

Synopsis

```
bdr.difference_fix_xact_set_avoid_conflict()
```

`bdr.drop_node`

Drops a node's metadata.

After a node has been `PARTED` its metadata remains present in the cluster's nodes. For example, the node will remain in the `bdr.node_sumary` results, marked as `PARTED`, until the node is dropped.

Calling `bdr.drop_node('some node', force := true)` can be necessary and appropriate when a node becomes stuck while parting. Note that it skips past syncing any data out of the node being dropped, if there is any data on that node that still needs to be synced out. If a node stuck parting has already been reimaged or deleted, there is no harm in calling `bdr.drop_node` on it. Note that this must be called for this stuck node on all nodes in the cluster so they all have a consistent view that the node has been dropped.

This function removes the metadata for a given node from the local database. The node can be either:

- The local node, in which case it removes all the node metadata, including information about remote nodes.
- A remote node, in which case it removes only metadata for that specific node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

> **When to use `bdr.drop_node()`**
>
> It is not necessary to use `bdr.drop_node()` to drop node metadata just to reuse node names. PGD 5 and later can reuse existing node names as long as the node name in question belongs to a node in a `PARTED` state. Instead of dropping the node, use `bdr.part_node()` to remove the original node and place it in a `PARTED`.
>
> Use of this internal function is limited to:
>
> - When you're instructed to by EDB Technical Support.
> - Where you're specifically instructed to in the documentation.
>
> Use `bdr.part_node` to remove a node from a PGD group. That function sets the node to `PARTED` state and enables reuse of the node name.

Synopsis

```
bdr.drop_node(node_name text, cascade boolean DEFAULT false, force boolean DEFAULT false)
```

Parameters

Parameter	Description
`node_name`	Name of an existing node.
`cascade`	Deprecated, will be removed in a future release.
`force`	Circumvents all sanity checks and forces the removal of all metadata for the given PGD node despite a possible danger of causing inconsistencies. Only Technical Support uses a forced node drop in case of emergencies related to parting.

Notes

Before you run this function, part the node using `bdr.part_node()`.

This function removes metadata for a given node from the local database. The node can be the local node, in which case all the node metadata is removed, including information about remote nodes. Or it can be the remote node, in which case only metadata for that specific node is removed.

> **Note**
>
> PGD can have a maximum of 1024 node records (both ACTIVE and PARTED) at one time because each node has a unique sequence number assigned to it, for use by snowflakeid and timeshard sequences. PARTED nodes aren't automatically cleaned up. If this becomes a problem, you can use this function to remove those records.

`bdr.get_global_locks`

Shows information about global locks held on the local node.

Used to implement the `bdr.global_locks` view to provide a more detailed overview of the locks.

`bdr.get_node_conflict_resolvers`

Displays a text string of all the conflict resolvers on the local node.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.get_slot_flush_timestamp`

Retrieves the timestamp of the last flush position confirmation for a given replication slot.

Used internally to implement the `bdr.node_slots` view.

`bdr.internal_alter_sequence_set_kind`

A function previously used internally for replication of the various function calls. No longer used by the current version of PGD. Exists only for backward compatibility during rolling upgrades.

`bdr.internal_replication_set_add_table`

A function previously used internally for replication of the various function calls. No longer used by the current version of PGD. Exists only for backward compatibility during rolling upgrades.

`bdr.internal_replication_set_remove_table`

A function previously used internally for replication of the various function calls. No longer used by the current version of PGD. Exists only for backward compatibility during rolling upgrades.

`bdr.internal_submit_join_request`

Submits a consensus request for joining a new node.

Needed by the PGD group reconfiguration internal mechanisms.

`bdr.isolation_test_session_is_blocked`

A helper function, extending (and actually invoking) the original `pg_isolation_test_session_is_blocked` with an added check for blocks on global locks.

Used for isolation/concurrency tests.

`bdr.local_node_info`

Displays information for the local node needed by the PGD group reconfiguration internal mechanisms.

The view `bdr.local_node_summary` provides similar information useful for user consumption.

`bdr.msgb_connect`

Connects to the connection pooler of another node. Used by the consensus protocol.

`bdr.msgb_deliver_message`

Sends messages to another node's connection pooler. Used by the consensus protocol.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.node_catchup_state_name`

Converts catchup state code in name.

Synopsis

```
bdr.node_catchup_state_name(catchup_state oid);
```

Parameters

Parameter	Description
`catchup_state`	Oid code of the catchup state.

`bdr.node_kind_name`

Returns human-friendly name of the node kind (data|standby|witness|subscriber-only).

`bdr.peer_state_name`

Transforms the node state (`node_state`) into a textual representation. Used mainly to implement the `bdr.node_summary` view.

`bdr.pg_xact_origin`

Returns the origin id of a given transaction.

Synopsis

```
bdr.pg_xact_origin(xmin xid)
```

Parameters

Parameter	Description
`xid`	Transaction id whose origin is returned.

`bdr.request_replay_progress_update`

Requests the immediate writing of a 'replay progress update' Raft message. Used mainly for test purposes but can also be used to test if the consensus mechanism is working.

`bdr.reset_relation_stats`

Returns a Boolean result after resetting the relation stats, as viewed by `bdr.stat_relation` .

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.reset_subscription_stats`

Returns a Boolean result after resetting the statistics created by subscriptions, as viewed by `bdr.stat_subscription`.

`bdr.resynchronize_table_from_node`

Resynchronizes the relation from a remote node.

Synopsis

```
bdr.resynchronize_table_from_node(node_name name, relation
regclass)
```

Parameters

Parameter	Description
`node_name`	The node from which to copy or resync the relation data.
`relation`	The relation to copy from the remote node.

Notes

This function acquires a global DML lock on the relation, truncates the relation locally, and copies data into it from the remote node.

The relation must exist on both nodes with the same name and definition.

The following are supported:

- Resynchronizing partitioned tables with identical partition definitions
- Resynchronizing partitioned table to nonpartitioned table and vice versa
- Resynchronizing referenced tables by temporarily dropping and re-creating foreign key constraints

After running the function on a referenced table, if the referenced column data no longer matches the referencing column values, the function throws an error. After resynchronizing the referencing table data, rerun the function.

Furthermore, it supports resynchronization of tables with generated columns by computing the generated column values locally after copying the data from remote node.

Currently, row_filters are ignored by this function.

The `bdr.resynchronize_table_from_node` function can be executed only by the owner of the table, provided the owner has bdr_superuser privileges.

`bdr.seq_currval`

Part of the internal implementation of global sequence manipulation.

Invoked automatically when `currval()` is called on a galloc or snowflakeid sequence.

`bdr.seq_lastval`

Part of the internal implementation of global sequence manipulation.

Invoked automatically when `lastval()` is called on a galloc or snowflakeid sequence.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.seq_nextval`

Part of the internal implementation of global sequence increments.

Invoked automatically when `nextval()` is called on a galloc or snowflakeid sequence

`bdr.show_subscription_status`

Retrieves information about the subscription status. Used mainly to implement the `bdr.subscription_summary` view.

`bdr.show_workers`

Information related to the bdr workers.

Synopsis

```
bdr.show_workers(
    worker_pid int,
    worker_role
int,
    worker_role_name
text,
    worker_subid oid)
```

`bdr.show_writers`

Function used in the `bdr.writers` view.

`bdr.sync_status_name`

Converts sync state code into a textual representation. Used mainly to implement the `bdr.sync_node_requests_summary` view.

Synopsis

```
bdr.sync_status_name(sync_state oid)
```

Parameters

Parameter	Description
`sync_state`	Oid code of the sync state.

Task manager functions

`bdr.taskmgr_set_leader`

Requests the given `node` to be the task manager leader node. The leader node is responsible for creating new tasks. (Currently only autopartition makes use of this facility.) A witness node, a logical standby, or a subscriber-only node can't become a leader. Such requests will fail with an error.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

Synopsis

```
bdr.taskmgr_set_leader(node name, wait_for_completion boolean DEFAULT
true);
```

`bdr.taskmgr_get_last_completed_workitem`

Return the `id` of the last workitem successfully completed on all nodes in the cluster.

Synopsis

```
bdr.taskmgr_get_last_completed_workitem();
```

`bdr.taskmgr_work_queue_check_status`

Lets you see the status of the background workers that are doing their job to generate and finish the tasks.

The status can be seen through these views:

- `bdr.taskmgr_work_queue_local_status`
- `bdr.taskmgr_work_queue_global_status`

Synopsis

```
bdr.taskmgr_work_queue_check_status(workid
bigint
                          local boolean DEFAULT false);
```

Parameters

Parameter	Description
`workid`	The key of the task.
`local`	Check the local status only.

Notes

Taskmgr workers are always running in the background, even before the `bdr.autopartition` function is called for the first time. If an invalid `workid` is used, the function returns `unknown`. `In-progress` is the typical status.

`bdr.pglogical_proto_version_ranges`

Internal function for diagnostic use only.

`bdr.get_min_required_replication_slots`

Returns the minimum value needed for `max_replication_slots` so a node join can complete without exhausting available slots. The estimate reserves headroom for the temporary catch-up subscription that briefly coexists with the steady-state subscriptions during a join. PGD-CLI uses this function internally, but you can also run it directly when sizing a cluster.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

`bdr.get_min_required_worker_processes`

Internal function intended for use by PGD-CLI.

`bdr.stat_get_activity`

Internal function underlying view `bdr.stat_activity`. Do not use directly. Use the `bdr.stat_activity` view instead.

`bdr.worker_role_id_name`

Internal helper function used when generating view `bdr.worker_tasks`. Do not use directly. Use the `bdr.worker_tasks` view instead.

`bdr.lag_history`

Internal function used when generating view `bdr.node_replication_rates`. Do not use directly. Use the `bdr.node_replication_rates` view instead.

`bdr.get_raft_instance_by_nodegroup`

Internal function used when generating view `bdr.group_raft_details`. Do not use directly. Use the `bdr.group_raft_details` view instead.

`bdr.monitor_camo_on_all_nodes`

Internal function used when generating view `bdr.group_camo_details`. Do not use directly. Use the `bdr.group_camo_details` view instead.

`bdr.monitor_raft_details_on_all_nodes`

Internal function used when generating view `bdr.group_raft_details`. Do not use directly. Use the `bdr.group_raft_details` view instead.

`bdr.monitor_replslots_details_on_all_nodes`

Internal function used when generating view `bdr.group_replslots_details`. Do not use directly. Use the `bdr.group_replslots_details` view instead.

`bdr.monitor_subscription_details_on_all_nodes`

Internal function used when generating view `bdr.group_subscription_summary`. Do not use directly. Use the `bdr.group_subscription_summary` view instead.

`bdr.monitor_version_details_on_all_nodes`

Internal function used when generating view `bdr.group_versions_details`. Do not use directly. Use the `bdr.group_versions_details` view instead.

`bdr.node_group_member_info`

Internal function used when generating view `bdr.group_raft_details`. Do not use directly. Use the `bdr.group_raft_details` view instead.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.

36.19 Column-level conflict functions

`bdr.column_timestamps_create`

This function creates column-level conflict resolution. It's called within `column_timestamp_enable`.

Synopsis

```
bdr.column_timestamps_create(p_source cstring, p_timestamp
timestampstz)
```

Parameters

- `p_source` — The two options are `current` or `commit`.
- `p_timestamp` — Timestamp depends on the source chosen. If `commit`, then `TIMESTAMP_SOURCE_COMMIT`. If `current`, then `TIMESTAMP_SOURCE_CURRENT`.

Copyright © 2009 - 2026 EnterpriseDB Corporation. All rights reserved.